

# SUSE<sup>®</sup> Linux Enterprise Desktop 10

SP 1

www.novell.com

March 16, 2007

QUICK START

## Welcome to SUSE Linux Enterprise Desktop

Use the following topics to install a new version of SUSE<sup>®</sup> Linux<sup>\*</sup> Enterprise Desktop 10 SP1 or update a SUSE Linux Enterprise Desktop 10 system to SUSE Linux Enterprise Desktop 10 SP1.

- ◆ "System Requirements" on page 1
- ◆ "Installing SUSE Linux Enterprise Desktop" on page 1
- ◆ "Updating SUSE Linux Enterprise Desktop" on page 6

For more detailed installation instructions and deployment strategies, see the [SUSE Linux Enterprise Desktop Deployment Guide \(http://www.novell.com/documentation/sled10/pdfdoc/sled10\\_deployment/sled10\\_deployment.pdf\)](http://www.novell.com/documentation/sled10/pdfdoc/sled10_deployment/sled10_deployment.pdf).

### SYSTEM REQUIREMENTS

- Personal computer with a Pentium<sup>\*</sup> III 500 MHz or higher processor (Pentium 4 2.4 GHz or higher or any AMD64 for Intel<sup>\*</sup> EM64T processor recommended)
- 256 MB physical RAM (512 MB recommended)
- 800 MB available disk space (2.5 GB recommended)
- 800 x 600 display resolution (1024 x 768 or higher recommended)

### INSTALLING SUSE LINUX ENTERPRISE DESKTOP

Use these instructions if there is no existing Linux system on your machine or if you want to replace an existing Linux system. See "Updating SUSE Linux Enterprise Desktop" on page 6 for information on updating a SLED 10 system to SLED 10 SP1.

- 1 Insert the SUSE Linux Enterprise Desktop SP1 CD 1 or DVD into the drive, then reboot the computer to start the installation program.
- 2 Select *Installation* on the boot screen, then press Enter.

**Novell**<sup>®</sup>

This loads the SUSE Linux Enterprise Desktop installation program and starts the installation in normal mode. You can also select from the following options:

- ◆ **Boot from Hard Disk:** Boots the system already installed on the hard drive (the system that is normally booted when the machine is started).
- ◆ **Installation—ACPI Disabled:** If the normal installation fails, it could be because the system hardware doesn't support the Advanced Configuration and Power Interface (ACPI). If this seems to be the case, use this option to install without ACPI support.
- ◆ **Installation—Local APIC Disabled:** If the normal installation fails, it could be because the system hardware doesn't support the local Advanced Programmable Interrupt Controller (APIC). If this seems to be the case, use this option to install without local APIC support.
- ◆ **Installation—Safe Settings:** Boots the system with the DMA mode (for CD-ROM drives) and any interfering power management functions disabled. You can also use the command line to enter or change kernel parameters.
- ◆ **Rescue System:** If you are unable to boot into your installed Linux system, you can boot the computer from the CD using this option. This starts a minimal Linux system without a graphical user interface, which lets you access disk partitions for troubleshooting and repairing the installed system.
- ◆ **Memory Test:** Tests your system RAM by means of repeated read and write cycles. This is done in an endless loop because memory corruption often shows up sporadically and many read and write cycles might be necessary to detect it. If you suspect that your RAM is defective, start this test and let it run for several hours. If no errors are found after a long period of time, you can assume that the memory is intact. End the test by rebooting the system.

**3** Select the language to be used during the installation and for the installed system, then click *Next*.

**4** Read the License Agreement, click *Yes, I Agree to the License Agreement*, then click *Next*.

**5** Select *New Installation*, then click *Next*:

**6** Select the clock and time zone to use in your system, then click *Next*.

**7** Use the Installation Settings screen to view the hardware detected and to view a number of proposed installation and partitioning options, then select your desired options.

The *Overview* tab contains options that sometimes need manual intervention (in most common installation situations). The *Expert* tab contains special options, described below.

**IMPORTANT:** If you do not make any changes to the Software selections, GNOME is installed as the default desktop environment. To install KDE, click *Software* and select *KDE*. Depending on your available disk space, you can choose to install both the GNOME and KDE desktops.

After configuring any of the items presented in these dialogs, you are always returned to the Installation Settings screen, which is updated accordingly.

- ◆ **System:** Detects system hardware and lets you save the results to a floppy or file.
- ◆ **Keyboard Layout:** Lets you change the previously selected keyboard layout. By default, the layout corresponds to the selected language.
- ◆ **Partitioning:** Lets you customize the partitioning. In most cases, SUSE Linux Enterprise Desktop proposes a reasonable partitioning scheme that can be accepted without change.

For more information on partitioning options, see “Section 3.7.1: Partitioning” in the *SUSE Linux Enterprise Desktop Deployment Guide* ([http://www.novell.com/documentation/sled10/pdfdoc/sled10\\_deployment/sled10\\_deployment.pdf](http://www.novell.com/documentation/sled10/pdfdoc/sled10_deployment/sled10_deployment.pdf)).

- ◆ **Add-On Products:** Use this option to install additional products from a separate media source. You can select various types of product media such as CD, DVD, or local directory. You can also work directly with .ISO files (select *Local Directory > ISO Image*).
- ◆ **Software:** SUSE Linux Enterprise Desktop offers several types of software packages with various installation scopes. Use this option to change the selected desktop environment and to add or remove packages and filters.
- ◆ **Booting:** During the installation, SUSE Linux Enterprise Desktop proposes a boot configuration for your system. You should normally leave these setting unchanged, but you can use this option if you need a custom setup.

You can configure the boot mechanism to rely on a special boot floppy. Although this means that the boot floppy must be in the drive when booting, it leaves an existing boot mechanism untouched. This is usually unnecessary because YaST can configure the boot loader to also boot existing operating systems.

You can also use the boot configuration to change the location of the boot mechanism on the hard disk.

For more information, see “Section 17.3: Configuring the Boot Loader with YaST” in the *SUSE Linux Enterprise Desktop Deployment Guide* ([http://www.novell.com/documentation/sled10/pdfdoc/sled10\\_deployment/sled10\\_deployment.pdf](http://www.novell.com/documentation/sled10/pdfdoc/sled10_deployment/sled10_deployment.pdf)).

- ◆ **Time Zone:** Lets you select a time zone. You can also set the hardware clock to Local Time or UTC. If you set the hardware clock to UTC, your system can rely on SUSE Linux Enterprise Desktop to switch between standard time and daylight saving time automatically. Set the clock to Local Time if you are dual booting.
- ◆ **Language:** Lets you change the language you selected in [Step 3 on page 2](#). You can also change the language when you log in.

- ◆ **Default Runlevel:** Lets you define how the system is started after booting. Use the default runlevel 5: Full Multiuser with Network and xdm (you will be prompted to log in directly under a graphical interface). Do not change the runlevel unless instructed to do so by your system administrator.

**8** Click *Accept* to accept any license agreements.

If you made changes to the default Software selections in [Step 7](#), you might also have to click *Continue* to resolve software dependencies.

**9** When you are finished configuring the installation settings, click *Accept*.

**10** Click *Install* to begin the installation.

After completing the basic system setup and the installation of all selected software packages, the SUSE Linux Enterprise Desktop installation boots into the new Linux system, after which you can create users, configure the hardware, and set up system services.

If you are installing from CD, leave CD 1 in your CD-ROM drive during the reboot and do not select any installation options. When the reboot is finished, the installation continues and you are prompted to insert the remaining CDs.

**11** Type a password for the system administrator account (called the `root` user, or `root`), then click *Next*.

Unlike regular users who might or might not have permission to do certain things on the system, `root` has unlimited power to do anything, including change the system configuration, install programs, set up new hardware, and change user passwords. The `root` account should be used only for system administration, maintenance, and repair. Logging in as `root` for daily work can be risky, because a single mistake could lead to the irretrievable loss of system files.

You should never forget the `root` password. After you enter it here, the password cannot be retrieved. It can only be reset with administrative assistance.

**12** Enter a name for this computer and the DNS domain that it belongs to, then click *Next*.

**13** In the Network Configuration screen, view or change the network connections of your system, then click *Next*.

If you have network devices (for example, network or wireless cards, a DSL connection, ISDN adapter, or modem), it is a good idea to configure them now, because an Internet connection allows SUSE Linux Enterprise Desktop to retrieve any available updates and include them in the installation.

To skip the network configuration, click *Skip Configuration > Next*.

**14** To test your Internet connection, click *Yes, Test Connection to the Internet*, then click *Next*.

This option also checks for the latest SUSE Linux Enterprise Desktop release notes. If you don't want to test the connection at this point (or check for updated release notes), click *No, Skip This Test*, click *Next*, then continue with [Step 17](#).

**15** On the Running Internet Connection Test screen, view the results of the test, then click *Next* to continue.

**16** On the Novell Customer Center Configuration screen, click *Configure Now > Next > Continue* to enable your system for online updates.

Click *Configure Later > Next* to skip this step and continue the installation. You can configure this option after the product has been installed.

**17** In the User Authentication Method screen, select *Local (/etc/passwd)*, unless instructed otherwise by your system administrator, then click *Next*.

**18** To create your user account, type your first and last name in the *User's Full Name* field, a username in the *Username* field, and a password (as recommended by your system administrator) in the *Password* field.

For security reasons, your password should be at least eight characters long and should contain both uppercase and lowercase letters and numbers. The maximum length for passwords is 72 characters, and passwords are case sensitive.

**19** Click *Next* to complete the User Authentication setup and start the system configuration.

**20** After the system configuration has completed, view the Release Notes, then click *Next*.

**21** Use the Hardware Configuration screen to view or configure your graphics card and other hardware devices, then click *Next*.

Click a component to start its configuration. For the most part, the SUSE Linux Enterprise Desktop installation detects and configures the devices automatically.

If you prefer not to perform this action right now, click *Skip Configuration > Next*. You can configure these items later, but we recommend that you configure the graphics card now. Although the display settings autoconfigured by SUSE Linux Enterprise Desktop should be generally acceptable, you might have strong preferences as far as resolution, color depth, and other graphics features are concerned. For more information, see "Section 7.13: SaX2" in the [SUSE Linux Enterprise Desktop Deployment Guide \(http://www.novell.com/documentation/sled10/pdfdoc/sled10\\_deployment/sled10\\_deployment.pdf\)](http://www.novell.com/documentation/sled10/pdfdoc/sled10_deployment/sled10_deployment.pdf).

**22** On the Installation Completed screen, click *Finish* to close the SUSE Linux Enterprise Desktop installation and continue to the login screen.

**23** Type your username in the *Username* field, then press Enter.

**24** Type your password in the *Password* field, then press Enter.

## UPDATING SUSE LINUX ENTERPRISE DESKTOP

Use these instructions to update a SUSE Linux Enterprise Desktop 10 system to SUSE Linux Enterprise Desktop 10 SP1. Configuration settings from your existing system are preserved whenever possible.

- 1 Insert the SUSE Linux Enterprise Desktop 10 SP1 CD 1 or DVD into the drive, then reboot the computer to start the installation program.
- 2 Select *Installation* on the boot screen, then press Enter.
- 3 Select the language to be used during the installation and for the installed system, then click *Next*.
- 4 Read the License Agreement, click *Yes, I Agree to the License Agreement*, then click *Next* to continue the installation.
- 5 Select *Update*, then click *Next*.
- 6 Select the partition or system to update, then click *Next*.
- 7 In the Installation Settings screen, adjust the settings according to your requirements.

You can usually leave the default settings untouched, but if you intend to enhance your system, select the packages offered in the *Update Options* submenu or add support for additional languages.

You can also make backups of various system components. Selecting backups slows down the update process. Use this option if you do not have a recent system backup.

- 8 When you are finished configuring the installation settings, click *Accept*.
- 9 Click *Start Update* to begin the installation  
After completing the basic system setup and the installation of all selected software packages, the SUSE Linux Enterprise Desktop installation boots into the updated Linux system, after which you can configure the hardware and set up system services.  
If you are updating from CD, leave CD 1 in your CD-ROM drive during the reboot and do not select any installation options. When the reboot is finished, the installation continues and you are prompted to insert the remaining CDs.

- 10 To test your Internet connection, click *Yes, Test Connection to the Internet > Next*.

This option also checks for the latest SUSE Linux Enterprise Desktop release notes. If you don't want to test the connection at this point (or check for updated release notes), click *No, Skip This Test > Next*, then continue with [Step 13](#).

- 11 On the Running Internet Connection Test screen, view the results of the test, then click *Next* to continue.
- 12 On the Novell Customer Center Configuration screen, click *Configure Now > Next* to enable your system for online updates.

Click *Configure Later > Next* to skip this step and continue the installation. You can configure this option after the product has been installed.

- 13 After the system configuration has completed, view the Release Notes, then click *Next*.
- 14 On the Installation Completed screen, click *Finish* to close the SUSE Linux Enterprise Desktop installation and continue to the login screen.
- 15 Type your username in the *Username* field, then press Enter.
- 16 Type your password in the *Password* field, then press Enter.

## CONFIGURING SUSE LINUX ENTERPRISE DESKTOP

For information on using and configuring SUSE Linux Enterprise Desktop, see the [SUSE Linux Enterprise Desktop 10 GNOME User Guide](http://www.novell.com/documentation/sled10/userguide_gnome/data/bktitle.html) ([http://www.novell.com/documentation/sled10/userguide\\_gnome/data/bktitle.html](http://www.novell.com/documentation/sled10/userguide_gnome/data/bktitle.html)) and the [SUSE Linux Enterprise Desktop 10 KDE User Guide](http://www.novell.com/documentation/sled10/pdfdoc/userguide_kde/userguide_kde.pdf) ([http://www.novell.com/documentation/sled10/pdfdoc/userguide\\_kde/userguide\\_kde.pdf](http://www.novell.com/documentation/sled10/pdfdoc/userguide_kde/userguide_kde.pdf)).

### Legal Notice

Copyright © 2007 Novell, Inc. All rights reserved. No part of this publication may be reproduced, photocopied, stored on a retrieval system, or transmitted without the express written consent of the publisher. For Novell trademarks, see the [Novell Trademark and Service Mark list](http://www.novell.com/company/legal/trademarks/tmlist.html) (<http://www.novell.com/company/legal/trademarks/tmlist.html>). All third-party trademarks are the property of their respective owners. A trademark symbol (®, TM, etc.) denotes a Novell trademark; an asterisk (\*) denotes a third-party trademark.