

Implementation Guide

Novell® Identity Manager Driver for Scripting

3.6.1

June 05, 2009

www.novell.com



Legal Notices

Novell, Inc. makes no representations or warranties with respect to the contents or use of this documentation, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. reserves the right to revise this publication and to make changes to its content, at any time, without obligation to notify any person or entity of such revisions or changes.

Further, Novell, Inc. makes no representations or warranties with respect to any software, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. reserves the right to make changes to any and all parts of Novell software, at any time, without any obligation to notify any person or entity of such changes.

Any products or technical information provided under this Agreement may be subject to U.S. export controls and the trade laws of other countries. You agree to comply with all export control regulations and to obtain any required licenses or classification to export, re-export or import deliverables. You agree not to export or re-export to entities on the current U.S. export exclusion lists or to any embargoed or terrorist countries as specified in the U.S. export laws. You agree to not use deliverables for prohibited nuclear, missile, or chemical biological weaponry end uses. For more information on exporting Novell software, see the [Novell International Trade Services Web page \(http://www.novell.com/info/exports/\)](http://www.novell.com/info/exports/). Novell assumes no responsibility for your failure to obtain any necessary export approvals.

Copyright © 2008-2009 Novell, Inc. All rights reserved. No part of this publication may be reproduced, photocopied, stored on a retrieval system, or transmitted without the express written consent of the publisher.

Novell, Inc. has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more of the U.S. patents listed at [Novell Legal Patents \(http://www.novell.com/company/legal/patents/\)](http://www.novell.com/company/legal/patents/) and one or more additional patents or pending patent applications in the U.S. and in other countries.

Novell, Inc.
404 Wyman Street, Suite 500
Waltham, MA 02451
U.S.A.
www.novell.com

Online Documentation: To access the online documentation for this and other Novell products, and to get updates, see [Novell Documentation \(http://www.novell.com/documentation/\)](http://www.novell.com/documentation/).

Novell Trademarks

For a list of Novell trademarks, see [Trademarks \(http://www.novell.com/company/legal/trademarks/tmlist.html\)](http://www.novell.com/company/legal/trademarks/tmlist.html).

Third-Party Materials

All third-party trademarks are the property of their respective owners.

Contents

About This Guide	9
1 Overview	11
1.1 Driver Architecture	11
1.1.1 Publisher Channel	12
1.1.2 Subscriber Channel	12
1.1.3 Scriptable Framework	13
1.1.4 Schema File	13
1.1.5 Include/Exclude File	13
1.1.6 Loopback State Files	13
1.2 Configuration Overview	13
1.2.1 Data Flow	13
1.2.2 Policies	14
2 Planning for the Scripting Driver	15
2.1 Prerequisites for Linux and UNIX Scripting	15
2.1.1 Identity Vault Server Requirements	15
2.1.2 Operating System Requirements	16
2.1.3 Other Software	16
2.2 Prerequisites for Windows Scripting	16
2.2.1 Identity Vault Server Requirements	16
2.2.2 Other Software	16
2.3 Establishing a Security-Equivalent User	16
3 Installing the Scripting Driver	19
3.1 Installing the Linux and UNIX Scripting Driver	19
3.1.1 Installing the Linux and UNIX Scripting Driver Shim	19
3.1.2 Creating the Driver in Novell eDirectory using iManager	20
3.1.3 Running the Driver	20
3.2 Installing the Windows Scripting Driver	20
3.2.1 Installing the Driver Shim	20
3.2.2 Creating the Driver in Novell eDirectory	21
3.2.3 Running the Driver	21
4 Configuring the Scripting Driver	23
4.1 Driver Parameters and Global Configuration Values	23
4.1.1 Properties That Can Be Set Only During Driver Import	23
4.1.2 Driver Configuration Page	25
4.1.3 Global Configuration Values Page	27
4.2 The Driver Shim Configuration File	29
5 Customizing the Scripting Driver	31
5.1 Scripting Driver Data Definition	31
5.1.1 Defining Data Classes and Attributes	31
5.1.2 Associating Identity Vault and Application Classes and Attributes	32
5.1.3 Defining an Association Rule	33

5.1.4	Defining Excluded Identities	33
5.1.5	Defining Relevant Events	33
5.2	The Connected System Schema File	34
5.2.1	Schema File Syntax	34
5.3	The Connected System Include/Exclude File	36
5.3.1	Include/Exclude Processing	36
5.3.2	Include/Exclude File Syntax	36
5.3.3	Example Include/Exclude Files	40
5.4	Managing Additional Attributes	40
5.4.1	Modifying the Filter	41
5.4.2	Modifying the Scripts for New Attributes	41
5.5	UNIX Shell Developer Guide	41
5.5.1	Application Tools Evaluation	42
5.5.2	Policy and Script Development	42
5.5.3	Deployment	54
5.6	Perl Developer Guide	55
5.6.1	Application Tools Evaluation	55
5.6.2	Policy and Script Development	56
5.6.3	Deployment	68
5.7	Microsoft VBScript Developer Guide	69
5.7.1	Application Tools Evaluation	69
5.7.2	Policy and Script Development	71
5.7.3	Deployment	82
5.8	Using an Alternate Scripting Language	83
6	Using the Scripting Driver	85
6.1	Starting and Stopping the Driver	85
6.2	Starting and Stopping the Driver Shim	85
6.3	Displaying Driver Shim Status	86
6.4	Monitoring Driver Messages	86
7	Securing the Scripting Driver	87
7.1	Using SSL	87
7.2	Physical Security	87
7.3	Network Security	87
7.4	Auditing	87
7.5	Driver Security Certificates	87
7.6	Driver Shell Scripts	88
7.7	The Change Log	88
7.8	Driver Passwords	88
7.9	Driver Code	88
7.10	Administrative Users	89
7.11	Connected Systems	89
A	Troubleshooting	91
A.1	Driver Status and Diagnostic Files	91
A.1.1	The System Log (Linux/UNIX only)	91
A.1.2	The Trace File	92
A.1.3	The Script Output File	93
A.1.4	DSTRACE	93
A.1.5	The Status Log	93
A.2	Troubleshooting Common Problems	93

A.2.1	Driver Shim Installation Failure	94
A.2.2	Driver Rules Installation Failure	94
A.2.3	Driver Certificate Setup Failure	94
A.2.4	Driver Start Failure	94
A.2.5	Driver Shim Startup or Communication Failure	95
A.2.6	Users or Groups Are Not Provisioned to the Connected System	95
A.2.7	Users or Groups Are Not Provisioned to the Identity Vault	95
A.2.8	Identity Vault User Passwords Are Not Provisioned to the Connected System.	96
A.2.9	Connected System User Passwords Are Not Provisioned to the Identity Vault.	96
A.2.10	Metadirectory Objects Are Not Modified, Deleted, Renamed, or Moved	96
A.3	Shared Memory Errors (Linux/UNIX only)	97
B	System and Error Messages	99
B.1	CFG Messages	99
B.2	CHGLOG Messages	100
B.3	DOM Messages	100
B.4	DRVCOM Messages	100
B.5	HES Messages	101
B.6	LWS Messages	101
B.7	NET Messages.	102
B.8	NIX Messages (Linux/UNIX only).	103
B.9	OAP Messages	105
B.10	RDXML Messages	106
C	IDMLib Reference	109
C.1	UNIX Shell (idmlib.sh) Reference	109
C.1.1	General Functions	109
C.1.2	Subscriber Functions	110
C.1.3	Publisher Functions	111
C.1.4	Query Functions	111
C.1.5	Heartbeat Functions	111
C.2	Perl (IDMLib.pm) Reference	112
C.2.1	General Functions	112
C.2.2	Subscriber Functions.	113
C.2.3	Publisher Functions	114
C.2.4	Query Functions	114
C.2.5	Heartbeat Functions	114
C.3	Microsoft VBScript (IDMLib.vbs) Reference	115
C.3.1	General Functions	115
C.3.2	Subscriber Functions.	116
C.3.3	Publisher Functions	117
C.3.4	Query Functions	118
C.3.5	Heartbeat Functions	120
D	Technical Details	121
D.1	Using the usdrv-config Command (Linux/UNIX only).	121
D.1.1	Setting the Remote Loader and Driver Object Passwords	121
D.1.2	Configuring the Driver for SSL	122
D.2	Driver Shim Command Line Options	122
D.2.1	Options Used to Set Up Driver Shim SSL Certificates	122
D.2.2	Other Options	123
D.3	Publisher Change Log Tool	123
D.4	Files and Directories Modified by Installing the Driver Shim	126

D.4.1	Driver Shim Directory	126
D.4.2	/usr/sbin Files (Linux/UNIX only)	126
D.4.3	init.d Files (Linux/UNIX only)	126
D.4.4	Man Pages (Linux/UNIX only)	126
D.4.5	Driver Shim Configuration File	127
D.4.6	Windows Support Files (Windows only)	127

E Documentation Updates 129

E.1	November 23, 2009	129
E.2	October 23, 2007	129

About This Guide

This guide describes implementation of the Novell® Identity Manager 3.6.1 driver for Scripting.

The driver synchronizes data from a connected system through a scriptable interface with Identity Manager 3.6.1, the comprehensive identity management suite that allows organizations to manage the full user life cycle, from initial hire, through ongoing changes, to ultimate retirement of the user relationship.

This guide includes the following sections:

- ♦ Chapter 1, “Overview,” on page 11
- ♦ Chapter 2, “Planning for the Scripting Driver,” on page 15
- ♦ Chapter 3, “Installing the Scripting Driver,” on page 19
- ♦ Chapter 4, “Configuring the Scripting Driver,” on page 23
- ♦ Chapter 5, “Customizing the Scripting Driver,” on page 31
- ♦ Chapter 6, “Using the Scripting Driver,” on page 85
- ♦ Chapter 7, “Securing the Scripting Driver,” on page 87
- ♦ Appendix A, “Troubleshooting,” on page 91
- ♦ Appendix B, “System and Error Messages,” on page 99
- ♦ Appendix C, “IDMLib Reference,” on page 109
- ♦ Appendix D, “Technical Details,” on page 121

Audience

This guide is for system administrators and others who plan, install, configure, and use the Scripting driver for Identity Manager. It assumes that you are familiar with Identity Manager, Novell eDirectory™, and the administration of systems and platforms you connect to Identity Manager.

Feedback

We want to hear your comments and suggestions about this manual and the other documentation included with this product. Please use the User Comments feature at the bottom of each page of the online documentation, or go to the [Novell Documentation Feedback site \(http://www.novell.com/documentation/feedback.html\)](http://www.novell.com/documentation/feedback.html) and enter your comments there.

Documentation Updates

For the most recent version of this guide, visit the [Identity Manager 3.6.1 Drivers Documentation Web site \(http://www.novell.com/documentation/idm36drivers\)](http://www.novell.com/documentation/idm36drivers).

Additional Documentation

For additional documentation about Identity Manager drivers, see the [Identity Manager 3.6.1 Drivers Documentation Web site \(http://www.novell.com/documentation/idm36drivers\)](http://www.novell.com/documentation/idm36drivers).

For additional documentation about Identity Manager, see the [Identity Manager 3.6.1 Documentation Web site \(http://www.novell.com/documentation/idm36\)](http://www.novell.com/documentation/idm36).

For documentation about other related Novell products, such as eDirectory and iManager, see [the Novell Documentation Web site's product index \(http://www.novell.com/documentation\)](http://www.novell.com/documentation).

Documentation Conventions

In Novell documentation, a greater-than symbol (>) is used to separate actions within a step and items in a cross-reference path.

A trademark symbol (®, ™, etc.) denotes a Novell trademark. An asterisk (*) denotes a third-party trademark.

When a single pathname can be written with a backslash for some platforms or a forward slash for other platforms, the pathname is presented with a backslash. Users of platforms that require a forward slash, such as Linux* or UNIX*, should use forward slashes as required by your software.

The Identity Manager 3.6.1 driver for Scripting synchronizes data between the Identity Vault and a connected system using a scripting environment suitable for the target application. Languages such as Shell, Perl* and Microsoft* VBScript* can be used to extend the base set of sample scripts to update and retrieve information from the target application. Traditional driver development is accomplished with Java* and the Policy Builder. With the Scripting environment, driver development can be done in alternate languages, which provide a large set of packages and complex language syntax. In addition, your target application might already provide management tools, commands, or APIs written or easily accessible in Perl, Shell Script or VBScript.

The Scripting driver runs on a large number of Linux and UNIX platforms, including Linux, Solaris*, AIX* and HP-UX*. In addition, a Microsoft Windows* service is available for applications that run on the Windows platform. The driver also uses embedded Remote Loader technology to communicate with the Identity Vault, bidirectionally synchronizing changes between the Identity Vault and the connected system. The embedded Remote Loader component, also called the driver shim, runs as a native process on the connected Linux or UNIX system or a Windows service on a Windows system. There is no requirement to install Java on the connected system. The simplicity of installation, configuration and security provides an excellent environment for the development of new drivers.

Major topics in this section include

- ♦ [Section 1.1, “Driver Architecture,” on page 11](#)
- ♦ [Section 1.2, “Configuration Overview,” on page 13](#)

1.1 Driver Architecture

The Scripting driver synchronizes information between the Identity Vault and an external account management system (the connected system).

The Identity Manager detects relevant changes to identities in the Identity Vault and notifies the Subscriber component of the driver. After customizable policy processing, events are sent to the Subscriber shim of the embedded Remote Loader process on the connected system. The Subscriber shim securely passes the information to customizable scripts that perform the required actions.

A process on the connected system polls the account management system for changes at a configurable interval. If the poll returns identity changes, they are written to the change log.

The Publisher shim of the embedded Remote Loader process submits the changes from the change log to the Metadirectory engine as events. The Metadirectory engine processes these events using customizable policies and posts relevant changes to the Identity Vault.

Topics in this section include

- ♦ [Section 1.1.1, “Publisher Channel,” on page 12](#)
- ♦ [Section 1.1.2, “Subscriber Channel,” on page 12](#)
- ♦ [Section 1.1.3, “Scriptable Framework,” on page 13](#)
- ♦ [Section 1.1.4, “Schema File,” on page 13](#)

- ♦ [Section 1.1.5, “Include/Exclude File,” on page 13](#)
- ♦ [Section 1.1.6, “Loopback State Files,” on page 13](#)

1.1.1 Publisher Channel

The Publisher shim provides identity change information to the Metadirectory engine as XDS event documents. The Metadirectory engine applies policies, takes the appropriate actions, and posts the events to the Identity Vault.

Change Log

The change log stores identity changes in encrypted form. The polling script uses the change log update command to record identity changes it detects. Events are removed from the change log by the Publisher shim at configurable intervals and submitted to the Metadirectory engine for processing. If communication with the Metadirectory engine is temporarily lost, events remain in the change log until communication becomes available again.

Change Log Update Command

The change log update command encrypts and writes events to the change log. Any process with rights to update the change log can use the change log update command. The change log update command takes command line arguments and standard input, and stores events in encrypted form in the change log for subsequent publishing. The polling script calls the change log update command to record identity changes. For information about using the change log update command, see the developer guides in [Chapter 5, “Customizing the Scripting Driver,” on page 31](#).

Polling Script

The polling script periodically scans the local account management system for modifications that have occurred since the last polling interval. If necessary, the polling script updates the change log by calling the change log update command. You can specify the polling interval during installation and by subsequent configuration of the Driver object.

Publisher Shim

The Publisher shim periodically scans the change log for events. Before scanning the change log, the driver calls the polling script to check the local system for changes that might have been made since the previous poll.

When the Publisher shim finds events in the change log, it decrypts, processes, and sends them to the Metadirectory engine in XDS format over a Secure Sockets Layer (SSL) network link.

1.1.2 Subscriber Channel

The Subscriber channel receives XDS command documents from the Metadirectory engine and calls the appropriate script or scripts to handle the command.

The provided scripts must be customized to handle connected system events. For more information see [Chapter 5, “Customizing the Scripting Driver,” on page 31](#).

1.1.3 Scriptable Framework

The interface between the connected system and the driver shim uses customizable scripts. You must extend the scripts that are provided with the driver to support your connected system. Several utility scripts and helper commands are provided with the driver to facilitate communication with the driver shim and the change log. An extensible connected system schema file allows you to add your own objects and attributes to those already supported by the driver.

For more information about the scriptable framework, see [Chapter 5, “Customizing the Scripting Driver,” on page 31](#).

1.1.4 Schema File

The configuration of class and attribute definitions for the connected system is specified using the schema file. You can modify and extend this file to include new objects and attributes. For details about configuring the schema file, see [Section 5.2, “The Connected System Schema File,” on page 34](#).

1.1.5 Include/Exclude File

The include/exclude file allows local system policy to enforce which objects are included or excluded from provisioning, on both the Publisher channel and the Subscriber channel, independently. For details about using the include/exclude file, see [Section 5.3, “The Connected System Include/Exclude File,” on page 36](#).

1.1.6 Loopback State Files

The loopback state files are used to provide automatic loopback detection for external applications that do not have mechanisms to perform loopback detection. This loopback detection prevents subscribed events from being published back to the Identity Vault.

1.2 Configuration Overview

This section discusses driver configuration details specific to the Scripting driver. For basic configuration information, see the *Identity Manager 3.6.1 Common Driver Administration Guide*. For detailed information about configuring the Scripting driver, see [Chapter 4, “Configuring the Scripting Driver,” on page 23](#).

Topics in this section include

- ♦ [Section 1.2.1, “Data Flow,” on page 13](#)
- ♦ [Section 1.2.2, “Policies,” on page 14](#)

1.2.1 Data Flow

Filters and policies control the data flow of identities to and from the connected system and the Identity Vault. The Data Flow option, specified during driver import, determines how these filters and policies behave.

- ♦ **Bidirectional:** Sets classes and attributes to be synchronized on both the Subscriber and Publisher channels.

- ♦ **Application to Identity Vault:** Sets classes and attributes to be synchronized on the Publisher channel only.
- ♦ **Identity Vault to Application:** Sets classes and attributes to be synchronized on the Subscriber channel only.

1.2.2 Policies

The Metadirectory engine uses policies to control the flow of information into and out of the Identity Vault. Policies can be customized to support desired operations. The following table describes the policy functions for the Scripting driver in the default configuration:

Table 1-1 *Default Linux and UNIX Driver Policy Functions*

Policy	Description
Mapping	Maps the Identity Vault objects and selected attributes to connected system objects and attributes.
Publisher Event	Processes Publisher-side operations.
Publisher Matching	Restricts privileged accounts and defines matching criteria for placement in the Identity Vault.
Publisher Create	Defines creation rules for provisioning into the Identity Vault.
Publisher Placement	Defines where new objects are placed in the Identity Vault.
Publisher Command	Defines password publishing policies.
Subscriber Matching	Defines rules for matching identities in the connected system.
Subscriber Create	Defines required creation criteria.
Subscriber Command	Transforms attributes and defines password subscribing policies.
Subscriber Output	Sends e-mail notifications for password failures and converts information formats from the Identity Vault to the connected system.
Subscriber Event	Restricts events to a specified container.

Planning for the Scripting Driver

2

The planning process for the Novell® Identity Manager Driver for Scripting begins by determining whether you develop your own scripts and policies for use with your external account management system or you obtain them from a third party.

If you are customizing the scripts, the process continues by installing the Scripting driver to a development system. The first decision to make is whether you run the driver shim on Windows or a Linux/UNIX system. (The driver engine component hosted by Novell Identity Manager can run on any operating system that supports Identity Manager.) The driver shim should be installed on a system that hosts, or is remotely connected to, the external account management system. The operating system of this system is the operating system of the driver shim.

Your operating system choice determines what scripting language to use. On Linux and UNIX, pre-written libraries are included for the Bourne shell and Perl. On Windows, a library is included for Microsoft VBScript. Also, with additional development work, you can port these libraries to another scripting language.

Continue the development process by reading [Chapter 5, “Customizing the Scripting Driver,” on page 31](#) and following its instructions.

If you have obtained custom scripts from a third party, you should follow their instructions for installing the Scripting driver and their custom components. You should install and test the driver on a test system first and then on production systems.

This section reviews some of the issues to consider before you install the Scripting driver. Major topics include

- ♦ [Section 2.1, “Prerequisites for Linux and UNIX Scripting,” on page 15](#)
- ♦ [Section 2.2, “Prerequisites for Windows Scripting,” on page 16](#)
- ♦ [Section 2.3, “Establishing a Security-Equivalent User,” on page 16](#)

For general information about planning for identity management, see the [Identity Manager 3.6.1 Installation Guide](#).

2.1 Prerequisites for Linux and UNIX Scripting

Topics in this section include

- ♦ [Section 2.1.1, “Identity Vault Server Requirements,” on page 15](#)
- ♦ [Section 2.1.2, “Operating System Requirements,” on page 16](#)
- ♦ [Section 2.1.3, “Other Software,” on page 16](#)

2.1.1 Identity Vault Server Requirements

- ♦ Novell eDirectory™ 8.7.3.4 or later, or Novell eDirectory 8.8.1 or later.
- ♦ Novell Identity Manager 3.5.1 or later.

2.1.2 Operating System Requirements

- ♦ Red Hat* Linux (x86 and x86_64)
- ♦ SUSE® Linux (x86 and x86_64)
- ♦ Debian* Linux
- ♦ Solaris (SPARC* and i386)
- ♦ AIX
- ♦ HP-UX (RISC and IA64)
- ♦ Tru64*
- ♦ FreeBSD*
- ♦ Mac* OSX* (Darwin x86)

2.1.3 Other Software

- ♦ Novell iManager 2.7 or later can be installed on the Identity Vault Server or a separate system.
- ♦ Novell Designer 2 or later (optional; for development).

2.2 Prerequisites for Windows Scripting

- ♦ [Section 2.2.1, “Identity Vault Server Requirements,” on page 16](#)
- ♦ [Section 2.2.2, “Other Software,” on page 16](#)

2.2.1 Identity Vault Server Requirements

- ♦ Novell eDirectory 8.7.3.4 or later, or Novell eDirectory 8.8.1 or later.
- ♦ Novell Identity Manager 3.5.1 or later.

2.2.2 Other Software

- ♦ Novell iManager 2.7 or later can be installed on the Identity Vault Server or a separate system
- ♦ Novell Designer 2 or later (optional; for development).

2.3 Establishing a Security-Equivalent User

The driver must run with security equivalent to a user with sufficient rights. You can set the driver equivalent to ADMIN or a similar user. For stronger security, you can define a user with only the minimal rights necessary for the operations you want the driver to perform.

The driver user must be a trustee of the containers where synchronized identities reside, with the rights shown in Table 2-1. Inheritance must be set for [Entry Rights] and [All Attribute Rights].

Table 2-1 Base Container Rights Required by the Driver Security-Equivalent User

Operation	[Entry Rights]	[All Attribute Rights]
Subscriber notification of account changes (recommended minimum)	Browse	Compare and Read
Creating objects in the Identity Vault without group synchronization	Browse and Create	Compare and Read
Creating objects in the Identity Vault with group synchronization	Browse and Create	Compare, Read, and Write
Modifying objects in the Identity Vault	Browse	Compare, Read, and Write
Renaming objects in the Identity Vault	Browse and Rename	Compare and Read
Deleting objects from the Identity Vault	Browse and Erase	Compare, Read, and Write
Retrieving passwords from the Identity Vault	Browse and Supervisor	Compare and Read
Updating passwords in the Identity Vault	Browse and Supervisor	Compare, Read, and Write

If you do not set Supervisor for [Entry Rights], the driver cannot set passwords. If you do not want to set passwords, set the Subscribe setting for the User class nspmDistributionPassword attribute to Ignore in the filter to avoid superfluous error messages. For details about accessing and editing the filter, see the Policy Builder and Driver Customization Guide on the Identity Manager 3 Documentation Web site (<http://www.novell.com/documentation/idm/index.html>). For complete information about rights, see the *Novell® eDirectory 8.7.3 Administration Guide* on the [Novell eDirectory 8.7.3 Documentation Web site](http://www.novell.com/documentation/edir873) (<http://www.novell.com/documentation/edir873>).

Installing the Scripting Driver

3

This section provides the information you need to install the Identity Manager 3.6.1 driver for Scripting.

Major topics include

- [Section 3.1, “Installing the Linux and UNIX Scripting Driver,” on page 19](#)
- [Section 3.2, “Installing the Windows Scripting Driver,” on page 20](#)

3.1 Installing the Linux and UNIX Scripting Driver

Topics in this section include

- [Section 3.1.1, “Installing the Linux and UNIX Scripting Driver Shim,” on page 19](#)
- [Section 3.1.2, “Creating the Driver in Novell eDirectory using iManager,” on page 20](#)
- [Section 3.1.3, “Running the Driver,” on page 20](#)

3.1.1 Installing the Linux and UNIX Scripting Driver Shim

- 1 Log in to the target application server as `root`.
- 2 Obtain the `<os>_linux_x86_scriptdriver_install.bin` file for 32-bit or `<os>_linux_x86_64_scriptdriver_install.bin` file for 64-bit from your installation media and execute this self-extracting file on your Linux or UNIX system.
- 3 Specify a language choice.
- 4 Read and accept the license agreement.
- 5 After the package is installed onto your system, you are prompted to enter Driver and Remote Loader passwords. These passwords are used to verify that an authorized driver shim is communicating with the Identity Manager engine. Follow the prompts:
 - 5a Enter and confirm the Remote Loader password.
 - 5b Enter and confirm the driver password.
- 6 Next, you are prompted to retrieve an SSL certificate. Novell® eDirectory™ must be running in order to retrieve the certificate. The certificate allows SSL encryption between the Identity Manager engine and the driver shim. Enabling SSL is optional but is recommended for better security. To retrieve the certificate, follow the prompts:
 - 6a Specify the DNS name or IP address of your eDirectory server.
 - 6b Specify the LDAP secure port, default 636.
 - 6c Enter `Y` to accept the certificate.
- 7 You are prompted for a Scripting language to be used on this system. Enter `Perl` for the sample Perl scripts to be installed or enter `Shell` for the sample Bourne Shell scripts to be installed.

- 8 If you select Perl, you are optionally asked to install the Perl IDMLib perl module into the Perl system path to be accessible by the sample Perl scripts. Enter **Yes** or **No** to install this library.
- 9 The installation of the driver shim is finished, with the option of starting the Driver Shim Service. Proceed to the next section to complete the installation of the driver.

3.1.2 Creating the Driver in Novell eDirectory using iManager

- 1 In iManager, click the *Import Drivers* task under *Identity Manager Utilities*.
- 2 All drivers are contained in a Driver Set. You can create a new Driver Set or install the driver into an existing one. See *Identity Manager 3.6.1 Common Driver Administration Guide* for more details. Click *Next* to proceed.
- 3 Select the Scripting driver from the list of drivers and click *Next* to proceed.
- 4 Enter information in the requested configuration fields, then click *Next* to continue.
When entering the Remote Loader and Driver object passwords, be sure to enter the same values that you entered when installing the Drivershim. For more information on these fields, see *Section 4.1, “Driver Parameters and Global Configuration Values,” on page 23*.
- 5 Click *Define Security Equivalences*, and select your administrative user to make the driver security-equivalent to that user (see also *Section 2.3, “Establishing a Security-Equivalent User,” on page 16*).
- 6 Click *Exclude Administrative Roles*, and select your administrative user and other high-privilege users that should not be monitored for events.
- 7 Click *Next* to proceed, then click *Finish* to complete the installation.

3.1.3 Running the Driver

Start the driver engine component in Novell iManager.

The driver shim is a UNIX daemon process. Use the UNIX startup script `usdrvd` to start and stop the Novell Identity Manager Linux and UNIX Script Driver (see *Chapter 6, “Using the Scripting Driver,” on page 85*.)

3.2 Installing the Windows Scripting Driver

Topics in this section include

- ♦ *Section 3.2.1, “Installing the Driver Shim,” on page 20*
- ♦ *Section 3.2.2, “Creating the Driver in Novell eDirectory,” on page 21*
- ♦ *Section 3.2.3, “Running the Driver,” on page 21*

3.2.1 Installing the Driver Shim

- 1 Obtain the `win_x86_scriptdriver_install.exe` file for 32-bit or `win_x86_64_scriptdriver_install.exe` file for 64-bit from your installation media. Run this file on your Windows system.
- 2 Click *Next* to continue the installation.
- 3 Accept the default installation folder or specify your own. Click *Next* to continue.

- 4 Review your settings and click *Next* to continue.
- 5 After the driver files are copied, you are prompted to retrieve an SSL certificate. Novell eDirectory must be running in order to retrieve the certificate. The certificate allows SSL encryption between the Identity Manager engine and the driver shim. Enabling SSL is optional but is recommended for better security. To retrieve the certificate, click *Yes* and follow the prompts in the console window:
 - 5a Specify the DNS name or IP address of your eDirectory server.
 - 5b Specify the LDAP secure port, default 636.
 - 5c Enter *y* to accept the certificate.
- 6 You are prompted to enter Driver and Remote Loader passwords. These passwords are used to verify that an authorized driver shim is communicating with the Identity Manager engine. Although you don't need to enter the passwords immediately, they must be set at some point before running the driver. Click *Yes* to the prompt and follow the prompts in the console window:
 - 6a Enter and confirm the Remote Loader password.
 - 6b Enter and confirm the Driver password.
- 7 The installation of the driver shim is finished, with the option of starting the Driver Shim Service. Proceed to the next section to complete the installation of the driver.

3.2.2 Creating the Driver in Novell eDirectory

- 1 In iManager, click the *Import Drivers* task under *Identity Manager Utilities*.
- 2 All drivers are contained in a driver set. You can create a new driver set or install the driver into an existing one. See *Identity Manager 3.6.1 Common Driver Administration Guide* for more details. Click *Next* to proceed.
- 3 Select the Scripting driver from the list of drivers, then click *Next* to proceed.
- 4 Fill in the requested configuration fields, then click *Next* to continue.

When entering the Remote Loader and Driver Object passwords, be sure to enter the same values that you entered when installing the driver shim. For more information on these fields, see [Section 4.1, "Driver Parameters and Global Configuration Values," on page 23](#).
- 5 Click *Define Security Equivalences*, and select your administrative user to make the driver security-equivalent to that user (see also [Section 2.3, "Establishing a Security-Equivalent User," on page 16](#)).
- 6 Click *Exclude Administrative Roles*, and select your administrative user and other high-privilege users that should not be included monitored for events.
- 7 Click *Next* to proceed, then click *Finish* to complete the installation.

3.2.3 Running the Driver

Start the driver engine component in Novell iManager.

The driver shim is a Windows service. Use the Windows Services application to start and stop the Novell Identity Manager Windows Script Driver service (see [Chapter 6, "Using the Scripting Driver," on page 85](#)).

Configuring the Scripting Driver

4

After you have installed the Identity Manager 3.6.1 driver for Scripting, use the information in this section for configuration. Major topics include

- ♦ [Section 4.1, “Driver Parameters and Global Configuration Values,” on page 23](#)
- ♦ [Section 4.2, “The Driver Shim Configuration File,” on page 29](#)

4.1 Driver Parameters and Global Configuration Values

You can control the operation of the Scripting driver by modifying the properties described in the following sections. Topics in this section include

- ♦ [Section 4.1.1, “Properties That Can Be Set Only During Driver Import,” on page 23](#)
- ♦ [Section 4.1.2, “Driver Configuration Page,” on page 25](#)
- ♦ [Section 4.1.3, “Global Configuration Values Page,” on page 27](#)

IMPORTANT: Changing these values requires a restart of the driver.

To edit the properties shown on the Driver Configuration page and the Global Configuration Values page:

- 1 In iManager, select *Identity Manager Overview* from the Identity Manager task list on the left side of the window.
- 2 Navigate to your driver set by searching the tree or by entering its name.
- 3 Click the driver to open its overview.
- 4 Click the driver icon.
- 5 Select *Driver Configuration* or *Global Config Values* as appropriate.
- 6 Edit the property values as desired, then click *OK*.

4.1.1 Properties That Can Be Set Only During Driver Import

Properties that you can set only during driver import are used to generate policies and other configuration details.

To change import-only properties, you must re-import the `Scripting.xml` driver configuration file over the existing driver.

Table 4-1 *Driver Import-Only Parameters*

Property Name	Values or Format
Data Flow	Bidirectional
	Application to Identity Vault
	Identity Vault to Application
Enable Entitlements	Yes
	No
Use SSL	No

Data Flow

- ♦ **Bidirectional:** Identities are synchronized from both the Identity Vault and the connected system (application). After all pending events are processed, the Identity Vault and connected system mirror each other.
- ♦ **Application to Identity Vault:** Identities are synchronized from the connected system (application) to the Identity Vault, but not vice versa. For example, an identity created in the Identity Vault is not created on the connected system unless explicitly migrated.
- ♦ **Identity Vault to Application:** Identities are synchronized from the Identity Vault to the connected system (application), but not vice versa. For example, changes made to a connected system's identity are not synchronized to the Identity Vault.

Enable Entitlements

Specifies whether the driver uses either Approval Flow or Role-Based Entitlements with the Entitlements Service driver.

Enable entitlements for the driver only if you plan to use the User Application or Role-Based Entitlements with the driver.

You can use Role-Based Entitlements to integrate the Scripting driver with the Identity Manager User Application.

Use SSL

Specifies whether the driver uses Secure Sockets Layer (SSL) to encrypt the connection between the Identity Vault and the application.

We strongly recommend that you use SSL. If you do not use SSL, identity data (including passwords) is sent across the network in clear text.

4.1.2 Driver Configuration Page

Table 4-2 *Driver Configuration Page*

Property Name	Values or Format
Driver Module	<i>Connect to Remote Loader</i> must be selected.
Driver Object Password	Text Value
Authentication ID	Not used by the Scripting driver.
Authentication Context	Not used by the Scripting driver.
Remote Loader Connection	Parameters Host name or IP address and port number of the driver shim on the connected system, and the RDN of the object with server certificate.
Driver Cache Limit	The recommended value is 0 (zero).
Application Password	Not used by the Scripting driver.
Remote Loader Password	Text Value
Startup Option	Auto start
	Manual
Automatic Loopback Detection	Yes
	No
Script Command	Text Value
Script Trace File	Filename
Subscriber Script	Filename
Polling Script	Filename
Heartbeat Script	Filename
Polling Interval	Number of seconds
Heartbeat Interval	Number of seconds

Driver Object Password

The Driver object password is used by the driver shim (embedded Remote Loader) to authenticate itself to the Metadirectory engine. This must be the same password that is specified as the Driver object password on the connected system driver shim.

Remote Loader Connection Parameters

Table 4-3 Remote Loader Connection Parameters

Parameter	Description
host=hostName	Connected system host name or IP address.
port=portNumber	Connected system TCP port number. The default is 8090.
kmo=objectRDN	The RDN of the object with the server certificate signed by the tree's certificate authority. Enclose the RDN in double quotes (") if the name contains spaces.

The following is an example Remote Loader connection parameter string:

```
hostname=192.168.17.41 port=8090 kmo="SSL CertificateIP"
```

Remote Loader Password

The Remote Loader password is used to control access to the driver shim (embedded Remote Loader). This must be the same password that is specified as the Remote Loader password on the connected system driver shim.

Automatic Loopback Detection

Specifies whether the driver shim discards events that would cause loopback conditions. This function supplements the loopback detection provided by the Metadirectory engine.

Script Command

Specifies the command line the driver uses when executing scripts. The driver provides default values for Shell scripts, Perl and VBScript. Normally this value does not need to be changed.

Script Trace File

Specifies a file to which script trace output will be written. The path is relative to the Scripting driver installation directory.

Subscriber Script

Specifies the script file that the driver runs for Subscriber events. The driver provides default values for Shell scripts, Perl and VBScript, so this value does not normally need to be changed.

Polling Script

Specifies the script file that the Publisher shim runs to poll for external events. The driver provides default values for Shell scripts, Perl and VBScript, so this value does not normally need to be changed.

Heartbeat Script

Specifies the script file that the Publisher shim runs to check the external account management system's status. The driver provides default values for Shell scripts, Perl and VBScript, so this value does not normally need to be changed.

Polling Interval

Specifies the number of seconds that the Publisher shim waits after running the polling script and sending events from the change log to the Metadirectory engine. The default interval is 60 seconds, and the minimum interval is 1 second.

Heartbeat Interval

Specifies how often, in seconds, the driver shim contacts the Metadirectory engine to verify connectivity. Specify 0 to disable the heartbeat.

4.1.3 Global Configuration Values Page

Table 4-4 *Global Configuration Values*

Property Name	Values or Format
Connected System or Driver Name	Text Value
The Scripting Connected System Accepts Passwords from the Identity Vault	Yes
	No
The Identity Vault Accepts Passwords from the Scripting Connected System	Yes
	No
The Identity Vault Accepts Administrative Password Resets from the Scripting Connected System	Yes
	No
Publish Passwords to NDS Password	Yes
	No
Publish Passwords to Distribution Password	Yes
	No
Require Password Policy Validation before Publishing Passwords	Yes
	No
Reset User's External System Password to the Identity Manager Password on Failure	Yes
	No
Notify the User of Password Synchronization Failure via E-Mail	Yes
	No
User Base Container	Identity Vault Container object

Property Name	Values or Format
Group Base Container	Identity Vault Container object

To view and edit Password Management GCVs, select *Show* for *Show Password Management Policy*.

To view and edit User and Group Placement GCVs, select *Show* for *Show User and Group Placements*.

Connected System or Driver Name

Specifies the name of the driver. This value is used by the e-mail notification templates.

The Scripting Connected System Accepts Passwords from the Identity Vault

Specifies whether the driver allows passwords to flow from the Identity Vault to the connected system.

The Identity Vault Accepts Passwords from the Scripting Connected System

Specifies whether the driver allows passwords to flow from the connected system to the Identity Vault.

The Identity Vault Accepts Administrative Password Resets from the Scripting Connected System

Specifies whether the driver allows passwords to be reset from the connected system in the Identity Vault.

Publish Passwords to NDS Password

Specifies whether the driver uses passwords from the connected system to set nonreversible NDS[®] passwords in the Identity Vault.

Publish Passwords to Distribution Password

Specifies whether the driver uses passwords from the connected system to set NMAS[™] Distribution passwords, which are used for Identity Manager password synchronization.

Require Password Policy Validation before Publishing Passwords

Specifies whether the driver applies NMAS password policies to published passwords. If so, a password is not written to the Identity Vault if it does not conform.

Reset User's External System Password to the Identity Manager Password on Failure

Specifies whether, on a publish Distribution Password failure, the driver attempts to reset the password on the connected system using the Distribution Password from the Identity Vault.

Notify the User of Password Synchronization Failure via E-Mail

Specifies whether the driver sends an e-mail to a user if the password cannot be synchronized.

User Base Container

Specifies the base container object in the Identity Vault for user synchronization. This container is used in the Subscriber channel Event Transformation policy to limit the Identity Vault objects being synchronized. This container is used in the Publisher channel Placement policy as the destination for adding objects to the Identity Vault. Use a value similar to the following:

```
users.myorg
```

Group Base Container

Specifies the base container object in the Identity Vault for group synchronization. This container is used in the Subscriber channel Event Transformation policy to limit the Identity Vault objects being synchronized. This container is used in the Publisher channel Placement policy as the destination when adding objects to the Identity Vault. Use a value similar to the following:

```
groups.myorg
```

4.2 The Driver Shim Configuration File

The driver shim configuration file controls operation of the driver shim. The location and name of the file is dependent on the operating system:

- ♦ Windows: `wsdrv.conf` in the `conf` directory in your installation directory.
- ♦ Linux or UNIX: `/etc/usdrv.conf`

A default configuration file is created at installation time.

You can specify the configuration options listed in [Table 4-5](#), one per line. You can also specify these options on the driver shim command line. For details about driver shim command line options, see [Section D.2, “Driver Shim Command Line Options,” on page 122](#).

Table 4-5 *Driver Shim Configuration File Statements*

Option (Short and Long Forms)	Description
-conn connString	A string with connection options. Enclose the string in double quotes ("). If you specify more than one option, separate the options with spaces. port=driverShimPort ca=Certificate Authority Key File
-connection connString	
-hp httpPort	Specifies the HTTP services port number. The default HTTP services port number is 8091. You can connect to this port to view log files. For details, see Section A.1, “Driver Status and Diagnostic Files,” on page 91 .
-httpport httpPort	

Option (Short and Long Forms)	Description
-path driverPath	Specifies the HTTP services port number. The default HTTP services port number is 8091. You can connect to this port to view log files. For details, see Section A.1, “Driver Status and Diagnostic Files,” on page 91.
-t traceLevel	Sets the level of debug tracing. 0 is no tracing, and 10 is all tracing. For details, see Section A.1, “Driver Status and Diagnostic Files,” on page 91.
-trace traceLevel	
	The output file location is specified by the tracefile option.
-tf fileName	Sets the trace file location.
-tracefile fileName	Windows default file: C:\Progra~1\Novell\WSDriver\logs\trace.log Linux/UNIX default file: /opt/novell/usdrv/logs/trace.log.

Example Configuration File

```
-tracefile /opt/novell/usdrv/logs/trace.log
-t trace 0
-connection "ca=/opt/novell/usdrv/keys/ca.pem port=8090"
-httpport 8091
-path /opt/novell/usdrv/
```

Customizing the Scripting Driver

5

This section describes how the scripts can be written to access and manage your target system. Scripting sets for both Linux and UNIX and for Windows provide libraries, accessible by the scripts, to retrieve event and driver data from the driver shim and to return information to the engine for processing.

The Identity Manager engine has some simple requirements in order to successfully process events. The provided library supplements your scripts to provide the tools necessary for this successful interaction.

Major topics in this section include

- ♦ [Section 5.1, “Scripting Driver Data Definition,” on page 31](#)
- ♦ [Section 5.2, “The Connected System Schema File,” on page 34](#)
- ♦ [Section 5.3, “The Connected System Include/Exclude File,” on page 36](#)
- ♦ [Section 5.4, “Managing Additional Attributes,” on page 40](#)
- ♦ [Section 5.5, “UNIX Shell Developer Guide,” on page 41](#)
- ♦ [Section 5.6, “Perl Developer Guide,” on page 55](#)
- ♦ [Section 5.7, “Microsoft VBScript Developer Guide,” on page 69](#)
- ♦ [Section 5.8, “Using an Alternate Scripting Language,” on page 83](#)

5.1 Scripting Driver Data Definition

Topics in this section include

- ♦ [Section 5.1.1, “Defining Data Classes and Attributes,” on page 31](#)
- ♦ [Section 5.1.2, “Associating Identity Vault and Application Classes and Attributes,” on page 32](#)
- ♦ [Section 5.1.3, “Defining an Association Rule,” on page 33](#)
- ♦ [Section 5.1.4, “Defining Excluded Identities,” on page 33](#)
- ♦ [Section 5.1.5, “Defining Relevant Events,” on page 33](#)

5.1.1 Defining Data Classes and Attributes

The first task is to examine your external application’s identity data and to determine what data is relevant and how it should be managed. Below is a series of questions to ask in this process. The list is not all-inclusive; there might be other questions you need to consider.

- ♦ Are identities stored in a hierarchical or flat format? In a hierarchical system, objects known as containers can contain identities and perhaps other containers, resulting in a tree-like structure. A flat system contains all identities at a single level.
- ♦ What types of identities exist in the external application? For example, Novell® eDirectory™ contains Users, Groups and Dynamic Groups, to name a few. Identity types, like Groups, are often aggregates of other identity types.

- ♦ What uniquely distinguishes (or names) each type of identity? The name is usually an attribute, known as the naming attribute. Systems often use a human-readable name and a unique serial number. You should determine which is suitable for your needs.
- ♦ What relationships exist among the identity types? Suppose Groups can contain Users. Can Groups contain other Groups? Are these relationships one-to-one or one-to-many?
- ♦ Is there a way for an identity to link to or represent another identity? For example, eDirectory provides Alias objects, which link to other objects. Your driver might need to handle these types of objects.
- ♦ What attributes describe each relevant type of object? Which of these attributes is relevant? What is the data type (string, number, etc.) for each attribute? Can the attribute contain multiple values? Are there restrictions on the attribute's values, such as being read-only, or are they restricted to a certain range of values?
- ♦ How will this data be synchronized between the Identity Vault and the application? Some attributes will be synchronized one-way (eDirectory-to-application or vice versa), and others will be synchronized bi-directionally.
- ♦ Does your application need password synchronization? Will password synchronization be one-way or bi-directional? Restrictions might also apply to other sensitive data. You need to study the APIs for your application to determine how this should be done.
- ♦ Are there identity types or specific identities that should be excluded from synchronization? Administrative users are often excluded from synchronization to avoid security issues.
- ♦ Does data need to be transformed when it is synchronized? For example, eDirectory stores a person's first name and last name as separate attribute, but an external application might store a name as one attribute. Such transformations can be done in policies or in the scripts.

Through this process, you should make a list of the application's identity types (also known as classes), their attributes, and each attribute's data type and special properties. This list can then be specified in the driver's `schema.def` file:

```
SCHEMA
CLASS User
  ATTRIBUTE loginName NAMING REQUIRED
  ATTRIBUTE firstName
  ATTRIBUTE lastName
  (etc.)
```

The format of this `schema.def` file is the same regardless of operating system and scripting language. See [Section 5.2, “The Connected System Schema File,” on page 34](#) for more information.

5.1.2 Associating Identity Vault and Application Classes and Attributes

The next step is to examine the Identity Vault's classes and attributes and determine which best correspond to the external application's identities. If the Identity Vault does not provide a suitable class or attribute, you can define your own by modifying the Identity Vault's schema. For more information, see the [Novell eDirectory 8.7.3 Documentation Web site \(http://www.novell.com/documentation/edir873\)](http://www.novell.com/documentation/edir873).

The driver's driver filter allows the Metadirectory engine to determine which attributes and classes are relevant to the driver. For the Subscriber channel, the engine notifies the driver of changes for only those classes and attributes that are set to Synchronize in the filter. When the driver receives

application identity changes on the Publisher channel, Synchronize must be set on classes and attributes in order for those items to be changed in eDirectory. The easiest way to define a driver filter is to create a new driver with the default XML configuration file provided with the Scripting driver (`Scripting.xml`). In Novell iManager, edit the Driver Filter to include relevant classes and attributes. Then, export the driver's configuration to an XML file for later use. See [Section 5.4, "Managing Additional Attributes,"](#) on page 40 for more information.

5.1.3 Defining an Association Rule

Each identity needs an association that uniquely identifies that identity for both eDirectory and the external application. The association must be based on information shared between both the Identity Vault and the application. The association is usually based on one or more attribute values. Below are some ideas for forming an association:

- ♦ If a naming attribute is unique across all classes, you could use that attribute value.
- ♦ If a naming attribute is unique for a specific class, concatenate the attribute and class name to form the association. For example, an identity named "Bob" with the class "User" could have association "BobUser".
- ♦ In a hierarchical system (like eDirectory), you could use a name with its complete hierarchical path, assuming that it is unique. For example, an identity with a hierarchical path "Bob.Users.ACME" could use that path as its association.
- ♦ A system can provide a serial number for each identity. This unique number can be used for an association.

5.1.4 Defining Excluded Identities

You might have a list of identities that you want to exclude from synchronization. Also, if an identity is synchronized with sensitive information, you might want to reject that identity. The `include-exclude.conf` file allows such specifications:

```
EXCLUDE
  adminUser
  CLASS secureUser
```

The format of this file is the same regardless of operating system and scripting language. See [Section 5.3, "The Connected System Include/Exclude File,"](#) on page 36 for more information.

5.1.5 Defining Relevant Events

When data changes in an identity management system, an event is said to have occurred. In preparation for the next step, evaluate which event types are relevant for your application:

- ♦ **Add:** An identity is created. All required attributes must be created. Security parameters, such as a password, should be defined for the identity to ensure that security isn't compromised.
- ♦ **Modify:** One or more attributes of an existing identity are changed. This might affect identities that have a relationship to the changed identity.
- ♦ **Modify-password:** An identity's password has changed. This event type can be considered a subtype of Modify, but because it often requires special handling, it is treated as a separate event type.

- ♦ **Delete:** An identity is destroyed. This might mean permanent deletion, or a change of status of the identity so that it can be undeleted if necessary. This might affect other identities. For example, deleting a User that is a member of a Group might cause a Modify event for that Group.
- ♦ **Rename:** An identity's naming attribute has changed.
- ♦ **Move:** An identity's logical location has changed. This usually applies to identities in a hierarchical system.

An event of a certain type in one system can result in an event of a different type in the synchronized system. For example, when a Modify event occurs for an identity that does not yet exist in the external system, an Add event is submitted.

There is one more type of event that does not represent a change but is a request for information: the Query event. Novell eDirectory issues queries to your application on the Subscriber channel. You can also query eDirectory from scripts on either Subscriber or Publisher channels.

Novell eDirectory supports all of the events above. You should make a list of what the result of a particular event in eDirectory will be in your external application. Conversely, you should list what event types can occur in your external application, which event types are relevant and what the result of relevant events should be in the Identity Vault.

5.2 The Connected System Schema File

The `schema.def` file on the connected system is stored in the `schema` directory under the driver installation directory. It is used to specify the classes and attributes that are available on the system.

The schema file is read by the driver shim when the Metadirectory engine requests it. This typically happens at driver startup. The schema file is also used by the Policy Editor to map the schema of the Identity Vault to the schema of the external application.

If you change the schema file, you must restart the driver shim and the driver.

The scripts written for the driver depend on the classes and attributes in the schema file.

5.2.1 Schema File Syntax

Each line in the schema file represents an element and must begin with the element name: SCHEMA, CLASS, or ATTRIBUTE.

The first element of the schema file is the schema definition. The schema definition is followed by class definitions. Each class definition can contain attribute definitions.

Except for the values of class and attribute names, the contents of the schema file are case insensitive.

Comments

Lines that begin with an octothorpe (#) are comments.

```
# This is a comment.
```

Schema Definition

The first line in the schema file that is not a comment must be the schema definition.

```
SCHEMA [HIERARCHICAL]
```

HIERARCHICAL specifies that the target application is not a flat set of users and groups, but is organized by hierarchical components, such as a directory-based container object.

Class Definition

```
CLASS className [CONTAINER]
```

You must specify a class name. Enclose the class name in double quotes (").

Add the CONTAINER keyword if objects of this class can contain other objects.

The class definition is ended by another class definition or by the end of the file.

Attribute Definition

Any number of attribute definitions can follow a class definition. Attribute definitions define attributes for the class whose definition they follow.

```
ATTRIBUTE attributeName [TypeAndProperties]
```

An attribute name is required. Enclose the attribute name in double quotes (").

If no attribute type is specified, the attribute has the string type. The allowable types are:

- ♦ STRING
- ♦ INTEGER
- ♦ STATE
- ♦ DN

The allowable attribute properties are:

- ♦ REQUIRED
- ♦ NAMING
- ♦ MULTIVALUED
- ♦ CASESENSITIVE
- ♦ READONLY

Example Schema File

```
SCHEMA HIERARCHICAL
  CLASS "User"
    ATTRIBUTE "cn" NAMING REQUIRED
    ATTRIBUTE "Group Membership" MULTIVALUED DN
  CLASS "Group"
    ATTRIBUTE "cn" NAMING REQUIRED
    ATTRIBUTE "Group Members" MULTIVALUED DN
```

5.3 The Connected System Include/Exclude File

You can use an optional include/exclude file on the connected system to control which identities are or are not synchronized between the Identity Vault and the connected system. Create a text file named `include-exclude.conf` and save it in the `conf` directory under your driver installation directory.

The file is read when the driver shim starts. If you make changes to it, you must restart the driver shim.

The include/exclude file can contain include rules and exclude rules.

You can use the include/exclude file to phase in your deployment of the Scripting driver, excluding most users and groups at first, and then adding more as you gain confidence and experience.

Topics in this section include

- ♦ [Section 5.3.1, “Include/Exclude Processing,” on page 36](#)
- ♦ [Section 5.3.2, “Include/Exclude File Syntax,” on page 36](#)
- ♦ [Section 5.3.3, “Example Include/Exclude Files,” on page 40](#)

5.3.1 Include/Exclude Processing

Identity Vault events for identities that match an exclude rule are discarded by the Subscriber shim. Connected system events for identities that match an exclude rule are not sent to the Metadirectory engine by the Publisher shim.

Included identities are treated normally by the Subscriber and Publisher shims.

Identities that do not match an include rule or an exclude rule in the file are included.

Identities are matched in the following priority:

1. Channel-specific (Publisher or Subscriber) exclude rules
2. Channel-specific include rules
3. General exclude rules
4. General include rules

Within each level of this matching priority, identities are matched against rules in the order that the rules appear in the file. The first rule that matches determines whether the identity is included or excluded.

5.3.2 Include/Exclude File Syntax

Except for class names, attribute names, and the values to match, the contents of the include/exclude file are case insensitive.

The include/exclude file can contain any number of include sections, exclude sections, and single-line rules.

Include sections and exclude sections can contain class matching rules, and class matching rules can contain attribute matching rules. Include sections and exclude sections can also contain association matching rules.

Include and exclude sections can be contained in subscriber and publisher sections to limit their scope to the specified channel.

Class and attribute names used in the include/exclude file must correspond to the names specified in the schema file. For details about the schema file, see [Section 5.2, “The Connected System Schema File,”](#) on page 34.

Comments

Lines that begin with an octothorpe (#) are comments.

```
# This is a comment.
```

Subscriber and Publisher Sections

Subscriber and publisher sections limit the include and exclude sections they contain to the specified channel.

A subscriber section begins with a subscriber line and ends with an endsubscriber line.

```
SUBSCRIBER
.
.
.
ENDSUBSCRIBER
```

A publisher section begins with a publisher line and ends with an endpublisher line.

```
PUBLISHER
.
.
.
ENDPUBLISHER
```

Each subscriber and publisher section can contain include and exclude sections.

Include and Exclude Sections

Include and exclude sections provide rules to specify which objects are to be included or excluded from synchronization.

An include section begins with an include line and ends with an endinclude line.

```
INCLUDE
.
.
.
ENDINCLUDE
```

An exclude section begins with an exclude line and ends with an endexclude line.

```
EXCLUDE
.
.
.
ENDEXCLUDE
```

You can use class matching rules and association matching rules within an include section and an exclude section.

Class Matching Rules

Use a class matching rule within an include section or an exclude section to specify the name of a class of objects to include or exclude.

A class matching rule is defined by a class line that specifies the name of the class and ends with an endclass line.

```
CLASS className
.
.
.
ENDCLASS
```

You can use attribute matching rules within a class matching rule.

Attribute Matching Rules

You can use attribute matching rules within a class matching rule to limit the objects that are included or excluded. If no attribute matching rules are specified for a class, all objects of the specified class are included or excluded.

An attribute matching rule comprises an attribute name, an equals sign (=), and an expression. The expression can be an exact value, or it can use limited regular expressions. For details about limited regular expressions, see [“Limited Regular Expressions” on page 39](#).

```
attributeName=expression
```

Multiple attribute matching rules can be specified for a given class.

Attribute matching rules within a class matching rule are logically ANDed together. To logically OR attribute matching rules for a class, specify multiple class matching rules. For example, the following include/exclude file excludes both user01 and user02:

```
# Exclude the User object if its loginName is user01 or user02.
EXCLUDE
CLASS User
    loginName=user01
ENDCLASS
CLASS User
    loginName=user02
ENDCLASS
ENDEXCLUDE
```

Association Matching Rules

You can specify association matching rules in an include or exclude section. Association matching rule expressions can specify an exact association or a limited regular expression. For details about limited regular expressions, see [“Limited Regular Expressions” on page 39](#).

The way associations are formed can be customized for an implementation. (See [Section 5.1](#), [“Scripting Driver Data Definition,” on page 31](#) for more information.)

This example works for associations that are a concatenation of the object name and class name. To exclude the root user, specify the following:

```
EXCLUDE
    rootUser
ENDEXCLUDE
```

Single-Line Rules

[SUBSCRIBER|PUBLISHER] INCLUDE|EXCLUDE [className] objectSelection

Where objectSelection can be

{associationMatch | attributeName=expression}

Single-line rules can specify the Subscriber or Publisher channel at the start of the rule. If a channel is specified, the rule applies only to that channel. Otherwise it applies to both channels.

You must specify whether the rule is to include or exclude the objects it matches.

You can specify a class name to limit matches to only objects of that class.

You must specify either an association or an attribute matching expression. The syntax of the association and attribute matching expression is the same as that of association matching rules and attribute matching rules previously described. For details, see [“Association Matching Rules” on page 38](#) and [“Attribute Matching Rules” on page 38](#).

For example, to ignore events from the ADMIN user in the Identity Vault, code:

```
# Do not subscribe to events for the ADMIN user.
SUBSCRIBER EXCLUDE adminUser
```

Limited Regular Expressions

A limited regular expression is a pattern used to match a string of characters.

Character matching is case sensitive.

Any literal character matches that character.

A period (.) matches any single character.

A bracket expression is a set of characters enclosed by left ([) and right (]) brackets that matches any listed character. Within a bracket expression, a range expression is a pair of characters separated by a hyphen, and is equivalent to listing all of the characters that sort between the given characters, inclusive. For example, [0-9] matches any single digit.

An asterisk (*) indicates that the preceding item is matched zero or more times.

A plus sign (+) indicates that the preceding item is matched one or more times.

A question mark (?) indicates that the preceding item is matched zero or one times.

You can use parentheses to group multiple expressions into a single item. For example, (abc)+ matches abc, abcabc, abcabcabc, etc. Nesting of parentheses is not supported.

5.3.3 Example Include/Exclude Files

- ♦ “Example 1” on page 40
- ♦ “Example 2” on page 40
- ♦ “Example 3” on page 40

Example 1

```
# Exclude users whose names start with temp
EXCLUDE
    CLASS User
        loginName=temp.*
    ENDCLASS
ENDEXCLUDE
```

Example 2

```
# Exclude usera and userb
# Because attribute rules are ANDed, these must be in separate
# CLASS sections.
EXCLUDE
    CLASS User
        loginName=usera
    ENDCLASS
    CLASS User
        loginName=userb
    ENDCLASS
ENDEXCLUDE
```

Example 3

```
# Exclude all users except those whose names start with idm
# This works because channel-specific matching takes precedence
# over general matching.
EXCLUDE
    CLASS User
    ENDCLASS
ENDEXCLUDE

SUBSCRIBER INCLUDE User loginName=idm.*
PUBLISHER INCLUDE User loginName=idm.*
```

5.4 Managing Additional Attributes

You can add additional attributes to the driver for both the Publisher and Subscriber channels. These attributes can be accessed by the scripts for all event types.

To publish or subscribe to additional attributes, you must add them to the filter and add support for them into the scripts. Topics in this section include

- ♦ Section 5.4.1, “Modifying the Filter,” on page 41
- ♦ Section 5.4.2, “Modifying the Scripts for New Attributes,” on page 41

5.4.1 Modifying the Filter

- 1 On the iManager Driver Overview page for the driver, click the Filter icon on either the Publisher or Subscriber channel. It is the same object.
- 2 In the Filter Edit dialog box, click the class containing the attribute to be added.
- 3 Click *Add Attribute*, then select the attribute from the list.
- 4 Select the flow of this attribute for the Publisher and Subscriber channels.
 - ♦ **Synchronize:** Changes to this object are reported and automatically synchronized.
 - ♦ **Ignore:** Changes to this object are not reported and not automatically synchronized.
 - ♦ **Notify:** Changes to this object are reported, but not automatically synchronized.
 - ♦ **Reset:** Resets the object value to the value specified by the opposite channel. (You can set this value on either the Publisher or Subscriber channel, but not both.)
- 5 Click *Apply*.
- 6 If you want to map this attribute to an existing attribute in the connected system's schema, modify the Schema Mapping policy for the driver.

For complete details about managing filters and Schema Mapping policies, see Policies in the *iManager for Identity Manager 3.5 Guide*.

5.4.2 Modifying the Scripts for New Attributes

In the Subscriber channel, scripts are called to take the appropriate action for each type of event. You will need to modify the appropriate scripts to read the values from the new attributes.

Publishing additional attributes requires that you act on changes made in the connected system application. In addition, the schema.def file should be updated with the additional attributes (see [Section 5.2, “The Connected System Schema File,” on page 34](#)).

5.5 UNIX Shell Developer Guide

The Scripting driver provides a complete Shell script API for interacting with identity management systems whose tools (including APIs) are available on Linux and UNIX. The Identity Vault and Identity Manager can run on any supported operating system. Identity Manager communicates with the driver on a different system over an encrypted network connection.

Before beginning script development, review the preceding topics in this section for information on defining what data will be synchronized between identity management systems.

With additional development work, the driver can also be customized to support any scripting language that supports command-line operation.

Developing a custom driver with Shell scripts is discussed in the following topics:

- ♦ [Section 5.5.1, “Application Tools Evaluation,” on page 42](#)
- ♦ [Section 5.5.2, “Policy and Script Development,” on page 42](#)
- ♦ [Section 5.5.3, “Deployment,” on page 54](#)

5.5.1 Application Tools Evaluation

In order to change the data in your external application, you need to know how to use the application's tools or API (Application Programming Interface). These tools must provide automated operation and not require user input.

Application Command Line Tools

An application often provides command line tools. These tools are manually executed from a shell, and they can be executed from scripts. Suppose the application provides a tool to add identities with a program called `appadd`.

```
appadd -n "Bob Smith" -t "818-555-2100"
```

This command adds an identity named “Bob Smith” with the specified phone number. The strings following the program name are called parameters or arguments. The Linux and UNIX Scripting driver provides a function called `EXEC` to execute external programs, log the command to the system log and produce a status document indicating the level of success.

```
CommandLine="appadd -n $UserName -t $PhoneNumber"  
EXEC $CommandLine
```

For command line tools, you can construct the command line's parameters using the values passed to the script, then execute the program.

Application Event Monitoring

You also need to determine what tools are available for monitoring event changes in the application. The Scripting driver works on a polling system. It periodically calls a polling script to determine what has changed in the external application. You can use the following ideas for monitoring changes:

- ♦ The first time the polling script is run, a list of identities and relevant attributes is read from the application using an application-provided tool. This list is stored as a file. On subsequent polls, a new list is generated and compared to the old list. Any differences are submitted as events to the driver.
- ♦ The application provides a tool that allows you to request all identities that have changed after a certain point in time. The polling script requests events that have occurred since the previous poll.
- ♦ The application allows a script to be run when an event occurs. You can write a script that stores the event data into a file. When the Script driver polling script runs, it consumes this file and submits the data as an event to the driver using the change log tool, `usclh`. For detailed information on `usclh`, see [Section D.3, “Publisher Change Log Tool,” on page 123](#)

Monitoring the application's changes might be the most difficult aspect of developing your driver. You must study your application's tools to determine the best way to achieve synchronization.

5.5.2 Policy and Script Development

At this point you should have a list of what data will be synchronized, how events will be handled and what application tools are available. It is time to develop the heart of your driver in policies and scripts.

Many types of tasks can be handled in driver policies. You can import the driver configuration provided with the Scripting driver, and then edit policies in Novell iManager. You can also edit policies and simulate their operation in Novell Designer. The extensive functionality of policies is outside the scope of this document, so you should refer to the appropriate publications at [the Identity Manager 3.6.1 Documentation Web site \(http://www.novell.com/documentation/idm36\)](http://www.novell.com/documentation/idm36).

It's often difficult to write complex tasks inside policies, such as executing external commands, processing input and output, and file I/O. Tasks requiring such operations are better suited in scripts, where an entire language environment and tools are available. You can also accomplish many of the operations performed in policies, so if you are more familiar with your scripting language than policies, you can develop your driver more quickly by using scripts. Scripting languages such as Perl and Shell scripts offer an environment that is often well suited for your target application's APIs or developer kits. For example, your target application might already contain Perl library routines for manipulating the application's identities.

Event Data Format

Event data is submitted to the scripts in name/value pair format. This format consists of lines containing a name, an equal sign (=) and a value. Therefore each line is a name/value pair. Each name/value pair is unique, but there can be multiple name/value pairs with identical names but different values.

```
ASSOCIATION=BobUser
ADD_TELEPHONE=818-555-2100
ADD_TELEPHONE=818-555-9842
```

You typically don't need to worry about the format. The script library provides functions for retrieving event data.

Subscriber Script Development

After all Policy processing is complete, Identity Manager submits the event in XML format to the driver shim. The driver shim submits the event data to the scripts.

In the default Scripting driver, the `subscriber.sh` script in the `scripts` folder is called. This script does some preliminary processing, and then calls a routine from an included script. The included scripts correspond to the Subscriber event types: `add.sh`, `modify.sh`, `modify-password.sh`, `delete.sh`, `rename.sh`, `move.sh`, and `query.sh`.

For each event type, you should retrieve the information you need from the event data, submit changes to the external application using application-provided tools, and return a status (such as success or failure) to Identity Manager.

Event data is retrieved primarily using the `IDMGETVAR` function. For detailed information on how to use `IDMGETVAR`, see [Section C.1, "UNIX Shell \(idmlib.sh\) Reference," on page 109](#). This function returns an array of values corresponding to the name specified as the function's parameter. The following table shows many item names.

Table 5-1 *Items*

Name	Description
COMMAND	The command for the event, usually indicating the event type. Possible values are: add, modify, delete, rename, modify-password, check-object-password.
ASSOCIATION	The identifier that distinguishes an identity on both identity management systems.
CLASS_NAME	An identity's class, such as User or Group.
SRC_DN	An identity's distinguished name (DN) in the namespace of the source (sender), in slash format.
EVENT_ID	An identifier for the event, for internal use.
SRC_ENTRY_ID	An identifier for the identity that generated the event, in the namespace of the source (sender).
DEST_DN	An identity's distinguished name (DN) in the namespace of the destination (receiver), in slash format.
DEST_ENTRY_ID	An identifier for an entry in the namespace of the destination (receiver).
ADD_{attr_name}	A value to be added to an identity, for attribute {attr_name}.
REMOVE_{attr_name}	A value to be removed from an identity, for attribute {attr_name}.
ADD_REF_{attr_name}	A value to be added to attribute {attr_name}, where the value is an association referring to another identity.
REMOVE_REF_{attr_name}	A value to be removed from attribute {attr_name}, where the value is an association referring to another identity.
OLD_PASSWORD	The previous password for an identity that has changed its password. Used in Modify Password events.
PASSWORD	The new password for an identity. Used in Add and Modify Password events.
OLD_SRC_DN	The distinguished name of an identity before a Move or Rename event.
REMOVE_OLD_NAME	Specifies whether an old relative distinguished name should be deleted or retained. Used in Rename events.
STATUS_LEVEL	The status of an event: success, warning, retry, error or fatal.
STATUS_MESSAGE	A message to report with a status.
STATUS_TYPE	A type of status, such as heartbeat.

Examples Of Obtaining Event Data

Example 1:

```

command='IDMGETVAR "COMMAND"\'
# check for an add event
if [ "$command" = "add" ]; then
    # call the add script
    add.sh
fi

```

Example 2:

```

# obtain the event's association and CN attribute
ASSOCIATION='IDMGETVAR "ASSOCIATION"\'
CN='IDMGETVAR "ADD_CN"\'
if [ "$CN" = "bob" ]; then
    # for "bob", check to see if he's been enabled
    ENABLE='IDMGETVAR "REMOVE_Login Disabled"\'
    if [ "$ENABLE" = "true" ]; then
        # bob is enabled again
        cmd="appenable -association $ASSOCIATION"
        EXEC "$cmd"
    fi
fi

```

Handling Associations

The association value indicates which identity has been changed. If the identity has no association, an association must be generated for it using an implementation-specific rule that you have adopted. When Identity Manager processes an event for an identity with no association, it executes the driver's Matching policy. This policy attempts to match the event's identity to an identity on the external application's system. Usually doing this involves executing a query. The default Matching policy included with the Scripting driver queries for matching Users and Groups based on the CN attribute. If the event's identity matches an identity on the external application, both identities must be assigned the new association. Assigning this association can be done as part of the query-handling script. (Handling queries is discussed in more detail in [“Handling Query Events” on page 47](#).) If no identity matches, an Add event is issued, and the new association can be assigned as part of the Add event-handling script:

```

# Adding an association
IDMSETVAR "COMMAND" "ADD_ASSOCIATION"
IDMSETVAR "ASSOCIATION" "$MyAssociation"
IDMSETVAR "EVENT_ID" "$EVENT_ID"
IDMSETVAR "DEST_DN" "$SRC_DN"
IDMSETVAR "DEST_ENTRY_ID" "$SRC_ENTRY_ID"

```

The above example demonstrates each name/value pair that must be set for an association to be assigned by the Identity Manager engine. The values of `EVENT_ID`, `SRC_DN` and `SRC_ENTRY_ID` are always sent by the engine during an add event, and therefore, are available for your add script to obtain using `IDMGETVAR`. The example above also illustrates the `IDMSETVAR` function. For detailed information on how to use `IDMSETVAR`, see [Section C.1, “UNIX Shell \(idmlib.sh\) Reference,” on page 109](#). This function sets a name and value which indicates what action Identity Manager should perform. For example, the pair `COMMAND` and `ADD_ASSOCIATION` instructs the shim to create an add-association document to assign an association to an identity, as discussed above. The pair `EVENT_ID` and `$EVENT_ID` instruct the shim to assign add-association document an event-id described by the variable `$EVENT_ID`. This is important for the engine to match documents sent and returned on the subscriber channel.

The Subscriber can also issue `MODIFY_ASSOCIATION` and `REMOVE_ASSOCIATION` commands:

```
# Removing an association
IDMSETVAR "COMMAND" "REMOVE_ASSOCIATION"
IDMSETVAR "ASSOCIATION" "$MyAssociation"
IDMSETVAR "EVENT_ID" "$EVENT_ID"
IDMSETVAR "DEST_DN" "$SRC_DN"
IDMSETVAR "DEST_ENTRY_ID" "$SRC_ENTRY_ID"

# Modifying an association
IDMSETVAR "COMMAND" "MODIFY_ASSOCIATION"
IDMSETVAR "ASSOCIATION" "$OldAssociation"
IDMSETVAR "ASSOCIATION" "$NewAssociation"
IDMSETVAR "EVENT_ID" "$EVENT_ID"
IDMSETVAR "DEST_DN" "$SRC_DN"
IDMSETVAR "DEST_ENTRY_ID" "$SRC_ENTRY_ID"
```

Returning an Event Status

On the Subscriber channel, you often do not need Identity Manager to perform an action, but simply need to report a status. The STATUS_ subroutines noted below can be used to indicate a status to Identity Manager. They take a message to be logged as their parameter.

Table 5-2 Status Subroutines

Subroutine	Identity Manager Action
STATUS_SUCCESS	Identity Manager marks the event as a success and submits the next event in the event queue, if any. You should issue this status even if your script does nothing.
STATUS_WARNING	The event can be processed, but it might require attention. Identity Manager issues your warning message in its log, and then submits the next event.
STATUS_RETRY	The event cannot be processed, but Identity Manager should resubmit the event because it should be able to be processed soon. This status can be issued if your external application appears to be temporarily unavailable. However, this status should be used cautiously because a backlog results if Identity Manager continually retries one event.
STATUS_ERROR	The event cannot be processed and it should not be resubmitted. Identity Manager issues the error message and submits the next event. You should make a detailed error message so the problem can be corrected.
STATUS_FATAL	For some reason, the driver must be stopped. Identity Manager issues your message and stops the driver. This could be used if the external application appears to be permanently offline. The event remains in the queue and is resubmitted when the driver is restarted.

Examples Using the STATUS Functions

Example 1:

```
EXEC "$cmd"
if [ $? -eq 0 ]; then
    STATUS_SUCCESS "Command was successful"
fi
```

Example 2:

```
EXEC "$cmd"
if [ $? -eq 0 ]; then
    if [ -z "$password" ]; then
        # created, but no password
        STATUS_WARNING "User added without password"
    fi
fi
```

Example 3:

```
EXEC "$cmd"
if [ $? -ne 0 ]; then
    STATUS_ERROR "Command failed"
fi
```

Writing Values

IDMSETVAR is used to set values to return to Identity Manager. For detailed information on how to use IDMSETVAR, see [Section C.1, “UNIX Shell \(idmlib.sh\) Reference,” on page 109](#). It is passed a name and value. In the previous ADD_ASSOCIATION example, IDMSETVAR is used to set the ASSOCIATION value. You can specify values for items listed in the table above. Generally, the only time IDMSETVAR is used is to add, modify and delete associations or return information for a query operation. Other information returned to the shim by the scripts is done through other command functions, such as STATUS_SUCCESS, which use IDMSETVAR indirectly.

Handling Query Events

For Query events, Identity Manager submits values that define the parameters of a search of the external application’s identity management system. Queries are usually issued from the Policies you have defined for your system. The table below specifies values that can be specified in queries. Not all values are relevant to your external application.

Table 5-3 *Values for Queries*

Value Name	Description
SCOPE	Specifies what identities will be searched. A base object is specified with the ASSOCIATION or DEST_DN values (see below). The value “entry” means that only the base object is searched. The value “subordinates” means that the immediate subordinates of the base object are searched. The value “subtree” (the default) indicates that the base object and all subordinates are searched. The last two values are only relevant in a hierarchical system.
ASSOCIATION	The base object for the search. If both ASSOCIATION and DEST_DN have values, ASSOCIATION is used. If neither is specified, the base object is the root of the identity management system.
DEST_DN	The base object for the search (see also ASSOCIATION above).
CLASS_NAME	The base class of the base object.
EVENT_ID	An identifier for the event.

Value Name	Description
SEARCH_CLASSES	A list of classes for which to search. Only identities of these classes are returned. If not specified, all identities in the scope matching SEARCH_ATTR_ values are returned (see below).
SEARCH_ATTRS	A list of the attribute names specified in SEARCH_ATTR_ values (see below).
SEARCH_ATTR_{attr_name}	A value that the specified attribute must match. Replace {attr_name} with the desired attribute name. Only identities matching all SEARCH_ATTR_ filters are returned.
READ_ATTRS	A list of the attribute names whose values are returned for each matching identity.
ALL_READ_ATTRS	The presence of this value indicates that all attribute values should be returned for matching identities.
NO_READ_ATTRS	The presence of this value indicates that no attribute values should be returned for matching identities.
READ_PARENT	The presence of this value indicates that the parent object of each matching identity should be returned. Only relevant in hierarchical systems.

Execute the query against the external application using application-provided tools. Then return each identity by setting an `INSTANCE` command, followed by relevant values from the list below.

Table 5-4 *Query Instance Values*

Value Name	Description
CLASS_NAME	The class of the identity. Required.
SRC_DN	A distinguished name representing the logical location of the identity in the system (optional).
ASSOCIATION	The association of the identity, if available (optional).
PARENT	The association of the parent object of the identity (optional). Only relevant in hierarchical systems.
ATTR_{attr_name}	A list of values for the attribute specified by {attr_name}. Return attribute values specified by the READ_ATTRS value.

After returning all identities, call `STATUS_SUCCESS` to indicate a successful query.

Subscriber Summary and Examples

Below is a more detailed summary of the actions to take for a non-Query event.

- 1 Gather information about the event using `IDMGETVAR`. Return a warning or error if there is a problem.
- 2 Submit the event data to the external application using application-provided tools.
- 3 Set return values with `IDMSETVAR`.
- 4 If you have not already done so, set a status with a `STATUS_` subroutine.

Below is an example `add.sh`, which forms an association from an identity's CN and class name, and uses a hypothetical tool called `appadd`.

```
#!/bin/sh
ClassName=`IDMGETVAR "CLASS_NAME"` CN=`IDMGETVAR "CN"`
EVENT_ID=`IDMGETVAR "EVENT_ID"`
SRC_DN=`IDMGETVAR "SRC_DN"`
SRC_ENTRY_ID=`IDMGETVAR "SRC_ENTRY_ID"`
PhoneNumber=`IDMGETVAR "Telephone"`

if [ -z "$ClassName" -o -z "$CN" ]; then
    STATUS_ERROR "Add event: missing CLASS_NAME and/or CN"
else
    Command="appadd -n $CN -t $PhoneNumber"
    EXEC $Command
    if [ $? -eq 0 ]; then
        IDMSETVAR "COMMAND" "ADD_ASSOCIATION"
        IDMSETVAR "ASSOCIATION" "${CN}${ClassName}"
        IDMSETVAR "EVENT_ID" "$EVENT_ID"
        IDMSETVAR "DEST_DN" "$SRC_DN"
        IDMSETVAR "DEST_ENTRY_ID" "$SRC_ENTRY_ID"

        STATUS_SUCCESS "Add event succeeded"
    else
        STATUS_ERROR "Add event failed with error code $RC"
    fi
fi
```

Handling a query is a similar process, except that you return `INSTANCE` items rather than using other commands. Below is an example `query.sh` that searches an external application for a telephone number. It uses a hypothetical tool called `appsearch`.

```
#!/bin/sh
SearchName=`IDMGETVAR "SEARCH_ATTR_CN"`
EVENT_ID=`IDMGETVAR "EVENT_ID"`
ASSOCIATION=`IDMGETVAR "ASSOCIATION"`
CLASS_NAME=`IDMGETVAR "CLASS_NAME"`

if [ -z "$SearchName" ]; then
    STATUS_ERROR "Query: no search value"
else
    Command="appsearch -n $SearchName"
    Results=`$Command`
    if [ -n "$Results" ]; then
        Phone=`echo $Results | awk '{print $1}'`
        IDMSETVAR "COMMAND" "INSTANCE"
        IDMSETVAR "EVENT_ID" "$EVENT_ID"
        IDMSETVAR "CLASS_NAME" "$CLASS_NAME"
        IDMSETVAR "ASSOCIATION" "$ASSOCIATION"
        IDMSETVAR "ATTR_Telephone" "$Phone"

        STATUS_SUCCESS "Query succeeded"
    else
        # Return success with no results
        STATUS_SUCCESS "Query succeeded (no matches)"
    fi
fi
```

Publisher Script Development

Events that occur on the external application are submitted to Identity Manager on the Publisher channel. The Scripting driver periodically polls the external application for events. How this poll detects events is implementation-specific and must be defined by you.

Polling for Application Events

The Driver calls `poll.sh` to detect application events. Implement `poll.sh` as follows:

- 1 Use application-provided tools to detect events in your application, as discussed in Step 2.
- 2 For each event, call the changelog tool `usclh` to submit the event to be published. The changelog tool allows for additional information to be supplied through standard input. This is an appropriate mechanism for passing data that might be too large for command line or too sensitive to appear in a shell's history or environment. For detailed information on `usclh`, see [Section D.3, "Publisher Change Log Tool," on page 123](#).

The following is an example of a `poll.sh` that checks for a password change. It uses a hypothetical application tool called `appchg`.

```
#!/bin/sh
# look for password changes
Results=`appchg --passwd-changes`
for Result in $Results; do
    # Entries are in the format "association:password"
    Association=`echo $Result | awk -F: '{print $1}'`
    Password=`echo $Result | awk -F: '{print $2}'`

    # submit a password change event
    usclh -t modify-password -a $Association <<EOF
$Password
EOF
done

# look for attribute values being added to each user
Results=`appchg --add-attr-changes`
for Result in $Results; do
    # Entries are in the format "association:attribute:value"
    Association=`echo $Result | awk -F: '{print $1}'`
    Attribute=`echo $Result | awk -F: '{print $2}'`
    Value=`echo $Result | awk -F: '{print $3}'`

    # submit the added attribute value
    usclh -t modify -c User -a $Association <<EOF
ADD_$Attribute=$Value
EOF
done

# look for attribute values being removed from each user
Results=`appchg --remove-attr-changes`
for Result in $Results; do
    # Entries are in the format "association:attribute:value"
    Association=`echo $Result | awk -F: '{print $1}'`
    Attribute=`echo $Result | awk -F: '{print $2}'`
    Value=`echo $Result | awk -F: '{print $3}'`
```

```
# submit the removed attribute value
usclh -t modify -c User -a $Association <<EOF
REMOVE_ $Attribute=$Value
EOF
done
```

In the above example, three separate events are submitted to the publisher change log using the change log tool, `usclh`. The first invocation submits a modify-password event to be published. The second event submits a modify event to be published for an attribute add. The third invocation submits another modify event to be published for an attribute removal. The second and third invocations can be combined into a single modify event, if desired.

Events submitted using `usclh` are processed through your driver's Publisher channel policies. See your [Identity Manager 3.6.1 Policy guides \(http://www.novell.com/documentation/idm36\)](http://www.novell.com/documentation/idm36) for more information.

Using the Heartbeat Script

Another script executed in the Publisher Channel is `heartbeat.sh`. This script is executed when the Publisher Channel is idle for the interval specified in the Driver parameters. (You can set the interval to 0 so no heartbeat is issued.) You can use the heartbeat to check the availability of the external system or do "idle state" tasks. The `HEARTBEAT_SUCCESS`, `HEARTBEAT_WARNING`, and `HEARTBEAT_ERROR` subroutines can be used to indicate the result of the heartbeat. Below is an example based on a hypothetical tool called `apphealth`.

```
apphealth
RC=$?
if [ $RC -eq 0 ]; then
    HEARTBEAT_SUCCESS "Heartbeat succeeded"
else
    HEARTBEAT_ERROR "Heartbeat failed with error code $RC"
fi
```

The response to the heartbeat is implementation-dependent, and can be defined in Policies or in the script itself. You could send a message to auditing using Novell Audit. You could store a value in a file, and have Subscriber scripts read the file and call `STATUS_RETRY` if they find that value in the file.

Other Scripting Topics

- ♦ "Driver Parameters" on page 51
- ♦ "Querying the Identity Vault" on page 52
- ♦ "Tracing and Debugging" on page 53

Driver Parameters

A driver has values known as driver parameters. The driver parameters are divided into driver settings applicable to the whole driver, and Subscriber and Publisher settings for their respective channels. The `IDMGETDRVVAR`, `IDMGETSUBVAR`, and `IDMGETPUBVAR` functions can be used to retrieve these values. The table below shows parameters in the default Scripting driver. Other parameters can be added to the driver's XML configuration file see [*Identity Manager 3.6.1 Common Driver Administration Guide*](#).

Table 5-5 *Scripting Driver Parameters*

Parameter Name	Driver/Channel	Description	Values
INSTALL_PATH	Driver	The installation path of the Driver	string value
auto-loopback-detection	Driver	Whether to enable automatic loopback detection	true/false
subscriber-script	Subscriber	The root script file for Subscriber events, relative to the Driver installation path	string value
pub-polling-interval	Publisher	The interval in seconds between Publisher polls for application events	number
pub-heartbeat-interval	Publisher	The amount of idle time in seconds before a heartbeat event is issued	number
pub-disabled	Publisher	Whether the Publisher Channel (i.e., polling) is disabled	true/false

In the following example, a script retrieves the Publisher polling interval.

```
PollingInterval=`IDMGETPUBVAR "pub-polling-interval" `
```

Querying the Identity Vault

Scripts might need to retrieve information from the Identity Vault. They can do this by issuing a query.

1 Execute the query by calling IDMQUERY with the appropriate parameters:

- ♦ The first parameter is the class-name
- ♦ The second parameter is the association of the object to query
- ♦ The third parameter are the attributes to read, comma-separated

2 Read the result (instance) using IDMGETQVAR.

Query support is currently limited. It only returns one instance based on the specified association or DN. (If both association and DN are specified, association is used.) The functions below allow you to retrieve information from the instance.

The following is an example of a query of the Identity Vault that retrieves the address and ZIP code for user Bob.

```
IDMQUERY "User" "Bob" "SA,Postal Code"

Address=`IDMGETQVAR "SA" `
ZIPCode=`IDMGETQVAR "Postal Code" `
# ... etc. ...
```

Tracing and Debugging

The IDMTRACE function allows you to write a message to the Trace Log. Tracing is useful for script debugging and auditing.

```
IDMTRACE "Trace message"
```

When developing scripts, you might need to do some debugging to track down problems. The following list indicates some facilities for debugging.

- ♦ The Driver traces activity to its Trace file (`logs/trace.log` by default). The trace level setting in `conf/usdrv.conf` controls how much debugging is written to the log.

Trace Level	Description
0	No debugging.
1-3	Identity Manager messages. Higher trace levels provide more detail.
4	Previous level plus Remote Loader, driver, driver shim, and Driver connection messages.
5-7	Previous level plus Change Log and loopback messages. Higher trace levels provide more detail.
8	Previous level plus Driver status log, Driver parameters, Driver command line, Driver security, Driver Web server, Driver schema, Driver encryption, Driver SOAP API, and Driver include/exclude file messages.
9	Previous level plus low-level networking and operating system messages.
10	Previous level plus maximum low-level program details.

The trace level is set using the `-trace` option in `usdrv.conf`, for example `-trace 9`.

You can view the trace file through a Web browser:

1. Use a Web browser to access the driver shim at `https://driver-address:8091`. Substitute the DNS name or IP address of your driver for `driver-address`.
 2. Authenticate by using any username and the password that you specified as the Remote Loader password.
 3. Click *Trace*.
- ♦ The IDMTrace function described above writes output to the trace file specified in the Driver Parameters (`logs/script-trace.log` by default).
 - ♦ The eDirectory tool DSTrace can be used to monitor Identity Manager activity. Set the tracing level for the driver in iManager. DSTrace shows the XML documents being submitted to the driver for events, and how Policies are evaluated. It also shows the status and message for each event.
 - ♦ The Status Log is written to `logs/dirxml.log`. It shows a summary of the events that have been recorded on the Subscriber and Publisher channels.

You can view the Status Log through a Web browser:

1. Use a Web browser to access the driver shim at `https://driver-address:8091`. Substitute the DNS name or IP address of your driver for `driver-address`.

2. Authenticate by using any username and the password that you specified as the Remote Loader password.
3. Click *Status*.

Although it is best to start the driver in production environments from the startup script, you can run `usdrv` manually. When you do so, any text written to standard output from scripts is displayed in the interactive shell.

5.5.3 Deployment

The Scripting driver is installed by using a setup program. See [Section 3.1, “Installing the Linux and UNIX Scripting Driver,” on page 19](#) for more information on installing the default driver.

Deploying a Custom Driver

To deploy your custom driver, the end user should first run the Scripting driver installation program provided by the installation media ([Section 3.1, “Installing the Linux and UNIX Scripting Driver,” on page 19](#)). This program installs core files needed by the driver. Then, your custom driver files can be deployed in any convenient way, whether through an installation program or even simply an archive file. The table below shows the directory structure below the installation directory and what files are installed.

Table 5-6 *Installation Directories and Files*

Directory	Description	Required Files
<code>bin/</code>	Location of executable programs	<code>usdrv</code> <code>ussmh</code> <code>usclh</code>
<code>changelog/</code>	Used for Publisher event processing	None
<code>conf/</code>	Location of the driver shim configuration file	<code>usdrv.conf</code> (customized)
<code>keys/</code>	Location of security key files	None
<code>logs/</code>	Location of log files	None
<code>loopback/</code>	Used for automatic loopback detection	None
<code>rules/</code>	Location of Driver configuration file	<code>Scripting.xml</code> (customized)
<code>schema/</code>	Location of schema files	<code>schema.def</code> (customized)
<code>scripts/</code>	Location of script files	

On Linux and UNIX, the Scripting driver is installed to `/opt/novell/usdrv`.

The formats of `usdrv.conf` and `schema.def` can be viewed in [Section 4.2, “The Driver Shim Configuration File,” on page 29](#) and [Section 5.2, “The Connected System Schema File,” on page 34](#).

If SSL encryption is desired for communication between the driver shim and Identity Manager engine, a certificate must be retrieved from the Identity Vault. Run `usdrv -s` and follow the prompts to retrieve the certificate, which will be stored in the `keys/` directory. You must have LDAP with SSL available for the Metadirectory. When making an installation program for deployment, you might want to run `usdrv -s` as part of the installation.

To ensure that only authorized systems access the Metadirectory, a Driver Object Password and Remote Loader Password are used. Run `usdrv -sp` and enter the passwords at the prompts. This action can be incorporated into an installation program.

You should distribute the XML configuration file that contains parameters and policies your Driver needs. The user can then select it when installing your Driver.

5.6 Perl Developer Guide

The Scripting driver provides a complete Perl API for interacting with identity management systems whose tools (including APIs) are available on Linux and UNIX. The Identity Vault and Identity Manager can run on any supported operating system. Identity Manager communicates with the driver on a different system over an encrypted network connection.

Before beginning script development, review the preceding topics in this section for information on defining what data is synchronized between identity management systems.

With additional development work, the driver can also be customized to support any scripting language that supports command-line operation.

Developing a custom driver with Perl scripts is discussed in this section. Topics include

- ♦ [Section 5.6.1, “Application Tools Evaluation,” on page 55](#)
- ♦ [Section 5.6.2, “Policy and Script Development,” on page 56](#)
- ♦ [Section 5.6.3, “Deployment,” on page 68](#)

5.6.1 Application Tools Evaluation

In order to change the data in your external application, you need to know how to use the application’s tools or API (Application Programming Interface). These tools must provide automated operation and not require user input.

Application Command Line Tools

An application often provides command line tools. These tools are manually executed from the command line, and they can be executed from scripts. For example, suppose the application provides a tool to add identities with a program called `appadd`.

```
appadd -n "Bob Smith" -t "818-555-2100"
```

This command adds an identity named “Bob Smith” with the specified phone number. The strings following the program name are called parameters or arguments. The Linux and UNIX Scripting driver provides a function called `exec` to execute external programs, log the command to the system log, and produce a status document indicating the level of success.

```
$CommandLine="appadd -n $; UserName -t $PhoneNumber";  
$idmlib = new IDMLib();  
$idmlib->exec($CommandLine);
```

For command line tools, you can construct the command line's parameters using the values passed to the script, then execute the program.

Application Event Monitoring

You also need to determine what tools are available for monitoring event changes in the application. The Scripting driver works on a polling system. It periodically calls a polling script to determine what has changed in the external application. You can use the following ideas for monitoring changes:

- ♦ The first time the polling script is run, a list of identities and relevant attributes is read from the application using an application-provided tool. This list is stored as a file. On subsequent polls, a new list is generated and compared to the old list. Any differences are submitted as events to the driver.
- ♦ The application provides a tool that allows you to request all identities that have changed after a certain point in time. The polling script requests events that have occurred since the previous poll.
- ♦ The application allows a script to be run when an event occurs. You can write a script that stores the event data into a file. When the Script driver polling script runs, it consumes this file and submits the data as an event to the driver using the `usclh change log` tool. For detailed information on `usclh`, see [Section D.3, “Publisher Change Log Tool,” on page 123](#).

Monitoring the application's changes might be the most difficult aspect of developing your driver. You must study your application's tools to determine the best way to achieve synchronization.

5.6.2 Policy and Script Development

At this point you should have a list of what data will be synchronized, how events will be handled, and what application tools are available. It is time to develop the heart of your driver in policies and scripts.

Many types of tasks can be handled in driver policies. You can import the driver configuration provided with the Scripting driver, and then edit policies in Novell iManager. You can also edit policies and simulate their operation in Novell Designer. The extensive functionality of policies is outside the scope of this document, and so you should refer to your [Identity Manager 3.6.1 Policy guides \(http://www.novell.com/documentation/idm36\)](http://www.novell.com/documentation/idm36) for help.

It's often difficult to write complex tasks inside policies, such as executing external commands, processing input and output, and file I/O. Tasks requiring such operations are better suited in scripts, where an entire language environment and tools are available. You can also accomplish many of the operations performed in policies, so if you are more familiar with your scripting language than policies, you can develop your driver more quickly by using scripts. Scripting languages such as Perl and Shell scripts offer an environment that is often well suited for your target application's APIs or developer kits. For example, your target application might already contain Perl library routines for manipulating the application's identities.

Event Data Format

Event data is submitted to the scripts in name/value pair format. This format consists of lines containing a name, an equal sign (=) and a value. Therefore, each line is a name/value pair. Each name/value pair is unique, but there can be multiple name/value pairs with identical names but different values.


```
ASSOCIATION=BobUser
ADD_TELEPHONE=818-555-2100
ADD_TELEPHONE=818-555-9842
```

You typically don't need to worry about the format. The script library provides functions for retrieving event data.

Subscriber Script Development

After all Policy processing is complete, Identity Manager submits the event in XML format to the driver shim. The driver shim submits the event data to the scripts.

In the default Scripting driver, the `subscriber.pl` script in the `scripts` folder is called. This script does some preliminary processing, and then calls a routine from an included script. The included scripts correspond to the Subscriber event types: `add.pl`, `modify.pl`, `modify-password.pl`, `delete.pl`, `rename.pl`, `move.pl`, and `query.pl`.

For each event type, you should retrieve the information you need from the event data, submit changes to the external application using application-provided tools and return a status (such as success or failure) to Identity Manager.

Event data is retrieved primarily by using the `$idmlib->idmgetvar()` function. This function returns an array of values corresponding to the name specified as the function's parameter. The following table shows many item names.

Table 5-7 *Item Names*

Name	Description
COMMAND	The command for the event, usually indicating the event type. Possible values are: <code>add</code> , <code>modify</code> , <code>delete</code> , <code>rename</code> , <code>modify-password</code> , <code>check-object-password</code> .
ASSOCIATION	The identifier that distinguishes an identity on both identity management systems.
CLASS_NAME	An identity's class, such as <code>User</code> or <code>Group</code> .
SRC_DN	An identity's distinguished name (DN) in the namespace of the source (sender), in slash format.
EVENT_ID	An identifier for the event, for internal use.
SRC_ENTRY_ID	An identifier for the identity that generated the event, in the namespace of the source (sender).
DEST_DN	An identity's distinguished name (DN) in the namespace of the destination (receiver), in slash format.
DEST_ENTRY_ID	An identifier for an entry in the namespace of the destination (receiver).
ADD_{attr_name}	A value to be added to an identity, for attribute {attr_name}.
REMOVE_{attr_name}	A value to be removed from an identity, for attribute {attr_name}.
ADD_REF_{attr_name}	A value to be added to attribute {attr_name}, where the value is an association referring to another identity.

Name	Description
REMOVE_REF_{attr_name}	A value to be removed from attribute {attr_name}, where the value is an association referring to another identity.
OLD_PASSWORD	The previous password for an identity that has changed its password. Used in Modify Password events.
PASSWORD	The new password for an identity. Used in Add and Modify Password events.
OLD_SRC_DN	The distinguished name of an identity before a Move or Rename event.
REMOVE_OLD_NAME	Specifies whether an old relative distinguished name should be deleted or retained. Used in Rename events.
STATUS_LEVEL	The status of an event: success, warning, retry, error or fatal.
STATUS_MESSAGE	A message to report with a status.
STATUS_TYPE	A type of status, such as heartbeat.

Examples Of Obtaining Event Data

Example 1:

```
my $idmlib = new IDMLib();
my $command = $idmlib->idmgetvar("COMMAND");
# check for an add event
if ($command eq "add") {
    # call the add script
    do add.pl;
}
```

Example 2:

```
my $idmlib = new IDMLib();
# obtain the event's association and CN attribute
my $association = $idmlib->idmgetvar("ASSOCIATION");
my $CN = $idmlib->idmgetvar("CN");
if ($CN eq "bob") {
    # for "bob", check to see if he's been enabled
    my $ENABLE = $idmlib->idmgetvar("REMOVE_Login Disabled");
    if ($ENABLE eq "true") {
        # bob is enabled again
        cmd="appenable -association ". $ASSOCIATION
        $idmlib->exec($cmd);
    }
}
```

Handling Associations

The association value indicates which identity has been changed. If the identity has no association, an association must be generated for it using an implementation-specific rule that you have adopted. When Identity Manager processes an event for an identity with no association, it executes the driver's Matching policy. This policy attempts to match the event's identity to an identity on the external application's system. Doing this usually involves executing a query. The default Matching policy included with the Scripting driver queries for matching Users and Groups based on the CN

attribute. If the event's identity matches an identity on the external application, both identities must be assigned the new association. Assigning this association can be done as part of the query-handling script. (Handling queries is discussed in [“Handling Query Events” on page 61.](#)) If no identity matches, an Add event is issued, and the new association can be assigned as part of the Add event-handling script:

```
# Adding an association
my $idmlib = new IDMLib();
$idmlib->idmsetvar("COMMAND", "ADD_ASSOCIATION");
$idmlib->idmsetvar("ASSOCIATION", $MyAssociation);
$idmlib->idmsetvar("EVENT_ID", $EVENT_ID);
$idmlib->idmsetvar("DEST_DN", $SRC_DN);
$idmlib->idmsetvar("DEST_ENTRY_ID", $SRC_ENTRY_ID);
```

The above example demonstrates each name/value pair that must be set for an association to be assigned by the Identity Manager engine. The values of `EVENT_ID`, `SRC_DN` and `SRC_ENTRY_ID` are always sent by the engine during an add event, and therefore, are available for your add script to obtain using `$idmlib->idmgetvar()`. The example above also illustrates the `$idmlib->idmsetvar()` function. For detailed information on how to use `$idmlib->idmsetvar()`, see [Section C.2, “Perl \(IDMLib.pm\) Reference,” on page 112.](#) This function sets a name and value which indicates what action Identity Manager should perform. For example, the pair `COMMAND` and `ADD_ASSOCIATION` instructs the shim to create an add-association document to assign an association to an identity, as discussed above. The pair `EVENT_ID` and `$EVENT_ID` instruct the shim to assign add-association document an event-id described by the variable `$EVENT_ID`. This is important for the engine to match documents sent and returned on the subscriber channel.

The Subscriber can also issue `MODIFY_ASSOCIATION` and `REMOVE_ASSOCIATION` commands:

```
# Removing an association
my $idmlib = new IDMLib();
$idmlib->idmsetvar("COMMAND", "REMOVE_ASSOCIATION");
$idmlib->idmsetvar("ASSOCIATION", $MyAssociation);
$idmlib->idmsetvar("EVENT_ID", $EVENT_ID);
$idmlib->idmsetvar("DEST_DN", $SRC_DN);
$idmlib->idmsetvar("DEST_ENTRY_ID", $SRC_ENTRY_ID);

# Modifying an association
my $idmlib = new IDMLib();
$idmlib->idmsetvar("COMMAND", "MODIFY_ASSOCIATION");
$idmlib->idmsetvar("ASSOCIATION", $OldAssociation);
$idmlib->idmsetvar("ASSOCIATION", $NewAssociation);
$idmlib->idmsetvar("EVENT_ID", $EVENT_ID);
$idmlib->idmsetvar("DEST_DN", $SRC_DN);
$idmlib->idmsetvar("DEST_ENTRY_ID", $SRC_ENTRY_ID);
```

Returning an Event Status

On the Subscriber channel, you often do not need Identity Manager to perform an action, but simply need to report a status. The `STATUS_` subroutines noted below can be used to indicate a status to Identity Manager. They take a message to be logged as the parameter.

Table 5-8 *STATUS Subroutines*

Subroutine	Identity Manager Action
<code>status_success()</code>	Identity Manager marks the event as a success and submits the next event in the event queue, if any. You should issue this status even if your script does nothing.
<code>status_warning()</code>	The event can be processed, but it might require attention. Identity Manager issues your warning message in its log, and then submits the next event.
<code>status_retry()</code>	The event cannot be processed, but Identity Manager should resubmit the event because it should be able to be processed soon. This status can be issued if your external application appears to be temporarily unavailable. However, this status should be used cautiously because a backlog results if Identity Manager continually retries one event.
<code>status_error()</code>	The event cannot be processed and it should not be resubmitted. Identity Manager issues the error message and submits the next event. You should make a detailed error message so the problem can be corrected.
<code>status_fatal()</code>	For some reason, the driver must be stopped. Identity Manager issues your message and stops the driver. This could be used if the external application appears to be permanently offline. The event remains in the queue and is resubmitted when the driver is restarted.

Examples Using the Status() Functions

```
$idmlib->exec($cmd);
if ($? == 0) {
    $idmlib->status_success("Command was successful");
}
$idmlib->exec($cmd);
if ($? == 0) {
    if ($password eq '') {
        # created, but no password
        $idmlib->status_warning("User added without password");
    }
}
$idmlib->exec($cmd);
if ($? != 0) {
    $idmlib->status_error("Command failed");
}
```

Writing Values

`$idmlib->idmsetvar()` is used to set values to return to Identity Manager. It is passed a name and value. For detailed information on how to use `$idmlib->idmsetvar()`, see [Section C.2, “Perl \(IDMLib.pm\) Reference,” on page 112](#). In the previous `ADD_ASSOCIATION` example, `$idmlib->idmsetvar()` is used to set the `ASSOCIATION` value. You can specify values for items listed in the table above. Generally, `$idmlib->idmsetvar()` is used to add, modify and delete associations or return information for a query operation. Other information is returned to the shim through other command functions, such as `status_success()`, which use `IDMSETVAR` indirectly.

Handling Query Events

For Query events, Identity Manager submits values that define the parameters of a search of the external application's identity management system. Queries are usually issued from the Policies you have defined for your system. The table below specifies values that can be specified in queries. Not all values are relevant to your external application.

Table 5-9 *Query Values*

Value Name	Description
SCOPE	Specifies what identities are searched. A base object is specified with the <code>ASSOCIATION</code> or <code>DEST_DN</code> values (see below). The value <code>entry</code> means that only the base object is searched. The value <code>subordinates</code> means that the immediate subordinates of the base object are searched. The value <code>subtree</code> (the default) indicates that the base object and all subordinates are searched. The last two values are only relevant in a hierarchical system.
ASSOCIATION	The base object for the search. If both <code>ASSOCIATION</code> and <code>DEST_DN</code> have values, <code>ASSOCIATION</code> is used. If neither is specified, the base object is the root of the identity management system.
DEST_DN	The base object for the search (see also <code>ASSOCIATION</code> above).
CLASS_NAME	The base class of the base object.
EVENT_ID	An identifier for the event.
SEARCH_CLASSES	A list of classes for which to search. Only identities of these classes are returned. If not specified, all identities in the scope matching <code>SEARCH_ATTR_</code> values are returned (see below)
SEARCH_ATTRS	A list of the attribute names specified in <code>SEARCH_ATTR_</code> values (see below).
SEARCH_ATTR_{attr_name}	A value that the specified attribute must match. Replace {attr_name} with the desired attribute name. Only identities matching all <code>SEARCH_ATTR_</code> filters are returned.
READ_ATTRS	A list of the attribute names whose values are returned for each matching identity.
ALL_READ_ATTRS	The presence of this value indicates that all attribute values should be returned for matching identities.
NO_READ_ATTRS	The presence of this value indicates that no attribute values should be returned for matching identities.
READ_PARENT	The presence of this value indicates that the parent object of each matching identity should be returned. Only relevant in hierarchical systems.

Execute the query against the external application using application-provided tools. Then return each identity by setting an `INSTANCE` command, followed by relevant values from the list below.

Table 5-10 *Query Values*

Value Name	Description
CLASS_NAME	The class of the identity. Required.
SRC_DN	A distinguished name representing the logical location of the identity in the system (optional).
ASSOCIATION	The association of the identity, if available (optional).
PARENT	The association of the parent object of the identity (optional). Only relevant in hierarchical systems.
ATTR_{attr_name}	A list of values for the attribute specified by {attr_name}. Return attribute values specified by the READ_ATTRS value.

After returning all identities, call `$idmlib->status_success()` to indicate a successful query.

Subscriber Summary and Examples

Below is a more detailed summary of the actions to take for a non-Query event.

- 1 Gather information about the event using `$idmlib->idmgetvar()`. Return a warning or error if there is a problem.
- 2 Submit the event data to the external application using application-provided tools.
- 3 Set event values with `$idmlib->idmsetvar()`.
- 4 If you have not already done so, set a status with a `$idmlib->status()` subroutine.

Below is an example `add.pl`, which forms an association from an identity's CN and class name, and uses a hypothetical tool called `appadd`.

```
#!/usr/bin/perl

use IDMLib;
my $idmlib = new IDMLib();
my $ClassName = $idmlib->idmgetvar("CLASS_NAME");
my $CN = $idmlib->idmgetvar("CN");
my $PhoneNumber = $idmlib->idmgetvar("Telephone");
my $EVENT_ID = $idmlib->idmgetvar("EVENT_ID");

if (($ClassName eq '') || ($CN eq '')) {
    $idmlib->status_error( "Add event: missing CLASS_NAME and/or CN" );
} else {
    my $Command = "appadd -n $CN -t $PhoneNumber";
    my $src = $idmlib->exec( $Command );
    if ( $src == 0 ) {
        $idmlib->idmsetvar("COMMAND", "ADD_ASSOCIATION");
        $idmlib->idmsetvar("ASSOCIATION", $CN . $ClassName);
        $idmlib->idmsetvar("EVENT_ID", $EVENT_ID);
        $idmlib->idmsetvar("DEST_DN", $SRC_DN);
        $idmlib->idmsetvar("DEST_ENTRY_ID", $SRC_ENTRY_ID);
    }
}
```

```

        $idmlib->status_success( "Add event succeeded" );
    } else {
        $idmlib->status_error( "Add event failed with error code" . $rc );
    }
}

```

Handling a query is a similar process, except that you return INSTANCE items rather than using other commands. Below is an example `query.pl` that searches an external application for a telephone number. It uses a hypothetical tool called `appsearch`.

```

#!/usr/bin/perl

use IDMLib;
my $idmlib = new IDMLib();
my $SearchName = $idmlib->idmgetvar("SEARCH_ATTR_CN");
my $EVENT_ID = $idmlib->idmgetvar("EVENT_ID");
my $ASSOCIATION = $idmlib->idmgetvar("ASSOCIATION");
my $CLASS_NAME = $idmlib->idmgetvar("CLASS_NAME");

if ($SearchName eq "") {
    $idmlib->status_error( "Query: no search value" );
} else {
    my $Command = "appsearch -n ". $SearchName;
    $Results = ` $Command `;
    if ($Results ne "") {
        my @phoneinfo = split(" ", $Results);
        my $Phone = $phoneinfo[0];

        $idmlib->idmsetvar("COMMAND", "INSTANCE");
        $idmlib->idmsetvar("CLASS_NAME", $CLASS_NAME);
        $idmlib->idmsetvar("EVENT_ID", $EVENT_ID);
        $idmlib->idmsetvar("ASSOCIATION", $ASSOCIATION);
        $idmlib->idmsetvar("ATTR_Telephone", $Phone);

        $idmlib->status_success( "Query succeeded" );
    } else {
        # Return success with no results
        $idmlib->status_success( "Query succeeded (no matches)" );
    }
}

```

Publisher Script Development

Events that occur on the external application are submitted to Identity Manager on the Publisher channel. The Scripting driver polls the external application for events periodically. How this poll detects events is implementation-specific and must be defined the user.

Polling for Application Events

The Driver calls `poll.pl` in order to detect application events. `poll.pl` should be implemented as follows:

- 1 Use application-provided tools to detect events in your application. (See the discussion in Step Two.)
- 2 For each event, call the `usclh changelog` tool to submit the event to be published. The changelog tool allows for additional information to be supplied through standard input. This is an appropriate mechanism for passing data that might be too large for command line or too sensitive to appear in a shell's history or environment. For more information on `usclh`, see [Section D.3, "Publisher Change Log Tool," on page 123](#)

Below is an example of a `poll.pl` that checks for a password change. It uses a hypothetical application tool called `appchg`.

```
#!/usr/bin/perl

use IDMLib;
$my idmlib = new IDMLib();
my $Results = `appchg --passwd-changes`;
foreach $Result ( split("\n", $Results) ) {
    # Entries are in the format "association:password"
    ($Association, $Password) = split(":", $Result);
    `usclh -t modify-password -a $Association <<EOF
$Password
EOF`;
}

# look for attribute values being added to each user
$Results = `appchg --add-attr-changes`;
foreach $Result ( split("\n", $Results) ) {
    # Entries are in the format "association:attribute:value"
    ($Association, $Attribute, $Value) = split(":", $Result);
    `usclh -t modify -c User -a $Association <<EOF
ADD_$Attribute=$Value
EOF`;
}

# look for attribute values being removed from each user
$Results = `appchg --remove-attr-changes`;
foreach $Result ( split("\n", $Results) ) {
    # Entries are in the format "association:attribute:value"
    ($Association, $Attribute, $Value) = split(":", $Result);
    `usclh -t modify -c User -a $Association <<EOF
REMOVE_$Attribute=$Value
EOF`;
}
```

In the above example, three separate events are submitted to the publisher change log, using the change log tool, `usclh`. The first invocation submits a modify-password event to be published. The second event submits a modify event to be published for an attribute add. The third invocation submits another modify event to be published for an attribute removal. The second and third invocations can be combined into a single modify event, if desired.

Events submitted using usclh are processed through your driver's Publisher Channel's policies. See the [Novell Identity Manager 3.6.1 Policy guides \(http://www.novell.com/documentation/idm36\)](http://www.novell.com/documentation/idm36) for more information.

Using the Heartbeat Script

Another script executed in the Publisher Channel is `heartbeat.pl`. This script is executed when the Publisher Channel is idle for the interval specified in the Driver parameters. (You can set the interval to 0 so no heartbeat is issued.) You can use the heartbeat to check the availability of the external system or do "idle state" tasks. The `$idmlib->heartbeat_success()`, `$idmlib->heartbeat_warning()`, and `$idmlib->heartbeat_error()` subroutines can be used to indicate the result of the heartbeat. Below is an example based on a hypothetical tool called `apphealth`.

```
my $idmlib = new IDMLib();
my $src = `apphealth`;
if ($src == 0) {
    $idmlib->heartbeat_success("Heartbeat succeeded");
} else {
    $idmlib->heartbeat_error("Heartbeat failed with error code " . $src);
}
```

The response to the heartbeat is implementation-dependent, and can be defined in policies or in the script itself. You could send a message to auditing using Novell Audit. You could store a value in a file and have Subscriber scripts read the file and call `$idmlib->heartbeat_retry()` if they find that value in the file.

Other Scripting Topics

- ♦ "Driver Parameters" on page 65
- ♦ "Querying the Identity Vault" on page 66
- ♦ "Tracing and Debugging" on page 66

Driver Parameters

A driver has values known as driver parameters. The driver parameters are divided into driver settings applicable to the whole driver, and Subscriber and Publisher Settings for their respective channels. The `$idmlib->idmgetdrvvar()`, `$idmlib->idmgetsubvar()` and `$idmlib->idmgetpubvar()` functions can be used to retrieve these values. The table below shows parameters in the default Scripting driver. Other parameters can be added to the driver's XML Configuration file (see the [Identity Manager 3.6.1 Common Driver Administration Guide](#)).

Table 5-11 Scripting Driver Parameters

Parameter Name	Driver/Channel	Description	Values
INSTALL_PATH	Driver	The installation path of the Driver	string value
auto-loopback-detection	Driver	Whether to enable automatic loopback detection	true/false

Parameter Name	Driver/Channel	Description	Values
subscriber-script	Subscriber	The root script file for Subscriber events, relative to the driver installation path	string value
pub-polling-interval	Publisher	The interval in seconds between Publisher polls for application events	number
pub-heartbeat-interval	Publisher	The amount of idle time in seconds before a heartbeat event is issued	number
pub-disabled	Publisher	Whether the Publisher Channel (such as for polling) is disabled	true/false

In the following example, a script retrieves the Publisher polling interval.

```
my $PollingInterval = $idmlib->idmgetpubvar("pub-polling-interval");
```

Querying the Identity Vault

Scripts might need to retrieve information from the Identity Vault. They can do this by issuing a query.

- 1 Execute the query by calling `$idmlib->idmquery($class, $association, $readattrs)` with the appropriate parameters:
 - ♦ The first parameter is the class-name
 - ♦ The second parameter is the association of the object to query
 - ♦ The third parameter are the attributes to read, comma-separated
- 2 Read the result (instance) using `$idmlib->idmgetqvar()`.

Query support is currently limited. It returns only one instance based on the specified association or DN. If both association and DN are specified, association is used. The functions below allow you to retrieve information from the instance.

The following is an example of a query of the Identity Vault that retrieves the address and ZIP code for user Bob.

```
my $idmlib = new IDMLib();
$idmlib->idmquery("User", "Bob", "SA,Postal Code");

my $Address = $idmlib->idmgetqvar( "SA" );
my $ZIPCode = $idmlib->idmgetqvar( "Postal Code" );
# ... etc. ...
```

Tracing and Debugging

The function `IDMTRACE` allows you to write a message to the Trace Log. Tracing is useful for script debugging and auditing.

```
$idmlib->trace("Trace Message");
```

When you develop scripts, you might need to do some debugging to track down problems. The following list indicates some facilities for debugging.

- ♦ The Driver traces activity to its Trace file (`logs/trace.log` by default). The trace level setting in `conf/usdrv.conf` controls how much debugging is written to the log.

Trace Level	Description
0	No debugging.
1-3	Identity Manager messages. Higher trace levels provide more detail.
4	Previous level plus Remote Loader, driver, driver shim, and Driver connection messages.
5-7	Previous level plus Change Log and loopback messages. Higher trace levels provide more detail.
8	Previous level plus Driver status log, Driver parameters, Driver command line, Driver security, Driver Web server, Driver schema, Driver encryption, Driver SOAP API, and Driver include/exclude file messages.
9	Previous level plus low-level networking and operating system messages.
10	Previous level plus maximum low-level program details.

The trace level is set using the `-trace` option in `usdrv.conf`, for example `-trace 9`.

You can view the trace file through a Web browser:

1. Use a Web browser to access the driver shim at `https://driver-address:8091`. Substitute the DNS name or IP address of your driver for `driver-address`.
 2. Authenticate by using any username and the password that you specified as the Remote Loader password.
 3. Click *Trace*.
- ♦ The eDirectory tool DSTrace can be used to monitor Identity Manager activity. Set the tracing level for the Driver in iManager. DSTrace shows the XML documents being submitted to the driver for events and how policies are evaluated. It also shows the status and message for each event.
 - ♦ The Status Log is written to `logs/dirxml.log`. It shows a summary of the events that have been recorded on the Subscriber and Publisher channels.

You can view the Status Log through a Web browser:

1. Use a Web browser to access the driver shim at `https://driver-address:8091`. Substitute the DNS name or IP address of your driver for `driver-address`.
2. Authenticate by using any username and the password that you specified as the Remote Loader password.
3. Click *Status*.

Although it is best to start the driver in production environments from the startup script, you can run `usdrv` manually. When you do so, any text written to standard output from scripts is displayed in the interactive shell.

5.6.3 Deployment

The Scripting driver is installed by using a setup program. See [Section 3.1, “Installing the Linux and UNIX Scripting Driver,” on page 19](#), for more information on installing the default driver.

Deploying a Custom Driver

To deploy your custom driver, the end user should first run the Scripting driver installation program provided by the installation media (see [Section 3.1, “Installing the Linux and UNIX Scripting Driver,” on page 19](#)). This program installs core files needed by the driver. Then, your custom driver files can be deployed in any convenient way, whether through an installation program or even simply an archive file. The table below shows the directory structure below the installation directory and what files are installed.

Table 5-12 *Directory Structure and Files*

Directory	Description	Required Files
bin/	Location of executable programs	usdrv ussmh usclh
changelog/	Used for Publisher event processing	None
conf/	Location of the driver shim configuration file	usdrv.conf (customized)
keys/	Location of security key files	None
logs/	Location of log files	None
loopback/	Used for automatic loopback detection	None
rules/	Location of Driver configuration file	Scripting.xml (customized)
schema/	Location of schema files	schema.def (customized)
scripts/	Location of script files	Those required by your Driver (customized)

On Linux and UNIX, the Scripting driver is installed to `/opt/novell/usdrv`.

The formats of `usdrv.conf` and `schema.def` can be viewed in [Section 4.2, “The Driver Shim Configuration File,” on page 29](#) and [Section 5.2, “The Connected System Schema File,” on page 34](#).

If SSL encryption is desired for communication between the driver shim and Identity Manager engine, a certificate must be retrieved from the Identity Vault. Run `usdrv -s` and follow the prompts to retrieve the certificate, which will be stored in the `keys/` directory. You must have LDAP with SSL available for the Metadirectory. When making an installation program for deployment, you might want to run `usdrv -s` as part of the installation.

To ensure that only authorized systems access the Metadirectory, a Driver object password and Remote Loader password are used. Run `usdrv -sp` and enter the passwords at the prompts. This action can be incorporated into an installation program.

You should distribute the XML configuration file that contains parameters and policies your Driver needs. The user can then select it when installing your Driver.

5.7 Microsoft VBScript Developer Guide

The Scripting driver provides a complete Microsoft VBScript API for interacting with identity management systems whose tools (including APIs) are available on Windows. The Identity Vault and Identity Manager can run on any supported operating system. Identity Manager communicates with the driver on a different system over an encrypted network connection.

Before beginning script development, review the preceding topics in this section for information on defining what data is synchronized between identity management systems.

With additional development work, the driver can also be adapted to support any scripting language that supports command line operation.

Developing a custom driver with VBScript is discussed in this section. Topics include

- ♦ [Section 5.7.1, “Application Tools Evaluation,” on page 69](#)
- ♦ [Section 5.7.2, “Policy and Script Development,” on page 71](#)
- ♦ [Section 5.7.3, “Deployment,” on page 82](#)

5.7.1 Application Tools Evaluation

In order to change the data in your external application, you need to know how to use the application’s tools or API (Application Programming Interface). These tools must provide automated operation and not require user input.

Application Command Line Tools

An application often provides command line tools. These tools are manually executed from the Windows command prompt, and they can be executed from scripts. For example, suppose the application provides a tool to add identities with a program called `appadd.exe`.

```
appadd -n "Bob Smith" -t "818-555-2100"
```

This command adds an identity named “Bob Smith” with the specified phone number. The strings following the program name are called parameters or arguments. The Scripting driver provides a function called `IDMExecute` to execute external programs.

```
CommandLine = "appadd -n " & UserName & " -t " & PhoneNumber  
ExitCode = IDMExecute(CommandLine)
```

There is also a function called `IDMExecuteIO` that allows you to pass information on the program’s standard input, and receive output from the program’s standard output and standard error.

```

Dim Input(1)

Input(0) = "USERNAME=bobsmith"
Input(1) = "TELEPHONE=818-555-2100"

Output = IDMExecuteIO("appadd", Input)

ExitCode = Output(0)

```

IDMExecuteIO's first parameter is the command line, and its second parameter is an array of strings (or Empty) that is submitted as lines to the command program. It returns an array, the first element of which is the program's exit code, and then strings that represent lines returned on the program's standard output and standard error.

For command line tools, you can construct the command line's parameters using the values passed to the script, then execute the program.

Application Objects

Another way to modify application data is through Windows COM (Common Object Model) objects. Consult your application's documentation to see whether it exposes any COM objects. These COM objects can be loaded directly in VBScript:

```

Set AppObject = WScript.CreateObject("MyApplication.MyObject")
AppObject.AddIdentity("Bob Smith", "818-555-2100")

```

There are no guarantees regarding what types of tools are available, or even whether any tools are available. You must determine if sufficient tools are provided by the application. If they are not, you can contact the application's developers and request that such tools be made available.

You should make a list of what tools can be used for each event type. The application might provide one program that can be used for any event type, or it might provide multiple tools.

Application Event Monitoring

You also need to determine what tools are available for monitoring event changes in the application. The Scripting driver works on a polling system. It periodically calls a polling script to determine what has changed in the external application. You can use the following ideas for monitoring changes:

- ♦ The first time the polling script is run, a list of identities and relevant attributes is read from the application using an application-provided tool. This list is stored as a file. On subsequent polls, a new list is generated and compared to the old list. Any differences are submitted as events to the driver.
- ♦ The application provides a tool that allows you to request all identities that have changed after a certain point in time. The polling script requests events that have occurred since the previous poll.
- ♦ The application allows a script to be run when an event occurs. You write a script that stores the event data into a file. When the Scripting driver polling script runs, it consumes this file and submits the data as an event to the driver.

Monitoring the application's changes might be the most difficult aspect of developing your driver. You must study your application's tools to determine the best way to achieve synchronization.

5.7.2 Policy and Script Development

At this point you should have a list of what data will be synchronized, how events will be handled, and what application tools are available. It is time to develop the heart of your driver in policies and scripts.

Many types of tasks can be handled in driver policies. You can import the driver configuration provided with the Scripting driver, and then edit policies in Novell iManager. You can also edit policies and simulate their operation in Novell Designer. The extensive functionality of policies is outside the scope of this document, so you should refer to your [Novell Identity Manager 3.6.1 Policy guides](http://www.novell.com/documentation/idm36) (<http://www.novell.com/documentation/idm36>) for help.

Tasks that don't interact with the external application might be more suited to policies. On the other hand, if you are more familiar with your scripting language than policies, you can develop your driver more quickly by using scripts.

Event Data Format

Event data is submitted to the scripts in name/value pair format. This format consists of lines containing a name, an equal sign (=) and a value. Therefore, each line is a name/value pair. Each name/value pair is unique, but there can be multiple name/value pairs with identical names but different values.

```
ASSOCIATION=BobUser
ADD_TELEPHONE=818-555-2100
ADD_TELEPHONE=818-555-9842
```

You typically don't have to worry about the format. The script library provides functions for retrieving event data.

Subscriber Script Development

After all policy processing is complete, Identity Manager submits the event in XML format to the driver shim. The driver shim submits the event data to the scripts.

In the default Scripting driver, the `Subscriber.wsf` script in the `scripts` folder is called. This script does some preliminary processing, and then calls a routine from an included script. The included scripts correspond to the Subscriber event types: `Add.vbs`, `Modify.vbs`, `ModifyPassword.vbs`, `Delete.vbs`, `Rename.vbs`, `Move.vbs`, and `Query.vbs`.

For each event type, you should retrieve the information you need from the event data, submit changes to the external application using application-provided tools and return a status (such as success or failure) to Identity Manager.

Event data is retrieved primarily using the `IDMGetEventValues` function. This function returns an array of values corresponding to the name specified as the function's parameter. (`IDMGetEventValue` is available for single-valued items.) The following table shows many item names.

Table 5-13 *Item Names*

Value	Description
COMMAND	The command for the event, usually indicating the event type.

Value	Description
ASSOCIATION	The identifier that distinguishes an identity on both identity management systems.
CLASS_NAME	An identity's class, such as User or Group.
SRC_DN	An identity's distinguished name (DN) in the namespace of the source (sender), in slash format.
EVENT_ID	An identifier for the event, for internal use.
SRC_ENTRY_ID	An identifier for the identity that generated the event, in the namespace of the source (sender).
DEST_DN	An identity's distinguished name (DN) in the namespace of the destination (receiver), in slash format.
DEST_ENTRY_ID	An identifier for an entry in the namespace of the destination (receiver).
ADD_{attr_name}	A value to be added to an identity, for attribute {attr_name}.
REMOVE_{attr_name}	A value to be removed from an identity, for attribute {attr_name}.
ADD_REF_{attr_name}	A value to be added to attribute {attr_name}, where the value is an association referring to another identity.
REMOVE_REF_{attr_name}	A value to be removed from attribute {attr_name}, where the value is an association referring to another identity.
OLD_PASSWORD	The previous password for an identity that has changed its password. Used in Modify Password events.
PASSWORD	The new password for an identity. Used in Add and Modify Password events.
OLD_SRC_DN	The distinguished name of an identity before a Move or Rename event.
REMOVE_OLD_NAME	Specifies whether an old relative distinguished name should be deleted or retained. Used in Rename events.
STATUS_LEVEL	The status of an event: success, warning, retry, error or fatal.
STATUS_MESSAGE	A message to report with a status.
STATUS_TYPE	A type of status, such as heartbeat.

Handling Associations

The association value indicates which identity has been changed. If the identity has no association, an association must be generated for it using an implementation-specific rule that you have adopted. When Identity Manager processes an event for an identity with no association, it executes the driver's Matching policy. This policy attempts to match the event's identity to an identity on the external application's system. Doing this usually involves executing a query. The default Matching policy included with the Scripting driver queries for matching Users and Groups based on the CN attribute. If the event's identity matches an identity on the external application, both identities must be assigned the new association. Assigning this association can be done as part of the query-

handling script. (Handling queries is discussed in “[Handling Query Events](#)” on page 74.) If no identity matches, an Add event is issued, and the new association can be assigned as part of the Add event-handling script:

```
IDMSetCommand "ADD_ASSOCIATION"
IDMWriteValue "ASSOCIATION", MyAssociation
(etc.)
```

The example above also illustrates the `IDMSetCommand` function. This function sets a command value which indicates what action Identity Manager should perform. The `ADD_ASSOCIATION` command assigns an association to an identity, as discussed above. The Subscriber can also issue `MODIFY_ASSOCIATION` and `REMOVE_ASSOCIATION` commands.

Returning an Event Status

On the Subscriber channel, you often do not need Identity Manager to perform an action, but simply need to report a status. The `IDMStatus` subroutines noted below can be used to indicate a status to Identity Manager. They take a message to be logged as the parameter.

Table 5-14 *Subroutines*

Subroutine	Identity Manager Action
<code>IDMStatusSuccess</code>	Identity Manager marks the event as a success and submits the next event in the event queue, if any. You should issue this status even if your script does nothing.
<code>IDMStatusWarning</code>	The event can be processed, but it might require attention. Identity Manager issues your warning message in its log, and then submits the next event.
<code>IDMStatusRetry</code>	The event cannot be processed, but Identity Manager should resubmit the event because it should be able to be processed soon. This status can be issued if your external application appears to be temporarily unavailable. However, this status should be used cautiously because a backlog results if Identity Manager continually retries one event.
<code>IDMStatusError</code>	The event cannot be processed and it should not be resubmitted. Identity Manager issues the error message and submits the next event. You should make a detailed error message so the problem can be corrected.
<code>IDMStatusFatal</code>	For some reason, the driver must be stopped. Identity Manager issues your message and stops the driver. This could be used if the external application appears to be permanently offline. The event remains in the queue and is resubmitted when the driver is restarted.

Writing Values

`IDMSetCommand` and/or a status subroutine must be called before specifying values with `IDMWriteValues`. `IDMWriteValues` (or its single-valued version `IDMWriteValue`) is used to set values to return to Identity Manager. It is passed a value name and an array of values. In the `ADD_ASSOCIATION` example above, `IDMWriteValue` is used to set the `ASSOCIATION` value. You can specify values for items listed in the table above.

Handling Query Events

For Query events, Identity Manager submits values that define the parameters of a search of the external application's identity management system. Queries are usually issued from the policies you have defined for your system. The table below specifies values that can be specified in queries. Not all values are relevant to your external application.

Table 5-15 *Query Values*

Value Name	Description
SCOPE	Specifies what identities will be searched. A base object is specified with the <code>ASSOCIATION</code> or <code>DEST_DN</code> values (see below). The value "entry" means that only the base object is searched. The value "subordinates" means that the immediate subordinates of the base object are searched. The value "subtree" (the default) indicates that the base object and all subordinates are searched. The last two values are only relevant in a hierarchical system.
ASSOCIATION	The base object for the search. If both <code>ASSOCIATION</code> and <code>DEST_DN</code> have values, <code>ASSOCIATION</code> is used. If neither is specified, the base object is the root of the identity management system.
DEST_DN	The base object for the search (see also <code>ASSOCIATION</code> above).
CLASS_NAME	The base class of the base object.
EVENT_ID	An identifier for the event.
SEARCH_CLASSES	A list of classes for which to search. Only identities of these classes are returned. If not specified, all identities in the scope matching <code>SEARCH_ATTR_</code> values are returned (see below).
SEARCH_ATTRS	List of attribute names used in <code>SEARCH_ATTR_</code> values (see below).
SEARCH_ATTR_{attr_name}	A value that the specified attribute must match. Replace {attr_name} with the desired attribute name. Only identities matching all <code>SEARCH_ATTR_</code> filters are returned.
READ_ATTRS	List of attribute names whose values returned for each identity match.
ALL_READ_ATTRS	The presence of this value indicates that all attribute values should be returned for matching identities.
NO_READ_ATTRS	The presence of this value indicates that no attribute values should be returned for matching identities.
READ_PARENT	The presence of this value indicates that the parent object of each matching identity should be returned. Only relevant in hierarchical systems.

Execute the query against the external application using application-provided tools. Then return each identity by setting an `INSTANCE` command, followed by relevant values from the list below.

Table 5-16 *Query Values*

Value Name	Description
CLASS_NAME	The class of the identity. Required.
SRC_DN	A distinguished name representing the logical location of the identity in the system (optional).
ASSOCIATION	The association of the identity, if available (optional).
PARENT	The association of the parent object of the identity (optional). Only relevant in hierarchical systems.
ATTR_{attr_name}	A list of values for the attribute specified by {attr_name}. Return attribute values specified by the READ_ATTRS value.

After returning all identities, call `IDMStatusSuccess` to indicate a successful query.

Subscriber Summary and Examples

Below is a more detailed summary of the actions to take for a non-Query event.

- 1 Gather information about the event using `IDMGetEventValues`. Return a warning or error if there is a problem.
- 2 Submit the event data to the external application using application-provided tools.
- 3 Set a command using `IDMSetCommand` and/or a status with the `IDMStatus` subroutines, based on the result of the event.
- 4 Set event values with `IDMWriteValues`.
- 5 If you have not already done so, set a status with an `IDMStatus` subroutine.

Below is an example of the `Add.vbs` script, which forms an association from an identity's CN and class name, and uses a hypothetical tool called `appadd`.

```
Sub ADD
  ClassName = IDMGetEventValue("CLASS_NAME")
  CN = IDMGetEventValue("CN")
  PhoneNumber = IDMGetEventValue("Telephone")
  If IsEmpty(ClassName) Or IsEmpty(CN) Then
    IDMStatusError "Add event: missing CLASS_NAME and/or CN"
  Else
    Command = "appadd -n "" & CN & "" -t "" & PhoneNumber & """"
    ExitCode = IDMExecute(Command)
    If ExitCode = 0 Then
      IDMSetCommand "ADD_ASSOCIATION"
      IDMWriteValue "ASSOCIATION", CN & ClassName
      IDMWriteValue "DEST_DN", IDMGetEventValue("SRC_DN")
      IDMStatusSuccess "Add event succeeded"
    Else
      IDMStatusError "Add event failed with error code " & ExitCode
    End If
  End If
End Sub
```

Handling a query is similar, except you return INSTANCE items rather than use other commands. Below is an example `Query.vbs` that searches an external application for a telephone number. It uses a hypothetical tool called `appsearch`.

```
Sub QUERY
    SearchName = IDMGetEventValue("SEARCH_ATTR_CN")
    If IsEmpty(SearchName) Then
        IDMStatusError "Query: no search value"
    Else
        Command = "appsearch -n " & SearchName
        Results = IDMExecuteIO(Command, Empty)
        If Results(0) = 0 Then
            Phone = Results(1)
            IDMSetCommand "INSTANCE"
            IDMWriteValue "CLASS_NAME", IDMGetEventValue("CLASS_NAME")
            IDMWriteValue "ASSOCIATION", IDMGetEventValue("ASSOCIATION")
            IDMWriteValue "ATTR_Telephone", Phone
            IDMStatusSuccess "Query succeeded"
        Else
            ' Return success with no results
            IDMStatusSuccess "Query succeeded (no matches)"
        End If
    End If
End Sub
```

Publisher Script Development

Events that occur on the external application are submitted to Identity Manager on the Publisher channel. The Scripting driver periodically polls the external application for events. How this poll detects events is implementation-specific and must be defined by you.

Polling for Application Events

The Driver calls `Poll.wsf` in order to detect application events. `Poll.wsf` should be implemented as follows:

- 1** Use application-provided tools to detect events in your application. (See [Step 2.](#))
- 2** For each event:
 - 2a** Call the `IDMPublishInit` function to set the appropriate command.
 - 2b** Call `IDMPublishValues` to set event values.
 - 2c** Call `IDMPublish` to submit the event to Identity Manager.
- 3** If there were events, call an `IDMStatus` function to report the status.

`IDMPublishInit` takes a command name as its single parameter. Below is a list of valid command names for `IDMPublish`.

Table 5-17 *Command Names*

Command Name	Description
ADD	Create an identity.
ADD_ASSOCIATION	Create an association for an identity.

Command Name	Description
DELETE	Remove an identity permanently.
MODIFY	Change an identity's attributes.
MODIFY_ASSOCIATION	Change an identity's association.
MODIFY_PASSWORD	Change an identity's password.
REMOVE_ASSOCIATION	Delete an identity's association.
RENAME	Change an identity's naming attribute.

Below is an example of a `Poll.wsf` that checks for a password change. It uses a hypothetical application tool called `apppwd`.

```
Results = IDMExecuteIO("apppwd --changes", Empty)
For I = 1 To UBound(Results)
    ' Entries are in the format "association=password"
    Association = Left(Results(I), InStr(Results(I), "=")-1)
    Password = Mid(Results(I), InStr(Results(I), "=")+1)
    IDMPublishInit "MODIFY_PASSWORD"
    IDMPublishValue "ASSOCIATION", Association
    IDMPublishValue "PASSWORD", Password

    IDMPublish
Next

IDMStatusSuccess "Poll succeeded"
```

Events submitted using `IDMPublish` are processed through your driver's Publisher channel policies. See the [Novell Identity Manager 3.6.1 Policy guides \(http://www.novell.com/documentation/idm36\)](http://www.novell.com/documentation/idm36) for more information.

Using the Heartbeat Script

Another script executed in the Publisher Channel is `Heartbeat.wsf`. This script is executed when the Publisher channel is idle for the interval specified in the driver parameters. (You can set the interval to 0 so no heartbeat is issued.) You can use the heartbeat to check the availability of the external system or do "idle state" tasks. The `IDMHeartbeatSuccess`, `IDMHeartbeatWarning`, and `IDMHeartbeatError` subroutines can be used to indicate the result of the heartbeat. Below is an example based on a hypothetical tool called `apphealth`.

```
ExitCode = IDMExecute("apphealth")
If ExitCode = 0 Then
    IDMHeartbeatSuccess "Heartbeat succeeded"
Else
    IDMHeartbeatError "Heartbeat failed with error code " & ExitCode
End If
```

The response to the heartbeat is implementation-dependent, and can be defined in policies or in the script itself. You could send a message to auditing using Novell Audit. You could store a value in a file, and have Subscriber scripts read the file and call `IDMStatusRetry` if they find that value in the file.

Other Scripting Topics

- ♦ “Driver Parameters” on page 78
- ♦ “Querying the Identity Vault” on page 79
- ♦ “Tracing and Debugging” on page 80

Driver Parameters

A driver has values known as driver parameters. The driver parameters are divided into driver settings applicable to the whole driver, and Subscriber and Publisher Settings for their respective channels. The `IDMGetDriverParam`, `IDMGetSubscriberParam`, and `IDMGetPublisherParam` functions can be used to retrieve these values. The table below shows parameters in the default Scripting driver. Other parameters can be added to the driver’s XML Configuration file (see the *Identity Manager 3.6.1 Common Driver Administration Guide*).

Table 5-18 *Driver Parameters*

Parameter Name	Driver/Channel	Description	Values
INSTALL_PATH	Driver	The installation path of the driver	string value
auto-loopback-detection	Driver	Whether to enable automatic loopback detection	true/false
script-command	Driver	The command to use to execute scripts	string value
script-trace-file	Driver	The file, relative to the driver installation path, to which to write trace messages	string value
subscriber-script	Subscriber	The script file for Subscriber events, relative to the driver installation path	string value
polling-script	Publisher	The script file that runs when the Publisher polls for application events	string value
heartbeat-script	Publisher	The script file that runs when the Publisher checks application status	string value
pub-polling-interval	Publisher	The interval in seconds between Publisher polls for application events	number
pub-heartbeat-interval	Publisher	The amount of idle time in seconds before a heartbeat event is issued	number

In the following example, a script retrieves the Publisher polling interval.

```
PollingInterval = IDMGetPublisherParam("pub-polling-interval")
```

Querying the Identity Vault

Scripts might need to retrieve information from the Identity Vault. They can do this by issuing a query.

- 1 Initialize the query with `IDMQueryInit`.
- 2 Set query search parameters using functions listed below.

Function	Description
<code>IDMQuerySetAssociation(Association)</code>	Sets the association of the object to query.
<code>IDMQuerySetSearchRoot(SearchRoot)</code>	Sets the DN (in slash format) of the object to query.
<code>IDMQueryAddSearchAttr(Name, Value)</code>	Specifies a search condition of the form Name=Value. The query will only return an instance if the named attribute has a value matching Value.
<code>IDMQueryAddReadAttr(Name)</code>	Specifies an attribute whose values will be returned with the instance.
<code>IDMQuerySetReadParent(ReadParent)</code>	Specifies whether the association and DN of the parent of the queried object should be returned (False by default).

- 3 Execute the query with `IDMQuery`.
- 4 Read the result (instance) using functions listed below.

Currently query support is limited. It will only return one instance based on the specified association or DN. (If both association and DN are specified, association is used.) The functions below allow you to retrieve information from the instance.

Function	Description
<code>IDMGetQueryInstanceAssociation</code>	Returns the association of the instance.
<code>IDMGetQueryInstanceDN</code>	Returns the DN of the instance (in slash format).
<code>IDMGetQueryInstanceClass</code>	Returns the class name of the instance.
<code>IDMGetQueryInstanceParentAssociation</code>	Returns the association of the parent of the instance (if requested).
<code>IDMGetQueryInstanceParentDN</code>	Returns the DN of the parent of the instance (if requested).
<code>IDMGetQueryInstanceAttrNames</code>	Returns an array containing the names of the attributes retrieved for the instance. Returns Empty if no attributes were retrieved.
<code>IDMGetQueryInstanceAttrCount</code>	Returns the number of attributes retrieved for the instance.

Function	Description
IDMGetQueryInstanceAttrValues(AttrName)	Returns an array of values for the attribute AttrName. Returns Empty if no values are available.
IDMGetQueryInstanceAttrValue(AttrName)	Returns a string value for the attribute AttrName. If multiple values are available, the first one is returned. Returns Empty if no values are available.

The following is an example of a query of the Identity Vault that retrieves the address and ZIP code for users living in Provo, Utah.

```
IDMQueryInit
IDMSetQueryAssociation IDMGetEventValue("ASSOCIATION")
IDMAddSearchAttr "City", "Provo"
IDMAddSearchAttr "S", "UT"      ' State
IDMAddReadAttr  "SA"           ' Street Address
IDMAddReadAttr  "Postal Code"

If IDMQuery Then
    Address = IDMQueryGetInstanceAttrValue("SA")
    ZIPCode = IDMQueryGetInstanceAttrValue("Postal Code")
    ' ... etc. ...
End If
```

Tracing and Debugging

The IDMTrace function allows you to write a message to the Script Trace File specified in the Driver Parameters. Tracing is useful for script debugging and auditing.

```
IDMTrace "Trace message"
```


When developing scripts, you might need to do some debugging to track down problems. The following list indicates some facilities for debugging.

- ♦ The Driver traces activity to its Trace file (`logs\trace.log` by default). The trace level setting in `conf\wsdrv.conf` controls how much debugging is written to the log.

Trace Level	Description
0	No debugging.
1-3	Identity Manager messages. Higher trace levels provide more detail.
4	Previous level plus Remote Loader, driver, driver shim, and Driver connection messages.
5-7	Previous level plus Change Log and loopback messages. Higher trace levels provide more detail.
8	Previous level plus Driver status log, Driver parameters, Driver command line, Driver security, Driver Web server, Driver schema, Driver encryption, Driver SOAP API, and Driver include/exclude file messages.
9	Previous level plus low-level networking and operating system messages.
10	Previous level plus maximum low-level program details.

The trace level is set using the `-trace` option in `wsdrv.conf`, for example. `-trace 9`.

You can view the trace file through a Web browser:

1. Use a Web browser to access the driver shim at `https://driver-address:8091`. Substitute the DNS name or IP address of your driver for `driver-address`.
 2. Authenticate by using any username and the password that you specified as the Remote Loader password.
 3. Click *Trace*.
- ♦ The IDMTTrace function described above writes output to the trace file specified in the Driver Parameters (`logs\script-trace.log` by default).
 - ♦ The eDirectory tool DSTrace can be used to monitor Identity Manager activity. Set the tracing level for the Driver in iManager. DSTrace shows the XML documents being submitted to the Driver for events, and how Policies are evaluated. It also shows the status and message for each event.
 - ♦ The Status Log is written to `logs\dirxml.log`. It shows a summary of the events that have been recorded on the Subscriber and Publisher channels.

You can view the Status Log through a Web browser:

1. Use a Web browser to access the driver shim at `https://driver-address:8091`. Substitute the DNS name or IP address of your driver for `driver-address`.
2. Authenticate by using any username and the password that you specified as the Remote Loader password.
3. Click *Trace*.

Although it is best to run the driver as a service in production environments, you can run `wsdriver.exe` as a standard program. When you do so, a console window displays trace messages (see above) for the driver. Also, text written to standard output from scripts (such as using `WScript.Echo` in VBScript) is displayed in this window.

VBScript programs can be debugged using programs such as Microsoft Visual Studio and Microsoft Script Debugger. Change the Script Command driver parameter to use the `//x` option: `cscript //nologo //x`. When the driver shim executes a script, you are prompted to debug the script execution.

5.7.3 Deployment

The Scripting driver is installed by using a setup program. See [Section 3.2, “Installing the Windows Scripting Driver,” on page 20](#) for information on installing the default driver.

Deploying a Custom Driver

To deploy your custom driver, the end user should first run the Windows Scripting driver installation program provided by the installation media (see [Section 3.2, “Installing the Windows Scripting Driver,” on page 20](#) for more information.) This program installs core files needed by the driver. Then, your custom driver files can be deployed in any convenient way, whether through an installation program or even simply an archive file. The table below shows the directory structure below the installation directory and what files are installed.

Table 5-19 *Directory Structure and Files*

Directory	Description	Required Files
bin\	Location of executable programs	EventReader.exe idmevent.exe wsdriver.exe
changelog\	Used for Publisher event processing	None
conf\	Location of the driver shim configuration file	wsdrv.conf (customized)
keys\	Location of security key files	None
logs\	Location of log files	None
loopback\	Used for automatic loopback detection	None
rules\	Location of Driver configuration file	Scripting.xml (customized)
schema\	Location of schema files	schema.def (customized)
scripts\	Location of script files	Those required by your Driver (customized)

If you are using an installation program, you can obtain the driver’s installation path from the following registry value:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Novell\Windows Script Driver\Path
```

The formats of `wsdrv.conf` and `schema.def` can be viewed in [Section 4.2, “The Driver Shim Configuration File,” on page 29](#) and [Section 5.2, “The Connected System Schema File,” on page 34](#).

If SSL encryption is desired for communication between the driver shim and Identity Manager engine, a certificate must be retrieved from the Identity Vault. Run `wsdriver.exe -s` and follow the prompts to retrieve the certificate, which will be stored in the `keys\` directory. You must have LDAP with SSL available for the Metadirectory. When making an installation program for deployment, you might want to run `wsdriver.exe -s` as part of the installation.

To ensure that only authorized systems access the Metadirectory, a Driver Object password and Remote Loader password are used. Run `wsdriver.exe -sp` and enter the passwords at the prompts. This action can be incorporated into an installation program.

You should run a Scripting driver as a service. To install the service, run `wsdriver.exe -installService`, or install it as part of an installation program. The service can then be run from the Services applet. The service can be removed with `wsdriver.exe -removeService`.

You should distribute the XML configuration file that contains parameters and policies your driver needs. The user can then select it when installing your driver.

5.8 Using an Alternate Scripting Language

An alternative scripting language can be used by porting the globals, IDMLib, and other scripts to the alternative language. Porting requires a solid understanding of one of the provided languages (Bourne Shell, Perl and Microsoft VBScript) and the target language. The language should have facilities for executing programs and reading/writing to their standard input and output. The script language program must be able to be run from the command prompt.

To change the program the driver executes when running a script, modify the Script Command driver parameter. After the name of the program, you can include any needed command line parameters. To this string, the driver appends a space and the name of the Subscriber, Polling or Heartbeat script. For the Subscriber script, the full path to the event file and the full path to the Driver Parameter file are the next two parameters. For the Polling and Heartbeat scripts, the Driver Parameter file is the next parameter.

The event file contains the event document in XML format. On Windows, you must use the `EventReader.exe` program included with the Scripting driver to process this file. Running `EventReader` with the `nvpairs` option retrieves the event document as name/value pairs (the default). Using the `xds` option retrieves the event in its original XDS/XML format. On Linux and UNIX, events are submitted to scripts using shared memory. You must use the Shared Memory Helper, `ussmh`, to process these events. Running `ussmh` with the `-xml` option retrieves the XML document in its original XDS/XML format.

The Driver Parameter file contains name/value pairs for the driver parameters. See [Section 5.5, “UNIX Shell Developer Guide,” on page 41](#), [Section 5.6, “Perl Developer Guide,” on page 55](#), and [Section 5.7, “Microsoft VBScript Developer Guide,” on page 69](#) for more information.

On the Publisher channel, you must use the Change Log tool (`idmevent.exe` on Windows and `usclh` on Linux/UNIX), to submit events to the driver.

The names of the Subscriber, Polling and Heartbeat scripts can be altered in the driver parameters.

Using the Scripting Driver

6

This section provides information about operational tasks commonly used with the Identity Manager 3.6.1 driver for Scripting.

Topics include

- ♦ [Section 6.1, “Starting and Stopping the Driver,” on page 85](#)
- ♦ [Section 6.2, “Starting and Stopping the Driver Shim,” on page 85](#)
- ♦ [Section 6.3, “Displaying Driver Shim Status,” on page 86](#)
- ♦ [Section 6.4, “Monitoring Driver Messages,” on page 86](#)

6.1 Starting and Stopping the Driver

To start the driver:

- 1 In Novell® iManager, navigate to the Driver Overview for the driver.
- 2 Click the upper right corner of the driver icon.
- 3 Click *Start driver*.

To stop the driver:

- 1 In iManager, navigate to the Driver Overview for the driver.
- 2 Click the upper right corner of the driver icon.
- 3 Click *Stop driver*.

6.2 Starting and Stopping the Driver Shim

To start the driver shim, perform the task appropriate for your operating system as shown in the following table:

Table 6-1 *Starting the Driver Shim*

Operating System	Command/Task
AIX	<code>/etc/rc.d/init.d/usdrvd start</code>
HP-UX	<code>/sbin/init.d/usdrvd start</code>
Linux	<code>/etc/init.d/usdrvd start</code>
Solaris	<code>/etc/init.d/usdrvd start</code>
Windows	Use the Windows Services application to start the Novell Identity Manager Windows Script Driver service.

To stop the driver shim, perform the task appropriate for your operating system as shown in the following table:

Table 6-2 *Stopping the Driver Shim*

Operating System	Command/Task
AIX	<code>/etc/rc.d/init.d/usdrvd stop</code>
HP-UX	<code>/sbin/init.d/usdrvd stop</code>
Linux	<code>/etc/init.d/usdrvd stop</code>
Solaris	<code>/etc/init.d/usdrvd stop</code>
Windows	Use the Windows Services application to stop the Novell Identity Manager Windows Script Driver service.

You can also run the driver shim on Windows from the command line by executing `wsdriver.exe` in the `bin` directory under the driver installation directory. Output is written to the console. Stop the driver shim by pressing Ctrl+Break. Running the driver shim this way is recommended only for development and testing.

6.3 Displaying Driver Shim Status

To see status and version information for the driver shim, use the appropriate command for your operating system as shown in the following table:

Table 6-3 *Displaying the Status of the Driver Shim*

Operating System	Command
AIX	<code>/etc/rc.d/init.d/usdrvd status</code>
HP-UX	<code>/sbin/init.d/usdrvd status</code>
Linux	<code>/etc/init.d/usdrvd status</code>
Solaris	<code>/etc/init.d/usdrvd status</code>
Windows	Use the Windows Services application.

6.4 Monitoring Driver Messages

The Scripting driver writes messages to the system log on Linux and UNIX, and the trace file on Windows (`trace.log` in the `logs` directory by default). For details about the messages written by the driver, see [Appendix B, “System and Error Messages,”](#) on page 99.

Securing the Scripting Driver

7

The section describes best practices for securing the Identity Manager 3.6.1 driver for Scripting. Topics include

- ♦ [Section 7.1, “Using SSL,” on page 87](#)
- ♦ [Section 7.2, “Physical Security,” on page 87](#)
- ♦ [Section 7.3, “Network Security,” on page 87](#)
- ♦ [Section 7.4, “Auditing,” on page 87](#)
- ♦ [Section 7.5, “Driver Security Certificates,” on page 87](#)
- ♦ [Section 7.6, “Driver Shell Scripts,” on page 88](#)
- ♦ [Section 7.7, “The Change Log,” on page 88](#)
- ♦ [Section 7.8, “Driver Passwords,” on page 88](#)
- ♦ [Section 7.9, “Driver Code,” on page 88](#)
- ♦ [Section 7.10, “Administrative Users,” on page 89](#)
- ♦ [Section 7.11, “Connected Systems,” on page 89](#)

For additional information about Identity Manager security, see the Novell® Identity Manager 3.6.1 Administration Guide on the [Identity Manager 3.6.1 Documentation Web site \(http://www.novell.com/documentation/idm36\)](http://www.novell.com/documentation/idm36).

7.1 Using SSL

Enable SSL for communication between the Metadirectory engine and the driver shim on the connected system. For more information, see [“Use SSL” on page 24](#). If you don’t enable SSL, you are sending information, including passwords, in the clear.

7.2 Physical Security

Keep your servers in a physically secure location with access by authorized personnel only.

7.3 Network Security

Require users outside of the corporate firewall to use a VPN to access corporate data.

7.4 Auditing

Track changes to sensitive information. Examine audit logs periodically. For details about using Novell Sentinel to monitor driver operation, see the [Novell Sentinel Documentation \(http://www.novell.com/documentation/sentinel61/index.html\)](http://www.novell.com/documentation/sentinel61/index.html).

7.5 Driver Security Certificates

SSL uses security certificates to control, encrypt, and authenticate communications.

Ensure that the security certificate directory `/opt/novell/usdrv/keys` is appropriately protected on Linux or UNIX platforms and `C:\Novell\wsdrv\keys` is protected on Windows platforms. The installation program sets secure file permissions for these directories.

The Driver Shim and the Identity Manager engine communicate through SSL using a certificate created in the Identity Vault and retrieved by the Driver Shim during the installation process. For more information on this certificate and how to renew or install third-party certificates, refer to the *Identity Manager Administration Guide*.

The Embedded Remote Loader web interface uses a dynamically generated, self-signed certificate for SSL communication. The details of this certificate are as follows:

Subject: SSL Server

Issuer: SSL Server

Validity: 1 year

Serial Number: 0

Key: 1024-bit RSA

Renewal of this certificate automatically occurs when the Driver Shim is restarted on the connected platform.

7.6 Driver Shell Scripts

The driver uses scripts to perform updates on the connected system, and to collect changes made there. Ensure that the script directory is appropriately protected. The installation program sets secure file permissions for this directory where applicable.

7.7 The Change Log

The change log file contains information about events on the connected system, including passwords. It is encrypted, but it should be protected against access by unauthorized users. Ensure that the change log directory is appropriately protected. The installation program sets secure file permissions for this directory where applicable.

7.8 Driver Passwords

Use strong passwords for the Driver object and Remote Loader passwords, and restrict knowledge of them to authorized personnel. These passwords are stored in encrypted form in the security certificate directory keys. The installation program sets secure file permissions for this directory.

7.9 Driver Code

Ensure that the driver executable directory `bin` and the driver files in `/usr/sbin` (Linux/UNIX only) are appropriately protected. The installation program sets secure file permissions for these items where applicable.

7.10 Administrative Users

Ensure that accounts with elevated rights on the Metadirectory system, Identity Vault systems, and the connected systems are appropriately secure. Protect administrative user IDs with strong passwords.

7.11 Connected Systems

Ensure that connected systems can be trusted with account information, including passwords, for the portions of the tree that are configured as their base containers.

Troubleshooting

A

This section provides information about troubleshooting the Identity Manager 3.6.1 driver for Scripting. Major topics include

- ♦ [Section A.1, “Driver Status and Diagnostic Files,” on page 91](#)
- ♦ [Section A.2, “Troubleshooting Common Problems,” on page 93](#)
- ♦ [Section A.3, “Shared Memory Errors \(Linux/UNIX only\),” on page 97](#)

A.1 Driver Status and Diagnostic Files

There are several log files that you can view to examine driver operation.

- ♦ [Section A.1.1, “The System Log \(Linux/UNIX only\),” on page 91](#)
- ♦ [Section A.1.2, “The Trace File,” on page 92](#)
- ♦ [Section A.1.3, “The Script Output File,” on page 93](#)
- ♦ [Section A.1.4, “DSTRACE,” on page 93](#)
- ♦ [Section A.1.5, “The Status Log,” on page 93](#)

A.1.1 The System Log (Linux/UNIX only)

The system log is used by the Scripting driver shim to record urgent, informational, and debug messages. Examining these should be foremost in your troubleshooting efforts. For detailed message documentation, see [Appendix B, “System and Error Messages,” on page 99](#).

The location for the system log varies from system to system and is generally configured through `/etc/syslog.conf`. The amount of information that is logged by the driver can also be configured through this system log configuration file. The following is a sample fragment from `/etc/syslog.conf`:

```
# sample /etc/syslog.conf
#
*.err;kern.notice;auth.notice                /dev/sysmsg
*.err;kern.debug;daemon.notice;mail.crit     /var/adm/messages

*.alert;kern.err;daemon.err                  operator
*.alert                                       root
```

The options in the first column determine which messages are logged. The options in the second column specify the destination file or user to send the log output to. For example, specifying `*.err` logs all messages with a priority of `err` or above. For more information about syslog priorities, view your system documentation using the `man syslog` command. Messages from the driver shim and messages from the scripts are logged with various priorities as shown in [Table A-1](#). The information that is recorded depends on your syslog configuration.

Table A-1 Message Priorities

Message Topic	Priority
Script being called	DEBUG
Successful Linux or UNIX command execution	INFO
Publication events	INFO
Failures	ERR

A.1.2 The Trace File

The default trace file exists on the connected system as `trace.log` in the `logs` directory under the installation folder. A large amount of debug information can be written to this file. Use the trace level setting in your driver shim configuration file to control what is written to the file. For details about the driver shim configuration file, see [Section 4.2, “The Driver Shim Configuration File,”](#) on [page 29](#).

Table A-2 Driver Shim Trace Levels

Trace Level	Description
0	No debugging
1–3	Identity Manager messages. Higher trace levels provide more detail.
4	Previous level plus Remote Loader, driver, driver shim, and driver connection messages.
5–7	Previous level plus change log and loopback messages. Higher trace levels provide more detail.
8	Previous level plus driver status log, driver parameters, driver command line, driver security, driver Web server, driver schema, driver encryption, driver PAM, driver SOAP API, and driver include/exclude file messages.
9	Previous level plus low-level networking and operating system messages.
10	Previous level plus maximum low-level program details (all options).

The following is an example configuration line to set the trace level:

```
-trace 9
```

To view the trace file:

- 1 Use a Web browser to access the driver shim at `https://driver-address:8091`. Substitute the DNS name or IP address of your driver for `driver-address`.
- 2 Authenticate by using any username and the password that you specified as the Remote Loader password.
- 3 Click *Trace*.

A.1.3 The Script Output File

By default, script output is written to `script-trace.log` in the `logs` directory under the driver installation directory on the connected system. This file captures the output from all scripts executed by the driver shim. The location of the script output file is set in the driver parameters.

A.1.4 DSTRACE

You can view Identity Manager information using the DSTRACE facility on the Metadirectory server. Use iManager to set the tracing level. For example, trace level 2 shows Identity Vault events in XML documents, and trace level 5 shows the results of policy execution. Because a high volume of trace output is produced, we recommend that you capture the trace output to a file. For details about using DSTRACE, see the *Identity Manager 3.6.1 Common Driver Administration Guide*.

A.1.5 The Status Log

The status log is a condensed summary of the events that have been recorded on the Subscriber and Publisher channels. This file exists on the connected system as `dirxml.log` in the `logs` directory under the driver installation directory. You can also view the status log in iManager on the Driver Overview page. You can change the log level to specify what types of events to log. For details about using the status log, see the *Identity Manager 3.6.1 Common Driver Administration Guide*.

To view the status log:

- 1 Use a Web browser to access the driver shim at `https://driver-address:8091`. Substitute the DNS name or IP address of your driver for `driver-address`.
- 2 Authenticate by using any username and the password that you specified as the Remote Loader password.
- 3 Click *Status*.

A.2 Troubleshooting Common Problems

- ♦ [Section A.2.1, “Driver Shim Installation Failure,” on page 94](#)
- ♦ [Section A.2.2, “Driver Rules Installation Failure,” on page 94](#)
- ♦ [Section A.2.3, “Driver Certificate Setup Failure,” on page 94](#)
- ♦ [Section A.2.4, “Driver Start Failure,” on page 94](#)
- ♦ [Section A.2.5, “Driver Shim Startup or Communication Failure,” on page 95](#)
- ♦ [Section A.2.6, “Users or Groups Are Not Provisioned to the Connected System,” on page 95](#)
- ♦ [Section A.2.7, “Users or Groups Are Not Provisioned to the Identity Vault,” on page 95](#)
- ♦ [Section A.2.8, “Identity Vault User Passwords Are Not Provisioned to the Connected System,” on page 96](#)
- ♦ [Section A.2.9, “Connected System User Passwords Are Not Provisioned to the Identity Vault,” on page 96](#)
- ♦ [Section A.2.10, “Metadirectory Objects Are Not Modified, Deleted, Renamed, or Moved,” on page 96](#)

A.2.1 Driver Shim Installation Failure

- ♦ Ensure that you use the correct installation program for your operating system and that you are running on a supported operating system. For details, see [Chapter 2, “Planning for the Scripting Driver,” on page 15](#).
- ♦ Ensure that you run the installation as `root` (Linux/UNIX) or Administrator (Windows) or equivalent.
- ♦ (Linux/UNIX only) Ensure that your package management software, such as RPM, is installed and up-to-date.

A.2.2 Driver Rules Installation Failure

Ensure that you use iManager 2.7 or higher, with the Identity Manager plug-ins installed.

A.2.3 Driver Certificate Setup Failure

To set up certificates, the driver shim communicates with the Metadirectory server using the LDAP secure port (636).

- ♦ Ensure that eDirectory™ is running LDAP with SSL enabled. For details about configuring eDirectory, see the *Novell eDirectory 8.7.3 Administration Guide* on [the Novell eDirectory 8.7.3 Documentation Web site \(http://www.novell.com/documentation/edir873/index.html\)](http://www.novell.com/documentation/edir873/index.html).
- ♦ Ensure that the connected system has network connectivity to the Metadirectory server.

You can use the command `/opt/novell/usdrv/bin/usdrv -s` (Linux/UNIX) or `wsdriver -s` (Windows) to configure the certificate at any time.

If you cannot configure SSL using LDAP, you can install the certificate manually:

- 1 In iManager, browse the Security container to locate your tree's Certificate Authority (typically named `treeName CA`).
- 2 Click the Certificate Authority object.
- 3 Click *Modify Object*.
- 4 Select the *Certificates* tab.
- 5 Click *Public Key Certificate*.
- 6 Click *Export*.
- 7 Select *No* to export the certificate without the private key, then click *Next*.
- 8 Select *Base64* format, then click *Next*.
- 9 Click *Save* to save the exported certificate to a file, then specify a location to save the file.
- 10 Use FTP or another method to store the file on the connected system as `ca.pem` in the `keys` directory under the driver installation directory.

A.2.4 Driver Start Failure

- ♦ Examine the status log and DSTRACE output.

- ♦ The driver must be specified as a Remote Loader driver, even if the Identity Vault and connected system are the same computer. You can set this option in the iManager Driver Edit Properties window.
- ♦ You must activate both Identity Manager and the driver within 90 days. The Driver Set Overview page in iManager shows when Identity Manager requires activation. The Driver Overview page shows when the driver requires activation.

For details about activating Novell Identity Manager Products, see the *Identity Manager 3.6.1 Common Driver Administration Guide*.

For more information about troubleshooting Identity Manager engine errors, see the [Identity Manager 3.6.1 Documentation Web site \(http://www.novell.com/documentation/idm36\)](http://www.novell.com/documentation/idm36).

A.2.5 Driver Shim Startup or Communication Failure

- ♦ Examine the trace file.
- ♦ Ensure that the connected system's operating system version is supported. For a list of supported operating systems, see [Chapter 2, "Planning for the Scripting Driver," on page 15](#).
- ♦ Apply all patches for your operating system.
- ♦ Ensure that the Remote Loader and Driver object passwords that you specified while setting up the driver on the Metadirectory server match the passwords stored with the driver shim.

To update these passwords on the connected system, use the `/opt/novell/usdrv/bin/usdrv -sp` (Linux/UNIX) or use the `wsdriver -sp` (Windows) command. The passwords are stored under keys in the driver installation directory in encrypted files `dpwdf40` (Driver object password) and `lpwdf40` (Remote Loader password).

To update these passwords on the Metadirectory server, use iManager to update the driver configuration. For details, see [Section 4.1.2, "Driver Configuration Page," on page 25](#).

- ♦ Ensure that the correct host name and port number of the connected system are specified in the Driver Configuration Remote Loader connection parameters. You can change the port number (default 8090) in `usdrv.conf` (Linux/UNIX) or `wsdrv.conf` (Windows).

A.2.6 Users or Groups Are Not Provisioned to the Connected System

- ♦ Examine the status log, DSTRACE output, trace file, and script output file.
- ♦ To be provisioned, users and groups must be in the appropriate base container. You can view and change the base containers in iManager on the Global Configuration Values page of the Driver Edit Properties window.
- ♦ To provision identities from the Identity Vault to the connected system, the driver Data Flow property must be set to Bidirectional or Identity Vault to Application. To change this value, reimport the driver rules file over your existing driver.
- ♦ The user that the driver is security equivalent to must have rights to read information from the base container. For details about the rights required, see [Table 2-1 on page 17](#).

A.2.7 Users or Groups Are Not Provisioned to the Identity Vault

- ♦ Examine the status log, DSTRACE output, and trace file.

- ♦ Examine the User Base Container and Group Base Container GCV values. For more details, [Section 4.1.3, “Global Configuration Values Page,” on page 27.](#)
- ♦ To provision identities from the connected system to the Identity Vault, the driver Data Flow property must be set to Bidirectional or Application to Identity Vault. To change this value, reimport the driver rules file over your existing driver.
- ♦ The user that the driver is security equivalent to must have rights to update the base container. For details about the rights required, see [Table 2-1 on page 17.](#)

A.2.8 Identity Vault User Passwords Are Not Provisioned to the Connected System

- ♦ Examine the status log, DSTRACE output, and script output file.
- ♦ There are several password management properties available in iManager on the Global Configuration Values page of the Driver Edit Properties window. Ensure that the connected system accepts passwords from the Identity Vault. To determine the right settings for your environment, view the help for the options, or see the [Identity Manager 3.6.1 Common Driver Administration Guide.](#)
- ♦ Ensure that the user’s container has an assigned Universal Password policy and that the Synchronize Distribution Password When Setting Universal Password GCV is set for this policy.

A.2.9 Connected System User Passwords Are Not Provisioned to the Identity Vault

- ♦ Examine the status log, DSTRACE output, and the trace file.
- ♦ There are several password management properties available in iManager on the Global Configuration Values page of the Driver Edit Properties window. Ensure that at least one of the following options is set:
 - ♦ The Identity Vault Accepts Passwords from the Connected System
 - ♦ The Identity Vault Accepts Administrative Password Resets from the Connected System
 - ♦ To determine the right settings for your environment, view the help for the options, or see the [Identity Manager 3.6.1 Common Driver Administration Guide.](#)
 - ♦ If the Require Password Policy Validation before Publishing Passwords GCV is set, the user’s password must satisfy the password rules in the password policy assigned to the user container.

A.2.10 Metadirectory Objects Are Not Modified, Deleted, Renamed, or Moved

- ♦ Examine the status log, DSTRACE output, trace file, and script output file.
- ♦ Examine the driver Data Flow setting to verify the authoritative source for identities.

- Identity Vault and connected system identities must be associated before events are synchronized. To view an identity's associations, use Modify User/Group in iManager and click the *Identity Manager* tab.
- Identity Vault move events can remove the identity from the base container monitored by the driver to a container that is not monitored by the driver. This makes the move appear to be a delete.

A.3 Shared Memory Errors (Linux/UNIX only)

Shared memory is used by the driver shim to safely and securely communicate with the scripts on Linux and UNIX. If the system shared memory segments become unusable, you must shut down the process and fix the shared memory segments.

Shared memory segments can become unusable on some UNIX systems if the driver shim is improperly terminated without detaching from the segments. For information about how to properly stop the driver shim, see [Section 6.2, “Starting and Stopping the Driver Shim,” on page 85](#). You can use the `ipcs` system tool to locate these segments and the `ipcrm` tool to manually clear them as shown in the following example:

```
> ipcs -m
----- Shared Memory Segments -----
key          shmid    owner    perms    bytes    nattch    status
0x2a065bbd 1802241  root     600      16384    1
> ipcrm -m 1802241
```

The driver shim generates default segments of 16384 bytes with permissions at 600.

System and Error Messages

B

Components of the Identity Manager 3.6.1 driver for Scripting write messages to the system log to report operational status and problems. For more information about the system log, see [Section A.1.1, “The System Log \(Linux/UNIX only\),” on page 91](#) For detailed troubleshooting information, see [Appendix A, “Troubleshooting,” on page 91](#).

Each message begins with a code of 3-6 characters associated with the driver component that generated the message. Use this code to find message information quickly as follows:

- ♦ [Section B.1, “CFG Messages,” on page 99](#)
- ♦ [Section B.2, “CHGLOG Messages,” on page 100](#)
- ♦ [Section B.3, “DOM Messages,” on page 100](#)
- ♦ [Section B.4, “DRVCOM Messages,” on page 100](#)
- ♦ [Section B.5, “HES Messages,” on page 101](#)
- ♦ [Section B.6, “LWS Messages,” on page 101](#)
- ♦ [Section B.7, “NET Messages,” on page 102](#)
- ♦ [Section B.8, “NIX Messages \(Linux/UNIX only\),” on page 103](#)
- ♦ [Section B.9, “OAP Messages,” on page 105](#)
- ♦ [Section B.10, “RDXML Messages,” on page 106](#)

B.1 CFG Messages

Messages beginning with CFG are issued by configuration file processing.

CFG001E Could not open configuration file filename.

Explanation: Could not open the configuration file.

Possible Cause: The file does not exist.

Possible Cause: You don't have permission to read the file.

Action: Ensure that the configuration file exists at the correct location and that you have file system rights to read it.

CFG002E Error parsing configuration file line:

Explanation: The line is not formatted as a valid configuration statement and cannot be parsed.

Possible Cause: The configuration file contains invalid or incorrect statements.

Action: Correct the line in the configuration file.

CFG003W Configuration file line was ignored. No matching statement name found: <configline>.

Explanation: This line is formatted as a valid configuration file statement, but the statement is not recognized. The line is ignored.

Possible Cause: The statement is incorrectly typed or the statement name is used only in a newer version of the software.

Action: Correct the statement.

CFG004E Error parsing configuration file line. No statement name was found: <configLine>.

Explanation: Could not find a statement name on the configuration line.

Action: Correct the line in the configuration file to supply the required statement.

CFG005E A required statement *statement_id* is missing from the configuration file.

Explanation: The *statement_id* statement was not specified in the configuration file, but is required for the application to start.

Possible Cause: The configuration file is missing required statements.

Action: Add the required statement to the configuration file.

B.2 CHGLOG Messages

Messages beginning with CHGLOG are issued by change log processing.

**CHGLOG000I nameversion Copyright 2005 Omnibond Systems, LLC.
ID=code_id_string.**

Explanation: This message identifies the system component version.

Action: No action is required.

B.3 DOM Messages

Messages beginning with DOM are issued by driver components as they communicate among themselves.

DOM0001W XML parser error encountered: errorString.

Explanation: An error was detected while parsing an XML document.

Possible Cause: The XML document was incomplete, or it was not a properly constructed XML document.

Action: See the error string for additional details about the error. Some errors, such as no element found, can occur during normal operation and indicate that an empty XML document was received.

B.4 DRVCOM Messages

Messages beginning with DRVCOM are issued by the include/exclude system.

**DRVCOM000I nameversion Copyright 2005 Omnibond Systems, LLC.
ID=code_id_string.**

Explanation: This message identifies the system component version.

Action: No action is required.

DRVCOM001W Invalid include/exclude CLASS statement.

Explanation: The include/exclude configuration file contains an invalid CLASS statement.

Action: Correct the include/exclude configuration file with proper syntax.

DRVCOM002D An include/exclude Rule was added for class: class.

Explanation: The include/exclude configuration supplied a rule for the specified class.

Action: None.

DRVCOM003D An include/exclude Association Rule was added for association association.

Explanation: The include/exclude configuration supplied an association rule for the specified association.

Action: None.

B.5 HES Messages

Messages beginning with HES are issued by driver components as they use HTTP to communicate.

HES001E Unable to initialize the HTTP client.

Explanation: Communications in the client could not be initialized.

Possible Cause: Memory is exhausted.

Action: Increase the amount of memory available to the process.

HES002I Connecting to host host_name on port port_number.

Explanation: The client is connecting to the specified server.

Action: None.

HES003W SSL communications have an incorrect certificate. rc = rc.

Explanation: The security certificate for SSL services could not be verified.

Possible Cause: The certificate files might be missing or invalid.

Action: Obtain a new certificate.

B.6 LWS Messages

Messages beginning with LWS are issued by the integrated HTTP server.

LWS0001I Server has been initialized.

Explanation: The server has successfully completed its initialization phase.

Action: None. Informational only.

LWS0002I All services are now active.

Explanation: All of the services offered by the server are now active and ready for work.

Action: None. Informational only.

LWS0003I Server shut down successfully.

Explanation: The server processing completed normally. The server ends with a return code of 0.

Action: No action is required.

LWS0004W Server shut down with warnings.

Explanation: The server processing completed normally with at least one warning. The server ends with a return code of 4.

Action: See the log for additional messages that describe the warning conditions.

LWS0005E Server shut down with errors.

Explanation: The server processing ended with one or more errors. The server ends with a return code of 8.

Action: See the log for additional messages that describe the error conditions.

LWS0006I Starting service.

Explanation: The server is starting the specified service.

Action: None. Informational only.

LWS0007E Failed to start service.

Explanation: The server attempted to start the specified service, but the service could not start. The server terminates processing.

Action: See the log for additional messages that describe the error condition.

LWS0008I Stopping all services.

Explanation: The server was requested to stop. All services are notified and will subsequently end processing.

Action: None. Informational only.

B.7 NET Messages

Messages beginning with NET are issued by driver components during verification of SSL certificates.

NET001W Certificate verification failed. Result is result.

Explanation: A valid security certificate could not be obtained from the connection client. Diagnostic information is given by result.

Possible Cause: A security certificate has not been obtained for the component.

Possible Cause: The security certificate has expired.

Possible Cause: The component certificate directory has been corrupted.

Action: Respond as indicated by result. Obtain a new certificate if appropriate.

B.8 NIX Messages (Linux/UNIX only)

Messages beginning with NIX are issued by the driver shim.

NIX000I nameversion Copyright 2005 Omnibond Systems, LLC. ID=code_id_string.

Explanation: This message identifies the system component version.

Action: No action is required.

NIX001S An error occurred attempting to attach the shared memory segment to an address space (errno=errno).

Explanation: The driver uses shared memory as the mechanism for providing information to the scripts. An error occurred attempting to attach the shared memory to a physical address for access.

Possible Cause: The calling process has no access permissions for the requested attach type.

Possible Cause: An invalid or non-page-aligned address was provided to the system routine.

Possible Cause: Memory could not be allocated for the descriptor or for the page tables.

Action: Restart the driver process and ensure that there are adequate memory resources. Verify that the driver process is run as root and has permissions to read its configuration files. Contact Novell[®] Support for additional instructions if necessary.

NIX002S An error occurred while attempting to allocate a shared memory segment (errno = errno).

Explanation: The driver uses shared memory as the mechanism for providing information to the scripts. An error occurred attempting to allocate a shared memory segment.

Possible Cause: The memory size was too small or too large.

Possible Cause: The system shared memory settings might not have adequate values

Possible Cause: The memory segment could not be created because it already exists. This could be caused by an abnormal termination of a previous driver process.

Possible Cause: All possible shared memory IDs have been taken.

Possible Cause: Allocating a segment of the requested size would cause the system to exceed the system-wide limit on shared memory.

Possible Cause: No shared memory segment exists for the given key.

Possible Cause: The user or process does not have permission to access the shared memory segment.

Possible Cause: No memory could be allocated for segment overhead..

Action: Restart the driver process and ensure that there is sufficient memory.

- Action: Verify that the driver process is run as root and has permissions to read its configuration files.
- Action: Verify that the driver process is run as root and has permissions to read its configuration files
- Action: If there are other applications on the server that use shared memory, ensure that they are running, healthy, and do not conflict with the requirements for the driver.
- Action: Contact Novell Support for additional instructions if necessary.

NIX003S An error occurred attempting to create a System V IPC key. The project identifier pathname = pathname.

- Explanation: The driver uses shared memory as the mechanism for providing information to the scripts. An error occurred attempting to create the key used to specify the shared memory segment.
- Possible Cause: The project pathname is invalid or does not exist.
- Action: Restart the driver process.
- Action: Ensure that the file pathname is correct and that the process has adequate permissions to read the path.

NIX004S An error occurred while writing data to shared memory (bytes = bytes, allocationSize = allocationSize).

- Explanation: The driver uses shared memory as the mechanism for providing information to the shell scripts. An error occurred while writing data from the driver process into the shared memory segment.
- Possible Cause: Invalid memory resources or internal error.
- Action: Contact Novell Support.

NIX005S An error occurred attempting to set an environment variable.

- Explanation: The driver uses environment variables for some of the communication between the driver and other processes called from the scripts. An error occurred setting an environment variable.
- Possible Cause: There was not enough space to allocate the new environment.
- Action: Restart the driver and ensure that there are adequate memory resources for the driver process.

NIX006S An error occurred attempting to execute the script [script].

- Explanation: The driver uses scripts to update the system for events from the Identity Vault. An error occurred while attempting to execute one of these scripts.
- Possible Cause: The script does not exist on the local system.
- Possible Cause: A memory or environment allocation failure occurred.
- Action: Restart the driver and ensure that the script exists on the local system.

NIX007S An error occurred attempting to terminate the script [script].

Explanation: The driver uses scripts to update the system for events from the Identity Vault. An error occurred while attempting to terminate the script.

Possible Cause: The script does not exist on the local system.

Possible Cause: A memory or environment allocation failure occurred.

Action: Restart the driver and ensure that the script exists on the local system.

NIX008S The shared memory tool was unable to retrieve a key from the environment.

Explanation: The shared memory tool uses an environment variable to retrieve the key used to unlock the shared memory region and access driver shim data. The tool could not obtain the key from the environment.

Possible Cause: The driver shim cannot set environment variables, or the environment has become corrupt during event processing.

Action: Restart the driver shim process and clear any residual shared memory segments.

B.9 OAP Messages

Messages beginning with OAP are issued by driver components while communicating among themselves.

OAP001E Error in SSL configuration. Verify system entropy.

Explanation: Entropy could not be obtained for SSL.

Possible Cause: A source of entropy is not configured for the system.

Action: Obtain and configure a source of entropy for the system.

OAP002E Error in SSL connect. Network address does not match certificate.

Explanation: The SSL client could not trust the SSL server it connected to, because the address of the server did not match the DNS name or IP address that was found in the certificate for the server.

Possible Cause: The appropriate credentials are missing from the configuration.

Action: If you cannot resolve the error, collect diagnostic information and call Novell Support.

OAP003E Error in SSL connect. Verify address and port.

Explanation: A TCP/IP connection could not be made.

Possible Cause: The server is not running.

Possible Cause: The configuration information does not specify the correct network address or port number.

Action: Verify that the server is running properly.

OAP004E HTTP Error: cause.

Explanation: The username or password provided failed basic authentication.

Possible Cause: The username or password is incorrect.

Action: Verify that username is in full context (cn=user,ou=ctx,o=org or user.ctx.org) and that the password was correctly typed.

OAP005E HTTP Error: Internal Server Error.

Explanation: The server experienced an internal error that prevents the request from being processed.

Possible Cause: A secure LDAP server is not available.

Action: Ensure that the LDAP server is available.

Action: Ensure that the LDAP host and port are configured correctly.

B.10 RDXML Messages

Messages beginning with RDXML are issued by the embedded Remote Loader.

**RDXML000I nameversion Copyright 2005 Omnibond Systems, LLC.
ID=code_id_string.**

Explanation: This message identifies the system component version.

Action: No action is required.

RDXML001I Client connection established.

Explanation: A client has connected to the driver. This can be the Metadirectory engine connecting to process events to and from the driver, or a Web-based request to view information or publish changes through the SOAP mechanism.

Action: No action required.

RDXML002I Request issued to start Driver Shim.

Explanation: The driver received a command to start the driver shim and begin processing events.

Action: No action required.

RDXML003E An unrecognized command was issued. The driver shim is shutting down.

Explanation: The driver received an unrecognized command from the Metadirectory engine. The driver shim is shutting down to avoid further errors.

Possible Cause: Network error.

Possible Cause: Invalid data sent to the driver.

Possible Cause: The Metadirectory engine version might have been updated with new commands that are unrecognized by this version of the driver.

Possible Cause: This message is logged when the driver shim process is shut down from the connected system rather than from a Driver object request. The local system can queue an invalid command to the driver shim to simulate a shutdown request and terminate the running process.

Action: Ensure that the network connection is secured and working properly.

Action: Apply updates for the engine or driver if necessary.

Action: If the driver shim process was shut down from the local system, no action is required.

RDXML004I Client Disconnected.

Explanation: A client has disconnected from the driver. This might be the Metadirectory engine disconnecting after a driver shutdown request or a Web-based request that has ended.

Action: No action required.

RDXML005W Unable to establish client connection.

Explanation: A client attempted to connect to the driver, but was disconnected prematurely.

Possible Cause: The client is not running in SSL mode.

Possible Cause: Mismatched SSL versions or mismatched certificate authorities.

Possible Cause: Problems initializing SSL libraries because of improperly configured system entropy settings.

Action: Ensure that both the Metadirectory engine and the driver are running in the same mode: either clear text mode or SSL mode.

Action: If you are using SSL, ensure that the driver and Metadirectory engine have properly configured certificates, and that the driver system is configured properly for entropy.

RDXML006E Error in Remote Loader Handshake.

Explanation: The Metadirectory engine attempted to connect to the driver, but the authorization process failed. Authorization requires that both supply mutually acceptable passwords. Passwords are configured at installation.

Possible Cause: The Remote Loader or Driver object passwords do not match.

Action: Set the Remote Loader and Driver object passwords to the same value for both the driver and the driver shim. Use iManager to modify the driver properties. Re-configure the driver shim on the connected system.

RDXML007I Driver Shim has successfully started and is ready to process events.

Explanation: The Metadirectory engine has requested the driver to start the shim for event processing, and the driver shim has successfully started.

Action: No action required.

RDXML008W Unable to establish client connection from remoteName.

Explanation: A client attempted to connect to the driver, but was disconnected prematurely.

Possible Cause: The client is not running in SSL mode.

Possible Cause: Mismatched SSL versions or mismatched certificate authorities.

Possible Cause: Problems initializing SSL libraries because of improperly configured system entropy settings.

Action: Ensure that both the Metadirectory engine and the driver are running in the same mode: either clear text mode or SSL mode.

Action: If you are using SSL, ensure that the driver and Metadirectory engine have properly configured certificates, and that the driver system is configured properly for entropy.

RDXML009I Client connection established from remoteName.

Explanation: A client has connected to the driver. This can be the Metadirectory engine connecting to process events to and from the driver, or a Web-based request to view information or publish changes through the SOAP mechanism.

Action: No action required.

IDMLib Reference

C

The Identity Manager 3.6.1 driver for Scripting provides an API library for accessing and updating data to and from the driver shim during event subscription and publication.

Major topics in this section include

- ♦ [Section C.1, “UNIX Shell \(idmlib.sh\) Reference,” on page 109](#)
- ♦ [Section C.2, “Perl \(IDMLib.pm\) Reference,” on page 112](#)
- ♦ [Section C.3, “Microsoft VBScript \(IDMLib.vbs\) Reference,” on page 115](#)

C.1 UNIX Shell (idmlib.sh) Reference

The scripts are written for the Linux and UNIX Bourne Shell. They are located in the scripts folder below the folder where the driver was installed (`/opt/novell/usdrv/` by default).

Subscriber events are submitted to `subscriber.sh`, which then calls the script for the event. Modify the shell script file corresponding to the event type: `add.sh`, `modify.sh`, `modify-password.sh`, `delete.sh`, `move.sh`, `rename.sh`. Queries of the external system should be handled in `query.sh`.

The Publisher calls `poll.sh` periodically. The frequency of the poll is determined by the Polling Interval driver parameter (60 seconds by default). Edit `poll.sh` to allow the driver to respond to events in the external account management system.

The Publisher calls `heartbeat.sh` periodically to determine whether the external account management system is responding correctly.

The built-in functions below are defined in `idmlib.sh`.

C.1.1 General Functions

- ♦ [“IDMGETDRVVAR ParamName” on page 109](#)
- ♦ [“IDMTRACE Message” on page 110](#)
- ♦ [“EXEC Command” on page 110](#)
- ♦ [“STATUS Level Message” on page 110](#)
- ♦ [“STATUS_SUCCESS Message” on page 110](#)
- ♦ [“STATUS_WARNING Message” on page 110](#)
- ♦ [“STATUS_RETRY Message” on page 110](#)
- ♦ [“STATUS_ERROR Message” on page 110](#)
- ♦ [“STATUS_FATAL Message” on page 110](#)

IDMGETDRVVAR ParamName

Returns the string value for the Driver parameter specified by the string ParamName.

IDMTRACE Message

Appends the specified message to the user-defined trace file.

EXEC Command

Executes an external program using the specified command line, and returns its numerical exit code on completion.

STATUS Level Message

Sends a status document with given level and message to return to the Identity Manager engine when the script completes.

The status document as seen by the engine looks like the following:

```
<status level="success">This is a message</status>
```

STATUS_SUCCESS Message

Sends a status document with a success level and message to return to the Identity Manager engine when the script completes.

STATUS_WARNING Message

Sends a status document with a warning level and message to return to the Identity Manager engine when the script completes.

STATUS_RETRY Message

Sends a status document with a retry level and message to return to the Identity Manager engine when the script completes.

STATUS_ERROR Message

Sends a status document with a error level and message to return to the Identity Manager engine when the script completes.

STATUS_FATAL Message

Sends a status document with a fatal level and message to return to the Identity Manager engine when the script completes.

C.1.2 Subscriber Functions

- ♦ “IDMGETSUBVAR ParamName” on page 110
- ♦ “IDMGETVAR Name” on page 111
- ♦ “IDMSETVAR Name Value” on page 111

IDMGETSUBVAR ParamName

Returns the string value for the Subscriber parameter specified by the string ParamName.

IDMGETVAR Name

Returns a string value for the item specified by Name through standard output. If no values exist, Empty is returned. If the value is multi-valued, each value will be separated by a newline character.

IDMSETVAR Name Value

Sets a single string value for the item specified by Name to be returned to the driver engine.

C.1.3 Publisher Functions

Only one function exists in this category.

IDMGETPUBVAR ParamName

Returns the string value for the Publisher parameter specified by the string ParamName.

C.1.4 Query Functions

- ♦ “[IDMQUERY ClassName Association ReadAttrs](#)” on page 111
- ♦ “[IDMGETQVAR ParamName](#)” on page 111

IDMQUERY ClassName Association ReadAttrs

Performs a query to the engine with the given ClassName, Association and ReadAttrs

IDMGETQVAR ParamName

Retrieves a string value for the query result item, specified by Name, through standard output. If no values exist, Empty is returned. If the value is multi-valued, each value is separated by a newline character.

C.1.5 Heartbeat Functions

- ♦ “[HEARTBEAT_SUCCESS Message](#)” on page 111
- ♦ “[HEARTBEAT_ERROR Message](#)” on page 111
- ♦ “[HEARTBEAT_WARNING Message](#)” on page 112

HEARTBEAT_SUCCESS Message

Use these functions in the `heartbeat.sh` script to indicate the status of the external application. Heartbeat documents are sent to the engine in following format:

```
<status level="success" type="heartbeat">This is a heartbeat message</status>
```

HEARTBEAT_ERROR Message

Use these functions in the `heartbeat.sh` script to indicate the status of the external application. Heartbeat documents are sent to the engine in following format:

```
<status level="success" type="heartbeat">This is a heartbeat message</status>
```

HEARTBEAT_WARNING Message

Use these functions in the `heartbeat.sh` script to indicate the status of the external application. Heartbeat documents are sent to the engine in following format:

```
<status level="success" type="heartbeat">This is a heartbeat message</status>
```

C.2 Perl (IDMLib.pm) Reference

These scripts are written for the Linux and UNIX Perl interpreter. They are located in the scripts folder below the folder where the driver was installed (`/opt/novell/usdrv/` by default).

Subscriber events are submitted to `subscriber.pl`, which then calls the script for the event. Modify the Perl script file corresponding to the event type: `add.pl`, `modify.pl`, `modify-password.pl`, `delete.pl`, `move.pl`, `rename.pl`. Queries of the external system should be handled in `query.pl`.

The Publisher calls `poll.pl` periodically. The frequency of the poll is determined by the Polling Interval driver parameter (60 seconds by default). Edit `poll.pl` to allow the driver to respond to events in the external account management system.

The Publisher calls `heartbeat.pl` periodically to determine whether the external account management system is responding correctly.

The built-in functions below are defined in `IDMLib.pm`.

C.2.1 General Functions

- ♦ “`idmgetvar($ParamName)`” on page 112
- ♦ “`idmtrace($Message)`” on page 112
- ♦ “`exec($Command)`” on page 113
- ♦ “`status($Level, $Message)`” on page 113
- ♦ “`status_success($Message)`” on page 113
- ♦ “`status_warning($Message)`” on page 113
- ♦ “`status_retry($Message)`” on page 113
- ♦ “`status_error($Message)`” on page 113
- ♦ “`status_fatal($Message)`” on page 113

idmgetvar(\$ParamName)

Returns the string value for the Driver parameter specified by the string `ParamName`.

idmtrace(\$Message)

Appends the specified message to the user-defined trace file.

exec(\$Command)

Executes an external program using the specified command line, and returns its numerical exit code on completion.

status(\$Level, \$Message)

Sends a status document with given level and message to return to the Identity Manager engine when the script completes.

The status document as seen by the engine looks like the following:

```
<status level="success">This is a message</status>
```

status_success(\$Message)

Sends a status document with a success level and message to return to the Identity Manager engine when the script completes.

status_warning(\$Message)

Sends a status document with a warning level and message to return to the Identity Manager engine when the script completes.

status_retry(\$Message)

Sends a status document with a retry level and message to return to the Identity Manager engine when the script completes.

status_error(\$Message)

Sends a status document with a error level and message to return to the Identity Manager engine when the script completes.

status_fatal(\$Message)

Sends a status document with a fatal level and message to return to the Identity Manager engine when the script completes.

C.2.2 Subscriber Functions

- ♦ “[idmgetsubvar\(\\$ParamName\)](#)” on page 113
- ♦ “[idmgetvar\(\\$Name\)](#)” on page 113
- ♦ “[idmsetvar\(\\$Name, \\$Value\)](#)” on page 114

idmgetsubvar(\$ParamName)

Returns the string value for the Subscriber parameter specified by the string ParamName.

idmgetvar(\$Name)

Returns a string value for the item specified by Name through standard output. If no values exist, Empty is returned. If the value is multi-valued, each value is separated by a newline character.

idmsetvar(\$Name, \$Value)

Sets a single string value for the item specified by Name to be returned to the driver engine.

C.2.3 Publisher Functions

- ♦ “[idmgetpubvar\(\\$ParamName\)](#)” on page 114

idmgetpubvar(\$ParamName)

Returns the string value for the Publisher parameter specified by the string ParamName.

C.2.4 Query Functions

- ♦ “[idmquery\(\\$ClassName, \\$Association, \\$ReadAttrs\)](#)” on page 114
- ♦ “[idmgetqva\(\\$ParamName\)](#)” on page 114

idmquery(\$ClassName, \$Association, \$ReadAttrs)

Performs a query to the engine with the given ClassName, Association and ReadAttrs.

idmgetqva(\$ParamName)

Retrieves a string value for the query result item, specified by Name, through standard output. If no values exist, Empty is returned. If the value is multi-valued, each value is separated by a newline character.

C.2.5 Heartbeat Functions

- ♦ “[heartbeat_success\(\\$Message\)](#)” on page 114
- ♦ “[heartbeat_error\(\\$Message\)](#)” on page 114
- ♦ “[heartbeat_warning\(\\$Message\)](#)” on page 115

heartbeat_success(\$Message)

Use these functions in the `heartbeat.sh` script to indicate the status of the external application. Heartbeat documents are sent to the engine in following format:

```
<status level="success" type="heartbeat">This is a heartbeat message</status>
```

heartbeat_error(\$Message)

Use these functions in the `heartbeat.sh` script to indicate the status of the external application. Heartbeat documents are sent to the engine in following format:

```
<status level="success" type="heartbeat">This is a heartbeat message</status>
```

heartbeat_warning(\$Message)

Use these functions in the `heartbeat.sh` script to indicate the status of the external application. Heartbeat documents are sent to the engine in following format:

```
<status level="success" type="heartbeat">This is a heartbeat message</status>
```

C.3 Microsoft VBScript (IDMLib.vbs) Reference

The scripts are written using Microsoft VBScript. They are located in the scripts folder below the folder where the driver was installed (`C:\Program Files\Novell\WSDriver` by default).

Subscriber events are submitted to `Subscriber.wsf`, which then calls the script for the event. Modify the VBS file corresponding to the event type: `Add.vbs`, `Modify.vbs`, `ModifyPassword.vbs`, `Delete.vbs`, `Move.vbs`, `Rename.vbs`. Queries of the external system should be handled in `Query.vbs`.

The Publisher calls `Poll.wsf` periodically. The frequency of the poll is determined by the Polling Interval driver parameter (60 seconds by default). Edit `Poll.wsf` to allow the driver to respond to events in the external account management system.

The Publisher calls `Heartbeat.wsf` periodically to determine whether the external account management system is responding correctly.

Topics discussing the built-in functions in `IDMLib.vbs` are categorized as follows:

- ♦ [Section C.3.1, “General Functions,” on page 115](#)
- ♦ [Section C.3.2, “Subscriber Functions,” on page 116](#)
- ♦ [Section C.3.3, “Publisher Functions,” on page 117](#)
- ♦ [Section C.3.4, “Query Functions,” on page 118](#)
- ♦ [Section C.3.5, “Heartbeat Functions,” on page 120](#)

C.3.1 General Functions

- ♦ [“Function IDMGGetDriverParam\(ParamName\)” on page 115](#)
- ♦ [“Sub IDMTrace Message” on page 116](#)
- ♦ [“Function IDMEExecute\(Command\)” on page 116](#)
- ♦ [“Function IDMEExecuteIO\(Command, Input\)” on page 116](#)
- ♦ [“Sub IDMStatus\(Level, Message\)” on page 116](#)
- ♦ [“Sub IDMStatusSuccess\(Message\)” on page 116](#)
- ♦ [“Sub IDMStatusWarning\(Message\)” on page 116](#)
- ♦ [“Sub IDMStatusRetry\(Message\)” on page 116](#)
- ♦ [“Sub IDMStatusError\(Message\)” on page 116](#)
- ♦ [“Sub IDMStatusFatal\(Message\)” on page 116](#)

Function IDMGGetDriverParam(ParamName)

Returns the string value for the Driver parameter specified by the string `ParamName`.

Sub IDMTrace Message

Appends the specified message to the user-defined trace file.

Function IDMExecute(Command)

Executes an external program using the specified command line, and returns its numerical exit code on completion.

Function IDMExecuteIO(Command, Input)

Executes an external program using the specified command line, submits the strings from array Input on standard input, and returns output from standard output and standard error as an array. You may specify Empty for the Input parameter. The function returns when the program completes. The first element of the returned array is the program exit code. Subsequent elements (if any) are strings, one for each line that was output to standard output and standard error.

Sub IDMStatus(Level, Message)

Set the status level and message to return to the Identity Manager engine when the script completes.

Sub IDMStatusSuccess(Message)

Set the status level and message to return to the Identity Manager engine when the script completes.

Sub IDMStatusWarning(Message)

Set the status level and message to return to the Identity Manager engine when the script completes.

Sub IDMStatusRetry(Message)

Set the status level and message to return to the Identity Manager engine when the script completes.

Sub IDMStatusError(Message)

Set the status level and message to return to the Identity Manager engine when the script completes.

Sub IDMStatusFatal(Message)

Set the status level and message to return to the Identity Manager engine when the script completes.

C.3.2 Subscriber Functions

- ♦ “Function `IDMGetSubscriberParam(ParamName)`” on page 117
- ♦ “Sub `IDMSetCommand(Command)`” on page 117
- ♦ “Function `IDMGetEventValueCount(Name)`” on page 117
- ♦ “Function `IDMGetEventValues(Name)`” on page 117
- ♦ “Function `IDMGetEventValue(Name)`” on page 117
- ♦ “Sub `IDMWriteValue(Name, Value)`” on page 117

- ♦ “Sub IDMWriteValues(Name, Values)” on page 117
- ♦ “Function IDMSubGetNamedPassword(Name)” on page 117

Function IDMGetSubscriberParam(ParamName)

Returns the string value for the Subscriber parameter specified by the string ParamName.

Sub IDMSetCommand(Command)

Sets the command that the Subscriber return to the Identity Manager engine. This function must be called before using IDMWriteValue functions. If only a status needs to be returned, use one of the IDMStatus functions (see above).

Function IDMGetEventValueCount(Name)

Returns the number of values for the item specified by Name. (Items include event information and attribute changes.)

Function IDMGetEventValues(Name)

Returns an array of string values for the item specified by Name. If no values exist, Empty is returned.

Function IDMGetEventValue(Name)

Returns the string value for the item specified by Name. If multiple values exist for the item, it returns the first value. If no values exist, Empty is returned.

Sub IDMWriteValue(Name, Value)

Sets a single string value for the item specified by Name to be returned to the driver engine when the script completes. You must call IDMSetCommand or one of the IDMStatus functions before calling this function.

Sub IDMWriteValues(Name, Values)

Sets an array of string values for the item specified by Name to be returned to the driver engine when the script completes. You must call IDMSetCommand or one of the IDMStatus functions before calling this function.

Function IDMSubGetNamedPassword(Name)

Returns a named password specified by Name from the Identity Manager engine. The value Empty is returned if no such password exists.

C.3.3 Publisher Functions

- ♦ “Function IDMGetPublisherParam(ParamName)” on page 118
- ♦ “Sub IDMPublishInit(Command)” on page 118
- ♦ “Sub IDMPublishValue(Name, Value)” on page 118
- ♦ “Sub IDMPublishValues(Name, Values)” on page 118

- ♦ “Function IDMPublish” on page 118
- ♦ “Function IDMPubGetNamedPassword(Name)” on page 118

Function IDMPublishParam(ParamName)

Returns the string value for the Publisher parameter specified by the string ParamName.

Sub IDMPublishInit(Command)

Sets the Publisher command specified by Command to return to the driver engine when IDMPublish is called.

Sub IDMPublishValue(Name, Value)

Sets a single string value for the item specified by Name to be returned to the driver engine when IDMPublish is called.

Sub IDMPublishValues(Name, Values)

Sets an array of string values for the item specified by Name to be returned to the driver engine when IDMPublish is called.

Function IDMPublish

Submit the command and item values specified above to the driver engine for Publication to the identity vault.

Function IDMPubGetNamedPassword(Name)

Returns a named password specified by Name from the Identity Manager engine. The value Empty is returned if no such password exists.

C.3.4 Query Functions

- ♦ “Sub IDMQQueryInit” on page 119
- ♦ “Sub IDMQQuerySetAssociation(Association)” on page 119
- ♦ “Sub IDMQQuerySetSearchRoot(SearchRoot)” on page 119
- ♦ “Sub IDMQQueryAddSearchAttr(Name, Value)” on page 119
- ♦ “Sub IDMQQueryAddReadAttr(Name)” on page 119
- ♦ “Sub IDMQQuerySetReadParent(ReadParent)” on page 119
- ♦ “Function IDMQQuery” on page 119
- ♦ “Function IDMQGetQueryInstanceAssociation” on page 119
- ♦ “Function IDMQGetQueryInstanceDN” on page 119
- ♦ “Function IDMQGetQueryInstanceClass” on page 119
- ♦ “Function IDMQGetQueryInstanceParentAssociation” on page 120
- ♦ “Function IDMQGetQueryInstanceParentDN” on page 120
- ♦ “Function IDMQGetQueryInstanceAttrNames” on page 120

- ♦ “Function `IDMGetQueryInstanceAttrCount`” on page 120
- ♦ “Function `IDMGetQueryInstanceAttrValues(AttrName)`” on page 120
- ♦ “Function `IDMGetQueryInstanceAttrValue(AttrName)`” on page 120

Sub `IDMQueryInit`

Initializes a query to be submitted to the identity vault with the `IDMQuery` call. NOTE: Currently only queries that query a single object are supported.

Sub `IDMQuerySetAssociation(Association)`

Specifies the association of the identity vault object to query.

Sub `IDMQuerySetSearchRoot(SearchRoot)`

Specifies the DN of the identity vault object to query. Either the object’s association or DN must be specified. If both are specified, the association value is used by the Identity Manager engine.

Sub `IDMQueryAddSearchAttr(Name, Value)`

Specifies a search condition to be used for the query, of the form `Name=Value`. `Name` specifies an attribute, and `Value` specifies a value it must match. The query will return only objects matching all specified conditions.

Sub `IDMQueryAddReadAttr(Name)`

Specifies an attribute name whose values should be returned by the query. By default, all attributes are returned.

Sub `IDMQuerySetReadParent(ReadParent)`

Specifies whether the association and DN of the parent of the queried object should be returned (`ReadParent` is boolean). The default is `False`.

Function `IDMQuery`

Executes the query with the parameters specified by `IDMQuerySetXXX` calls. The function returns `True` if an object (called an instance) is returned.

Function `IDMGetQueryInstanceAssociation`

Returns the association for the returned instance.

Function `IDMGetQueryInstanceDN`

Returns the DN for the returned instance. The DN is in slash format, such as `\ACME\Users\Bob`.

Function `IDMGetQueryInstanceClass`

Returns the class name for the returned instance.

Function IDMGGetQueryInstanceParentAssociation

Returns the association for instance's parent object, if the ReadParent flag was specified.

Function IDMGGetQueryInstanceParentDN

Returns the DN for instance's parent object, if the ReadParent flag was specified.

Function IDMGGetQueryInstanceAttrNames

Returns an array containing the names of the attributes retrieved for the instance. Returns Empty if no attributes were retrieved.

Function IDMGGetQueryInstanceAttrCount

Returns the number of attributes retrieved for the instance.

Function IDMGGetQueryInstanceAttrValues(AttrName)

Returns an array of values for the attribute with the specified AttrName. Returns Empty if no values are available.

Function IDMGGetQueryInstanceAttrValue(AttrName)

Returns a string value for the attribute with the specified AttrName. If multiple values are available for the attribute, the first one is returned. If no values are available, Empty is returned.

C.3.5 Heartbeat Functions

- ♦ “Sub IDMHearbeatSuccess(Message)” on page 120
- ♦ “Sub IDMHearbeatError(Message)” on page 120
- ♦ “Sub IDMHearbeatWarning(Message)” on page 120

Sub IDMHearbeatSuccess(Message)

Use these functions in the heartbeat.wsf script to indicate the status of the external application.

Sub IDMHearbeatError(Message)

Use these functions in the heartbeat.wsf script to indicate the status of the external application.

Sub IDMHearbeatWarning(Message)

Use these functions in the heartbeat.wsf script to indicate the status of the external application.

Topics in this section include

- [Section D.1, “Using the usdrv-config Command \(Linux/UNIX only\),” on page 121](#)
- [Section D.2, “Driver Shim Command Line Options,” on page 122](#)
- [Section D.3, “Publisher Change Log Tool,” on page 123](#)
- [Section D.4, “Files and Directories Modified by Installing the Driver Shim,” on page 126](#)

D.1 Using the usdrv-config Command (Linux/UNIX only)

You can use `/usr/sbin/usdrv-config` to change the driver shim configuration. When you run this command, you are prompted for the function to perform.

```
> usdrv-config
Which configuration do you want to perform?
1) Set the Remote Loader and Driver object passwords
2) Configure the driver for Secure Sockets Layer (SSL)
Select one configuration option [q/?]:
```

Enter the number of the function you want to configure, then respond to the prompts.

D.1.1 Setting the Remote Loader and Driver Object Passwords

The `usdrv-config` command prompts you to enter and confirm the Remote Loader password and the Driver object password.

```
Enter Remote Loader password:
Confirm Remote Loader password:
Enter Driver object password:
Confirm Driver object password:
```

The Remote Loader password is used by the Metadirectory engine to authenticate itself to the driver shim (embedded Remote Loader). The Driver object password is used by the driver shim to authenticate itself to the Metadirectory engine.

The Remote Loader and Driver object passwords set by `usdrv-config` are stored on the connected system. The Remote Loader and Driver object passwords set for the driver using iManager are stored in the Identity Vault. Each password on the connected system must exactly match its counterpart in the Identity vault.

To change the passwords after driver installation:

- 1 In iManager, navigate to the Driver Overview for the driver.
- 2 Click the driver icon.
- 3 Specify the Driver object password.
- 4 Specify the Remote Loader password.

The Remote Loader password is below the Authentication heading.

- 5 Click *Apply*.
- 6 Restart the driver.

D.1.2 Configuring the Driver for SSL

The `usdrv-config` command prompts you to enter the LDAP server host address and port, then displays the Certificate Authority for that server and asks you if you accept it.

```
You are about to connect to the eDirectory LDAP server to retrieve
the eDirectory Tree Trusted Root public certificate.
```

```
Enter the LDAP Server Host Address [localhost]: sr.digitalairlines.com
Enter the LDAP Server Port [636]:
```

```
Certificate Authority:
  Subject:      ou=Organizational CA,o=TREENAME
  Not Before:   20070321144845Z
  Not After:    20170321144845Z
Do you accept the Certificate Authority? (Y/N) y
```

Enter the host name or IP address and TCP port number of an LDAP server for your Identity Vault. The LDAP server must be configured for SSL, and it must be listening on the SSL port. The default SSL port is 636.

The driver shim connects to the specified server and displays information about the Certificate Authority. If you accept the Certificate Authority, the driver shim saves it to the local file system.

If you do not have LDAP configured for SSL, you can use a manual process to configure the driver for SSL. For details, see Section A.2.3, "Driver Certificate Setup Failure."

D.2 Driver Shim Command Line Options

The following options can be specified on the driver shim (`usdrv` on Linux and UNIX, `wsdriver` on Windows) command line. You can also specify driver shim command line options as driver shim configuration file statements. For details about the driver shim configuration file, see [Section 4.2](#), "The Driver Shim Configuration File," on page 29.

D.2.1 Options Used to Set Up Driver Shim SSL Certificates

The following command line options are used to set up the driver shim SSL certificates:

Table D-1 Driver Shim Command Line Options for Setting Up SSL Certificates

Option (Short and Long Forms)	Description
-s	Secures the driver by creating SSL certificates, then exits.
-secure	
-p	Specifies the Remote Loader password
-password	

D.2.2 Other Options

Table D-2 Other Driver Shim Command Line Options

Option (Short and Long Forms)	Description
-c <congFile>	Instructs the driver shim to read options from the specified configuration file. Options are read from <code>conf/usdrv.conf</code> (Linux/UNIX) or <code>conf\wsdrv.conf</code> (Windows) by default.
-config <configFile>	
-sp [remoteLoaderPassword driverObjectPassword]	Sets the Remote Loader and driver object passwords to the passwords specified on the command line, then stops the driver shim. If the passwords are omitted, the driver shim prompts for the passwords.
-setpassword [remoteLoaderPassword driverObjectPassword]	
-installService	Creates a Windows service for the driver shim called Novell IDM Windows Script Driver (Windows only).
-removeService	Removes the Windows service Novell IDM Windows Script Driver (Windows only).
-?	Displays the command line options, then exits.
-help	
-v	Displays the driver shim version and build date, then exits.
-version	

D.3 Publisher Change Log Tool

The publisher channel may submit events to be published, using the change log tool `usclh` (on UNIX) or `idmevent.exe` (on Windows). These tools will create an event, which will be picked up by the driver shim on a polling interval and published to the Identity Manager engine, where it may be processed by Policy. The change log tool may be invoked at anytime on the application system. One commonly-used technique is to call the `changelog` tool from the polling script, which is executed on the polling interval as well. In such a scenario, the polling script can determine what changed and submit the changes to the change log to be processed immediately after the polling script terminates. However, if you wish to invoke the change log tool from another mechanism, events will be queued in the changelog and published on intervals when necessary.

The syntax for the change log tool on UNIX, `usclh`, is as follows:

```
usclh -t <type>
    [-c class]
    [-e event-id]
    [-a association]
    [-s src-dn]
    [-o old-src-dn]
    [-p password]
    [-w old-password]
    [-n new-name]
    [-r]
    [-y old-association]
```

```

[-z new-association]
[-l status-level]
[-m status-message]
[-1 | -2]
[-?]

```

Where each option is described in the following table:

Table D-3 *Options*

Name	Description
type	The command type, which may be one of the following: add, delete, modify, modify-password, rename, modify-association, status, xds. When using the xds type, a raw XML document may be passed to the tool to be published as is.
event-id	The event-id of the document to be published. Typically, this is a timestamp or a counter. If none is specified, a default timestamp will be used.
association	The association string value for which the event being published describes.
src-dn	The source distinguished name of the object being published, if this object resides in a hierarchical directory structure.
old-src-dn	If the published event is a move or rename, the old-src-dn specifies the old distinguished name before the move or rename event.
password	The new password of the object being published. This is only valid for add or modify-password events.
old-password	The old password of the object being published. This is only valid for modify-password events.
new-name	The new name of an object being published during a rename event.
-r	If specified, instructs the event to remove the old name during a rename event.
old-association	Specifies the name of the old association value, during a modify-association event.
new-association	Specifies the name of the new association value, during a modify-association event.
status-level	Specifies the status level for a status message. Valid levels are: success, error, warning, retry, fatal.
status-message	Specifies the text messages that should be included for a status document.
-1	Specifies that the event should be put on hold (do not publish), until a release is issued.
-2	Specifies that all events on hold should be released (publishable).
-?	This help menu.

When invoked, the changelog utility waits for input on standard input until an EOF (end of file) character is received. If entered on the command-line, you can terminate it with the Ctl-d meta character. Additional name/value pairs can then be passed to this tool to supply additional event information such as attribute values being added or removed.

When invoked from a script, you can use a “here-is” document format to pass standard input to the changelog tool. When passing input to a command-line utility through standard input, you have the advantage that the information is protected from the environment, adding security to your publisher. When using command-line arguments, these options will appear in cleartext to the outside environment with tools such as “ps”.

Examples from a script:

```
usclh -t add -c User -a bob <<EOF
ADD_CN=bob
ADD_Login Disabled=true
EOF

usclh -t modify -c User -a bob <<EOF
ADD_CN=bob
ADD_Login Disabled=true
EOF

usclh -t modify-password -c User -a bob <<EOF
OLD_PASSWORD=secret
PASSWORD=newsecret
EOF

usclh -t rename -c User -a bob -n bob2 -r <<EOF

EOF
```

Examples from a command line:

```
usclh -t add -c User -a bob
ADD_CN=bob
ADD_Login Disabled=true
^d

usclh -t delete -c User -a bob
^d

usclh -t modify-password -c User -a bob -w secret -p newsecret
^d

usclh -t xds
<modify class-name="User" event-id="12345">
  <association>bob</association>
  <modify-attr attr-name="MyAttr">
    <remove-all-values/>
    <add-value>
      <value>some new value</value>
    </add-value>
  </modify-attr>
</modify>
^d
```

D.4 Files and Directories Modified by Installing the Driver Shim

- ♦ [Section D.4.1, “Driver Shim Directory,” on page 126](#)
- ♦ [Section D.4.2, “/usr/sbin Files \(Linux/UNIX only\),” on page 126](#)
- ♦ [Section D.4.3, “init.d Files \(Linux/UNIX only\),” on page 126](#)
- ♦ [Section D.4.4, “Man Pages \(Linux/UNIX only\),” on page 126](#)
- ♦ [Section D.4.5, “Driver Shim Configuration File,” on page 127](#)
- ♦ [Section D.4.6, “Windows Support Files \(Windows only\),” on page 127](#)

D.4.1 Driver Shim Directory

When you install the driver, the `/opt/novell/usdrv` or `C:\Program Files\Novell\WSDriver` directory is created and populated with driver-related files and subdirectories.

D.4.2 /usr/sbin Files (Linux/UNIX only)

The following commands are added to `/usr/sbin`:

Table D-4 *Driver Commands Placed in /usr/sbin*

Command	Function
<code>usdrv-uninstall</code>	Uninstalls the Scripting driver
<code>usdrv-config</code>	Updates the configuration

D.4.3 init.d Files (Linux/UNIX only)

Commands to start, stop, and display the status of the driver are added to the appropriate file for the connected system operating system.

Table D-5 *Commands for Starting, Stopping, and Displaying the Status of the Driver Shim*

Operating System	Command
AIX	<code>/etc/rc.d/init.d/usdrvd</code>
HP-UX	<code>/sbin/init.d/usdrvd</code>
Linux	<code>/etc/init.d/usdrvd</code>
Solaris	<code>/etc/init.d/usdrvd</code>

D.4.4 Man Pages (Linux/UNIX only)

The installation process adds man pages for the driver shim, change log update command, and shared memory tool to `/usr/man`.

D.4.5 Driver Shim Configuration File

The installation program places a default driver shim configuration file at `/etc/usdrv.conf` on Linux and UNIX. On Windows, this file is `wsdrv.conf` in the `conf` directory in the installation directory.

D.4.6 Windows Support Files (Windows only)

Support files such as DLLs for the Visual C++ runtime are installed on Windows systems in the WinSxS directory (usually `C:\Windows\WinSxS`). If the driver shim is uninstalled, these files are removed.

Documentation Updates



This appendix summarizes changes to this document since the initial release of Identity Manager 3.6.

E.1 November 23, 2009

- Updated the file names in [Section 3.1, “Installing the Linux and UNIX Scripting Driver,”](#) on [page 19](#) and [Section 3.2, “Installing the Windows Scripting Driver,”](#) on [page 20](#).

E.2 October 23, 2007

- Updated information in [Chapter 5, “Customizing the Scripting Driver,”](#) on [page 31](#), including significant changes to code samples and related text in [Section 5.5.2, “Policy and Script Development,”](#) on [page 42](#) and [Section 5.6.2, “Policy and Script Development,”](#) on [page 56](#).
- Replaced entire section in [Appendix D](#), resulting in [Section D.3, “Publisher Change Log Tool,”](#) on [page 123](#).

