


ZENworks Mobile Management 2.8.x

Integrating the ZENworks Mobile Management Dashboard into ZENworks Control Center

Novell®

If you use ZENworks Control Center to manage one or more ZENworks 11 products, you can integrate the ZENworks Mobile Management dashboard into ZENworks Control Center. This allows you, or other administrators, to log in to ZENworks Control Center to manage both ZENworks 11 and ZENworks Mobile Management.



Review the information and complete the tasks in the following sections to integrate the ZENworks Mobile Management dashboard into ZENworks Control Center:

- ◆ [Section 1, "Integration through OpenID,"](#) on page 2
- ◆ [Section 2, "Administrator Support,"](#) on page 2
- ◆ [Section 3, "Requirements,"](#) on page 2
- ◆ [Section 4, "Configuring ZENworks Mobile Management,"](#) on page 2
- ◆ [Section 5, "Configuring ZENworks 11,"](#) on page 7
- ◆ [Section 6, "Accessing the Mobile Management Dashboard in ZENworks Control Center,"](#) on page 8

1 Integration through OpenID

The OpenID standard is used to integrate the ZENworks Mobile Management dashboard into ZENworks Control Center.

The ZENworks 11 Server functions as an OpenID provider. When an administrator logs in to ZENworks Control Center and clicks the Mobile Management link, the ZENworks 11 Server authenticates the administrator to ZENworks Mobile Management and displays the dashboard.

2 Administrator Support

ZENworks Mobile Management provides two levels of administrators: System Administrator and Organization Administrator. A System Administrator can manage the system and all organizations. An Organization Administrator can manage a single organization.

You can support login through ZENworks Control Center for all System Administrators or for the Organization Administrators of one organization. Login for both System Administrators and Organization Administrators is not supported, and login for Organization Administrators from multiple organizations is not supported.

3 Requirements

- ♦ **Version Support:** The minimum versions required for integration are:
 - ♦ ZENworks 11.2.4 - You must download and apply a patch to enable integration in ZENworks 11.2.4. For details, see [Novell TID 7014106 \(http://www.novell.com/support/kb/doc.php?id=7014106\)](http://www.novell.com/support/kb/doc.php?id=7014106).
 - ♦ ZENworks Mobile Management 2.7
- ♦ **Administrator Accounts:** An administrator must have both a ZENworks Control Center account and a ZENworks Mobile Management account. The ZENworks Mobile Management account can be either a System Administrator account or an Organization Administrator account. The two accounts do not need to have the same username and password.

4 Configuring ZENworks Mobile Management

Complete the following configuration tasks in the ZENworks Mobile Management dashboard:

- ♦ [Section 4.1, “Configuring a ZENworks OpenID Provider,” on page 2](#)
- ♦ [Section 4.2, “Enabling OpenID Login for Administrators,” on page 4](#)

4.1 Configuring a ZENworks OpenID Provider

To enable System Administrators to access the ZENworks Mobile Management dashboard through ZENworks Control Center, you configure the ZENworks OpenID provider at the system level.

To enable the Organization Administrators for an organization to access the dashboard through ZENworks Control Center, you configure the ZENworks OpenID provider at the organization level.


The following sections provide instructions:

- ♦ [Section 4.1.1, “Configuring a ZENworks OpenID Provider for the System,” on page 3](#)
- ♦ [Section 4.1.2, “Configuring a ZENworks OpenID Provider for an Organization,” on page 3](#)

4.1.1 Configuring a ZENworks OpenID Provider for the System

In order for ZENworks Mobile Management System Administrators to access the ZENworks Mobile Management dashboard from ZENworks Control Center, you must configure a ZENworks OpenID provider for the system.

- 1 Launch the ZENworks Mobile Management dashboard as a System Administrator with full rights.
- 2 Click *System > System Administration > OpenID Provider*.



- 3 Configure the following settings:

- ◆ **Enabled:** Select the checkbox to enable the provider.
- ◆ **Predefined Providers:** Select *ZENworks*.
- ◆ **OpenID Provider URL:** Specify the ZENworks Primary Server address in the following form:

`https://server:port/zenworks/?requestHandler=ZENOpenIDHandler`

Replace *server:port* with the hostname (or IP address) and port of the ZENworks Primary Server. The port is required only if the server is using a non-standard port.

- ◆ **OpenID Return URL:** Click *Use Default* to populate the field with the address of the current ZENworks Mobile Management server.


- 4 Click *Save Changes*.

4.1.2 Configuring a ZENworks OpenID Provider for an Organization

In order for ZENworks Mobile Management Organization Administrators to access the ZENworks Mobile Management dashboard from ZENworks Control Center, you must configure a ZENworks OpenID provider for the organization.

- 1 Launch the ZENworks Mobile Management dashboard as a System Administrator with full rights.
- 2 Click *Organization > OpenID Providers* (under *Organization Control*).
- 3 Click *Add OpenID Provider*.

4 In the *Predefined Providers* list, select *ZENworks*.



5 Configure the following settings:

- ♦ **Zone:** Specify a name for the ZENworks OpenID provider. This name is used in the ZENworks 11 system to authenticate to this organization via the OpenID provider.
- ♦ **OpenID Provider URL:** Specify the ZENworks Primary Server address in the following form:

`https://server:port/zenworks/?requestHandler=ZENOpenIDHandler`

Replace *server:port* with the hostname/IP address and port of the ZENworks Primary Server. The port is required only if the server is using a non-standard port.

- ♦ **OpenID Return URL:** Click *Use Default* to populate the field with the address of the current ZENworks Mobile Management server.

6 Click *Finish*.

4.2 Enabling OpenID Login for Administrators


You must enable OpenID login for each administrator who plans to access the ZENworks Mobile Management dashboard through ZENworks Control Center.

- ♦ [Section 4.2.1, “Enabling Existing System Administrators,” on page 4](#)
- ♦ [Section 4.2.2, “Creating and Enabling New System Administrators,” on page 5](#)
- ♦ [Section 4.2.3, “Enabling Existing Organization Administrators,” on page 6](#)
- ♦ [Section 4.2.4, “Creating and Enabling New Organization Administrators,” on page 6](#)

4.2.1 Enabling Existing System Administrators

- 1 Launch the ZENworks Mobile Management dashboard as a System Administrator with full rights.
- 2 Click *System > System Administration > System Administrators*.
- 3 In the *System Administrators* list, select the administrator for whom you want to enable OpenID login.

4 Select the *Use OpenID* check box.




5 Click *Save Changes*.

The administrator is sent an e-mail with the OpenID PIN needed the first time he or she logs in to ZENworks Mobile Management through ZENworks Control Center. For information about this login process, see [Section 6, "Accessing the Mobile Management Dashboard in ZENworks Control Center,"](#) on page 8.

4.2.2 Creating and Enabling New System Administrators

- 1 Launch the ZENworks Mobile Management dashboard as a System Administrator with full rights.
- 2 Click *System > System Administration > System Administrators*.
- 3 Click *Add System Administrator*.



4 Click *OpenID*.

- 5 Follow the prompts to define the OpenID details and account settings.

After you click *Finish*, the administrator account is created and the administrator is sent an e-mail with the OpenID PIN needed the first time he or she logs in to ZENworks Mobile Management through ZENworks Control Center. For information about this login process, see [Section 6, “Accessing the Mobile Management Dashboard in ZENworks Control Center,”](#) on page 8.

4.2.3 Enabling Existing Organization Administrators

- 1 Launch the ZENworks Mobile Management dashboard as a System Administrator with full rights.
- 2 Click *System > Organization Administrators*.
- 3 In the *Organization Administrators* list, select the administrator for whom you want to enable OpenID login.
- 4 Select the *Use OpenID* check box.
- 5 In the *OpenID Provider* field, select the ZENworks OpenID provider.

The screenshot shows the 'Organization Administrators' configuration page. At the top, there are two tabs: 'Organization Administrators' (selected) and 'Administrator Groups'. Below the tabs is a table with the following data:

Display Name	Administrator Username	OpenID Identity	Contact E-Mail Address
kburnett		https://www.google.com/accounts/o	kburnett@novell.com
Jon Enos	jenos@zmm.net		jenos@zmm.net
Bob Jones	bjones@zmm.net		bjones@zmm.net

Below the table is a configuration form for the selected administrator, Jon Enos. The form includes the following fields and options:

- Use OpenID:**
- OpenID Identity:** OpenID has not been set yet.
- OpenID Provider:** novell (dropdown)
- Display Name:** Jon Enos (text input)
- E-mail Address:** jenos@zmm.net (text input)
- Carrier:** None (dropdown)
- Phone Number:** (text input)
- Add to Alert Recipients List:**
- Pin:** (text input) with a 'Reset Pin' button
- Role:** Full Admin (dropdown)
- Default View:** Organization (dropdown)
- System Timeout (minutes):** 20 (spinners)
- Enabled:**
- Created By:** admin@zmm.net
- Date Created:** 04/03/2013 9:37 AM (-06:00 GMT)


- 6 Click *Save Changes*.

The administrator is sent an e-mail with the OpenID PIN needed the first time he or she logs in to ZENworks Mobile Management through ZENworks Control Center. For information about this login process, see [Section 6, “Accessing the Mobile Management Dashboard in ZENworks Control Center,”](#) on page 8.

4.2.4 Creating and Enabling New Organization Administrators

- 1 Launch the ZENworks Mobile Management dashboard as a System Administrator with full rights.
- 2 Click *System > System Administration > System Administrators*.

- 3 Click *Add Administrator*.




- 4 Click *OpenID*.
- 5 Follow the prompts to define the OpenID details and account settings.

After you click *Finish*, the administrator account is created and the administrator is sent an e-mail with the OpenID PIN needed the first time he or she logs in to ZENworks Mobile Management through ZENworks Control Center. For information about this login process, see [Section 6, "Accessing the Mobile Management Dashboard in ZENworks Control Center,"](#) on page 8.

5 Configuring ZENworks 11

- 1 Log in to ZENworks Control Center as an administrator who has rights to modify Management Zone settings.
Super administrators and any administrators with the *Zone Rights - Modify Settings* right can modify zone settings.
- 2 Click *Configuration*.
- 3 In the Management Zone Settings panel, click *Mobile Management > Mobile Management Zone Registration*.




- 4 Enable the *Register ZENworks Mobile Management Server* option, then fill in the following fields:
 - ♦ **Mobile Management Server Hostname or IP Address:** Specify the hostname or IP address of the ZENworks Mobile Management server.
 - ♦ **Mobile Management Zone Name:** Leave this field blank to enable login by ZENworks Mobile Management System Administrators.


To enable login by Organization Administrators, specify the zone name that is assigned to the ZENworks OpenID provider in the administrators' organization.
- 5 Click *OK* to save the settings.

6 Accessing the Mobile Management Dashboard in ZENworks Control Center

- 1 Log in to ZENworks Control Center.
- 2 Click *Mobile Management* to display the Admin Setup Pin Code prompt:



- 3 Enter the OpenID PIN you were e-mailed, then click *OK* to authenticate to ZENworks Mobile Management and display the dashboard.



Your ZENworks Control Center administrator account is now linked to your ZENworks Mobile Management administrator account. Whenever you are in ZENworks Control Center and click *Mobile Management*, you will be automatically authenticated to the ZENworks Mobile Management dashboard.