## **Utilities Reference**

**GroupWise 2014** 

April 2014



#### **Legal Notices**

Novell, Inc. makes no representations or warranties with respect to the contents or use of this documentation, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. reserves the right to revise this publication and to make changes to its content, at any time, without obligation to notify any person or entity of such revisions or changes.

Further, Novell, Inc. makes no representations or warranties with respect to any software, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. reserves the right to make changes to any and all parts of Novell software, at any time, without any obligation to notify any person or entity of such changes.

Any products or technical information provided under this Agreement may be subject to U.S. export controls and the trade laws of other countries. You agree to comply with all export control regulations and to obtain any required licenses or classification to export, re-export, or import deliverables. You agree not to export or re-export to entities on the current U.S. export exclusion lists or to any embargoed or terrorist countries as specified in the U.S. export laws. You agree to not use deliverables for prohibited nuclear, missile, or chemical biological weaponry end uses. See the Novell International Trade Services web page (http://www.novell.com/company/legal/exports/) for more information on exporting Novell software. Novell assumes no responsibility for your failure to obtain any necessary export approvals.

Copyright © 2003-2014 Novell, Inc. All rights reserved. No part of this publication may be reproduced, photocopied, stored on a retrieval system, or transmitted without the express written consent of the publisher.

Novell, Inc. 1800 South Novell Place Provo, UT 84606 U.S.A. www.novell.com

Online Documentation: To access the online documentation for this and other Novell products, and to get updates, see the Novell Documentation website (http://www.novell.com/documentation/).

#### **Novell Trademarks**

For Novell trademarks, see the Novell Trademark and Service Mark list (http://www.novell.com/company/legal/trademarks/).

#### **Third-Party Materials**

All third-party trademarks are the property of their respective owners.

## **Contents**

	About This Guide	
1	GroupWise Administration Utility	7
	gwadminutil	8
2	GroupWise Administration Utility — Database Options	11
	gwadminutil-convert	12
	gwadminutil-merge	14
	gwadminutil-rebuild	16
	gwadminutil-reclaim	
	gwadminutil-recover	
	gwadminutil-reindex	
	gwadminutil-release	
	gwadminutil-sync	
	gwadminutil-validategwadminutil-validate	
	gwadiiiiidiii vaiidato	
3	GroupWise Administration Utility — Security Options	33
	gwadminutil-ca	34
	gwadminutil-certinst	
	gwadminutil-installcfg	
	gwadminutil-setadmin	4′
4	GroupWise Administration Utility —Other Options	43
	gwadminutil-config	44
	gwadminutil-dbinfo	46
	gwadminutil-services	48
5	GroupWise Service Control Utility	53
	gwsc	54
6	GroupWise Database Utilities	57
Ü	gwcheck	
	gwcheckt	
	dbcopy	
	gwtmstmp	
7	Linux GroupWise Agent Commands	71
	grpwiseg	7'
	grpwise-magrpwise-ma	
	awnoa	77

gwmta	 	 	 		 	 																	79
gwia	 		 																				81
gwdva	 		 																				84
awmon	 	 	 		 																		86

## **About This Guide**

This Novell *GroupWise 2014 Utilities Reference* presents the content of the GroupWise Linux man pages in guide format as a reference.

- "GroupWise Administration Utility" on page 7
  - gwadminutil(1)
- "GroupWise Administration Utility Database Options" on page 11
  - gwadminutil-convert(1)
  - gwadminutil-merge(1)
  - gwadminutil-rebuild(1)
  - gwadminutil-reclaim(1)
  - gwadminutil-recover(1)
  - gwadminutil-reindex(1)
  - gwadminutil-release(1)
  - gwadminutil-sync(1)
  - gwadminutil-upgrade(1)
  - gwadminutil-validate(1)
- "GroupWise Administration Utility Security Options" on page 33
  - gwadminutil-ca(1)
  - gwadminutil-certinst(1)
  - gwadminutil-installcfg(1)
  - gwadminutil-setadmin(1)
- "GroupWise Administration Utility —Other Options" on page 43
  - gwadminutil-config(1)
  - gwadminutil-dbinfo(1)
  - gwadminutil-services(1)
- "GroupWise Service Control Utility" on page 53
  - gwsc(1)
- "GroupWise Database Utilities" on page 57
  - gwcheck(1)
  - gwcheckt(1)
  - dbcopy(1)
  - gwtmstmp(1) (page 67)
- "Linux GroupWise Agent Commands" on page 71
  - grpwise(1)
  - grpwise-ma(1)
  - gwpoa(1)

- gwmta(1)
- gwia(1)
- gwdva(1)
- gwmon(1)

#### **Audience**

This guide is intended for network administrators who install and administer GroupWise.

#### **Feedback**

We want to hear your comments and suggestions about this manual and the other documentation included with this product. Please use the User Comment feature at the bottom of each page of the online documentation.

#### **Additional Documentation**

For additional GroupWise documentation, see the Novell GroupWise 2014 Documentation website (http://www.novell.com/documentation/groupwise2014/).

## **1** GroupWise Administration Utility

• "gwadminutil(1)" on page 8

## gwadminutil(1)

#### Name

gwadminutil - GroupWise Administration Utility

## **Syntax**

gwadminutil option [arguments]

### **Description**

The GroupWise Administration Utility (GWAdminUtil) includes the following capabilities:

- Command-line alternatives to the domain and post office database maintenance tasks available in the GroupWise Admin console.
- Domain database maintenance tasks that are not available in the Admin console because they require simultaneous direct file access to two domain databases.
- Security tasks for managing passwords and certificates.
- Installation of agents on GroupWise servers where no domain or post office is located.
- Management of agents similar to the grpwise script.

## **Options**

## Database Usage Options That Are Also Available in the Admin Console:

#### validate

Checks a database to determine if there are any physical problems with the database.

See gwadminutil-validate(1) for detailed syntax and examples.

#### recover

Corrects physical problems in a domain or post office database, but does not update incorrect information. After you perform a Recover Database operation, you can update information by synchronizing the database.

See gwadminutil-recover(1) for detailed syntax and examples.

#### rebuild

Corrects physical problems in a domain or post office database, and updates incorrect information. It is useful to rebuild a database when you have many user deletions or when GroupWise information has been lost.

See gwadminutil-rebuild(1) for detailed syntax and examples.

#### reclaim

Reclaims unused database space. As you add information to a GroupWise system, the databases increase in size. If you delete information, the space that was created in the databases for the deleted information is not immediately released. When you reclaim the disk space, it can reduce the size of the database.

See gwadminutil-reclaim(1) for detailed syntax and examples.

#### reindex

Rebuilds the listing indexes in the database that are used for sorting users in the Admin console. See <a href="mailto:gwadminutil-reindex">gwadminutil-reindex</a>(1) for detailed syntax and examples.

### Database Usage Options That Are Not Available in the Admin Console:

#### sync

Updates the primary domain database from a secondary domain database.

This process usually takes place automatically. However, if the link between the two domains has been down, you might want to run the synchronization manually. Any records owned by the secondary domain, such as post offices or users, are replicated from the secondary domain database to the primary domain database.

See gwadminutil-sync(1) for detailed syntax and examples.

#### convert

Promotes a secondary domain to a primary domain in your GroupWise system. When you do this, the current primary domain is demoted to a secondary domain. The MTA and POA must be running to perform this conversion.

See gwadminutil-convert(1) for detailed syntax and examples.

#### release

Removes a secondary domain from the current GroupWise system and creates a new GroupWise system. The released domain becomes the new primary domain in its own single-domain GroupWise system.

See gwadminutil-release(1) for detailed syntax and examples.

#### merge

Merges an external domain into the local GroupWise system as a new secondary domain. The external domain must be the only domain in the other GroupWise system.

See gwadminutil-merge(1) for detailed syntax and examples.

#### upgrade

Upgrades the version of a domain or post office database.

See gwadminutil-upgrade(1) for detailed syntax and examples.

## Security Usage Options

#### setadmin

Changes the user name and password for the GroupWise Super Admin.

See gwadminutil-setadmin(1) for detailed syntax and examples.

#### installcfg

Sets the authentication mode for the GroupWise Installation console.

See gwadminutil-installcfg(1) for detailed syntax and examples.

ca

Interacts with the GroupWise Admin Service certificate authority (CA) to generate, issue, list, and revoke certificates for use with GroupWise domains, post offices, and agents.

See gwadminutil-ca(1) for detailed syntax and examples.

#### certinst

Contacts the primary domain Admin Service certificate authority (CA) and installs a new certificate for the Admin Service on the local domain or post office server.

See gwadminutil-certinst(1) for detailed syntax and examples.

### **Other Usage Options**

#### services

Manages the GroupWise agent services. (Some functionality overlaps with the grpwise script.) See gwadminutil-services(1) for detailed syntax and examples.

#### config

Provides configuration alternatives for the following aspects of the GroupWise Admin Service:

- Support in the GroupWise Admin console for clustering of the GroupWise agents
- Default port for the GroupWise Admin console

See gwadminutil-config(1) for detailed syntax and examples.

#### dbinfo

Displays information about a GroupWise domain or post office database.

See gwadminutil-dbinfo(1) for detailed syntax and examples.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

/opt/novell/groupwise/admin/gwadminutil

Script file that runs GWAdminUtil.

#### Authors

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

#### See Also

gwadminutil-ca(1), gwadminutil-certinst(1), gwadminutil-convert(1), gwadminutil-dbinfo(1), gwadminutil-installcfg(1), gwadminutil-merge(1), gwadminutil-rebuild(1), gwadminutil-reclaim(1), gwadminutil-recover(1), gwadminutil-reindex(1), gwadminutil-release(1), gwadminutil-services(1), gwadminutil-setadmin(1), gwadminutil-sync(1), gwadminutil-upgrade(1), gwadminutil-validate(1)

# 2 GroupWise Administration Utility — Database Options

- "gwadminutil-convert(1)" on page 12
- "gwadminutil-merge(1)" on page 14
- "gwadminutil-rebuild(1)" on page 16
- "gwadminutil-reclaim(1)" on page 18
- "gwadminutil-recover(1)" on page 20
- "gwadminutil-reindex(1)" on page 22
- "gwadminutil-release(1)" on page 24
- "gwadminutil-sync(1)" on page 26
- "gwadminutil-upgrade(1)" on page 28
- "gwadminutil-validate(1)" on page 30

## gwadminutil-convert(1)

#### Name

gwadminutil-convert - The GroupWise Administration Utility database convert option.

## **Syntax**

qwadminutil convert -d path -p path

## **Description**

Promotes a secondary domain to a primary domain in your GroupWise system. When you do this, the current primary domain is demoted to a secondary domain. The MTA and POA must be running to perform this conversion.

This task requires direct file access to both databases. For that reason, it is not available in the Admin console, which provides direct file access to one domain database through the Admin Service for that domain.

## **Options**

### **Usage Options:**

-d /path\_to\_secondary\_domain

Specifies the path to the secondary domain that you want to promote to the primary domain.

-p /path to primary domain

Specifies the path to the primary domain that you want to convert into a secondary domain.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

/opt/novell/groupwise/admin/gwadminutil

Script file that runs GWAdminUtil.

## **Examples**

This program normally runs as root.

```
gwadminutil -convert -d /gwsystem/provo2 -p /gwsystem/provo1
```

Promotes the Provo2 secondary domain to be the primary domain and converts the original Provo1 primary domain into a secondary domain.

## **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

## See Also

gwadminutil(1), gwadminutil-convert(1), gwadminutil-merge(1), gwadminutil-rebuild(1), gwadminutil-reclaim(1), gwadminutil-recover(1), gwadminutil-reindex(1), gwadminutil-release(1), gwadminutil-sync(1), gwadminutil-upgrade(1), gwadminutil-validate(1)

## gwadminutil-merge(1)

#### Name

gwadminutil-merge - The GroupWise Administration Utility system merge option

## **Syntax**

```
gwadminutil merge [-mergesync] -d path -p path
```

## **Description**

Merges an external domain into the local GroupWise system as a new secondary domain. The external domain must be the only domain in the other GroupWise system.

This task requires direct file access to both databases. For that reason, it is not available in the Admin console, which provides direct file access to one domain database through the Admin Service for that domain.

After you merge an external domain into your GroupWise system, you must perform the following additional steps in order to complete the setup of the new secondary domain and its post offices:

1 On the secondary domain server, install a new server certificate so that the local Admin Service can communicate with the primary domain Admin Service:

**2** Wait for replication of the domain information to the post office.

On each post office server, you can use the following command to view the owning domain name in the post office database:

```
gwadminutil dbinfo /path_to_post_office
```

**3** On each post office server, install a new server certificate so that the local Admin Service can communicate with the primary domain Admin Service:

## **Options**

## **Usage Options:**

```
-d, --domain /path_to_external_domain
```

Specifies the path to the external domain that you want to merge into the local GroupWise system.

#### -mergesync

Merges external system synchronization information from the external domain into the local GroupWise system.

```
-p, --primary /path_to_primary_domain
```

Specifies the path to the primary domain of your local GroupWise system.

### **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

/opt/novell/groupwise/admin/gwadminutil

Script file that runs GWAdminUtil.

## **Examples**

#### gwadminutil merge -p /gwsystem/provo1 -d /gwmail/orem4

Merges the Orem4 external domain into the local GroupWise system where Provo1 is the primary domain.

#### gwadminutil merge -mergesync -p /gwsystem/provo1 -d /gwmail/orem4

Merges the Orem4 external domain into the local GroupWise system were Provo1 is the primary domain, and establishes external system synchronization between the local GroupWise system and any other external systems that were syncing with the Orem4 domain.

## **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

### See Also

gwadminutil(1), gwadminutil-convert(1), gwadminutil-merge(1), gwadminutil-rebuild(1), gwadminutil-reclaim(1), gwadminutil-recover(1), gwadminutil-reindex(1), gwadminutil-release(1), gwadminutil-sync(1), gwadminutil-upgrade(1), gwadminutil-validate(1)

## gwadminutil-rebuild(1)

#### Name

gwadminutil-rebuild - The GroupWise Administration Utility database rebuild option

## **Syntax**

gwadminutil rebuild -d path -n name -o path [-cd]

## **Description**

Corrects physical problems in a domain or post office database, and updates incorrect information. It is useful to rebuild a database when you have many user deletions or when GroupWise information has been lost.

When you rebuild a domain database, you must be connected to the primary domain in order to rebuild the secondary domain. Rebuilding the primary domain database is not recommended, but can be necessary in a single-domain system.

When you rebuild a post office database, you must be connected to the domain that owns the post office.

This task requires exclusive access to the owning domain database. Stop the agents and the Admin Service for the domain before rebuilding the database.

## **Options**

## **Usage Options:**

#### -cd, --create-directory

Creates a new domain or post office folder structure, along with the rebuilt database and the accompanying dictionary (.dc) files.

#### -d, --domain /path to domain database

Specifies the path to the domain database from which the domain or post office database will be rebuilt.

#### -n, --name object

Specifies the name of the domain or post office that is being rebuilt. For a post office, use the <code>domain.post\_office</code> format.

#### -o /path\_to\_output\_folder

Specifies the location for the rebuilt database. After the database has been rebuilt, copy it into the original domain or post office folder.

## **Help Options:**

#### --help, -?

Displays the help information and exits.

#### **Files**

/opt/novell/groupwise/admin/gwadminutil

Script file that runs GWAdminUtil.

## **Examples**

This program normally runs as root.

```
gwadminutil rebuild -d /gwsystem/provo1 -n provo2 -o /tmp
```

Rebuilds the Provo2 secondary domain database, based on the Provo1 primary domain database in the /gwsystem/provo1 folder, and places the rebuilt secondary domain database in the /tmp folder.

```
gwadminutil rebuild -d /gwsystem/provol -n provol -o /tmp
```

Rebuilds the Provo1 primary domain database, and places the rebuilt primary domain database in the /tmp folder. Rebuilding the primary domain database is not recommended. If the primary domain database is sufficiently damaged, the rebuilt version not viable. Regular backups of the primary domain database in a single-domain system are critical.

```
gwadminutil rebuild -d /gwsystem/provo2 -n provo2.sales -o /tmp
```

Rebuilds the Sales post office that belongs to the Provo2 domain, and places the rebuilt post office database in the /tmp folder.

```
gwadminutil rebuild -d /gwsystem/provo1 -n provo2 -o /tmp -cd
```

Rebuilds the Provo2 domain, places the rebuilt domain database in the /tmp folder, and provides all the supporting folder structure and files to create a new domain directory.

```
gwadminutil rebuild -d /gwsystem/provo2 -n provo2.sales -o /tmp -cd
```

Rebuilds the Sales post office that belongs to the Provo2 domain, places the rebuilt post office database in the / tmp folder, and provides all the supporting folder structure and files to create a new post office directory. This process does not rebuild user databases (userxxx.db) and message databases (msgnnn.db).

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

#### See Also

gwadminutil(1), gwadminutil-convert(1), gwadminutil-merge(1), gwadminutil-rebuild(1), gwadminutil-reclaim(1), gwadminutil-recover(1), gwadminutil-reindex(1), gwadminutil-release(1), gwadminutil-sync(1), gwadminutil-upgrade(1), gwadminutil-validate(1)

## gwadminutil-reclaim(1)

#### Name

gwadminutil-reclaim - The GroupWise Administration Utility database reclaim option

## **Syntax**

gwadminutil reclaim path

## **Description**

Reclaims unused database space. As you add information to a GroupWise system, the databases increase in size. If you delete information, the space that was created in the databases for the deleted information is not immediately released. When you reclaim the disk space, it can reduce the size of the database.

## **Options**

## **Usage Options:**

/path to database

Removes unused space from the database at the specified location.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

/opt/novell/groupwise/admin/gwadminutil Script file that runs GWAdminUtil.

## **Examples**

This program normally runs as root.

```
gwadminutil reclaim /gwsystem/provo1
```

Removes unused space from the domain database for the Provo1 domain.

```
gwadminutil reclaim /gwsystem/engineering
```

Removes unused space from the post office database for the Engineering post office.

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

## See Also

gwadminutil(1), gwadminutil-convert(1), gwadminutil-merge(1), gwadminutil-rebuild(1), gwadminutil-reclaim(1), gwadminutil-recover(1), gwadminutil-reindex(1), gwadminutil-release(1), gwadminutil-sync(1), gwadminutil-upgrade(1), gwadminutil-validate(1)

## gwadminutil-recover(1)

#### Name

gwadminutil-recover - The GroupWise Administration Utility database recover option

## **Syntax**

gwadminutil recover path

## **Description**

Corrects physical problems in a domain or post office database, but does not update incorrect information. After you perform a Recover Database operation, you can update information by synchronizing the database.

### **Options**

### **Usage Options:**

/path\_to\_database

Specifies the path to the database to recover.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

/opt/novell/groupwise/admin/gwadminutil Script file that runs GWAdminUtil.

## **Examples**

This program normally runs as root.

#### gwadminutil recover /gwsystem/provo1

Recovers the domain database for the Provo1 domain.

#### gwadminutil recover /gwsystem/engineering

Recovers the post office database for the Engineering domain.

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

## See Also

gwadminutil(1), gwadminutil-convert(1), gwadminutil-merge(1), gwadminutil-rebuild(1), gwadminutil-reclaim(1), gwadminutil-recover(1), gwadminutil-reindex(1), gwadminutil-release(1), gwadminutil-sync(1), gwadminutil-upgrade(1), gwadminutil-validate(1)

## gwadminutil-reindex(1)

#### Name

gwadminutil-reindex - The GroupWise Administration Utility database reindex option

## **Syntax**

gwadminutil reindex path

## **Description**

Rebuilds the listing indexes in the database that are used for sorting users in the Admin console.

There is a listing index for all users in your GroupWise system, for all users in each domain, and for all users in each post office. If you see differences in user listings when you are connected to different domains in the Admin console, you should rebuild the listing indexes. When you rebuild the listing indexes, the current system index is used.

### **Options**

### **Usage Options:**

```
/path_to_database
```

Specifies the path to the database to reindex.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

```
/opt/novell/groupwise/admin/gwadminutil
Script file that runs GWAdminUtil.
```

## **Examples**

This program normally runs as root.

```
gwadminutil reindex /gwsystem/provo1
```

Rebuilds the listing index for the Provo1 domain.

```
gwadminutil reindex /gwsystem/engineering
```

Rebuilds the listing index for the Engineering post office.

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

## See Also

gwadminutil(1), gwadminutil-convert(1), gwadminutil-merge(1), gwadminutil-rebuild(1), gwadminutil-reclaim(1), gwadminutil-recover(1), gwadminutil-reindex(1), gwadminutil-release(1), gwadminutil-sync(1), gwadminutil-upgrade(1), gwadminutil-validate(1)

## gwadminutil-release(1)

#### Name

gwadminutil-release - The GroupWise Administration Utility database release option

## **Syntax**

```
gwadminutil release -d path -p path -n name
```

## **Description**

Removes a secondary domain from the current GroupWise system and creates a new GroupWise system. The released domain becomes the new primary domain in its own single-domain GroupWise system.

After you release a domain, you must perform the following additional steps in order to complete the setup of the new GroupWise system:

1 On the server where you performed the release, set up the GroupWise Super Admin user for the new GroupWise system:

```
gwadminutil setadmin /path_to_primary_domain_database -a admin_user_name -p
```

**2** On the new primary domain server, set up the GroupWise certificate authority for the new GroupWise system:

```
gwadminutil ca -d /path_to_primary_domain_database -g
```

**3** Wait for replication of the new GroupWise system information from the primary domain to the post office.

On each post office server, you can use the following command to view the system name in the post office database:

```
gwadminutil dbinfo /path to post office
```

**4** On each post office server, install a new server certificate so that the local Admin Service can communicate with the primary domain Admin Service:

## **Options**

## **Usage Options:**

```
-d, --domain /path_to_domain_to_release
```

Specifies the path to the secondary domain that you want to release from one GroupWise system so that it can be merged into another GroupWise system.

```
-n, --name name of new system
```

Specifies the name of the new GroupWise system that is created when the domain is released.

#### -p,--primary /path\_to\_new\_primary\_domain

Specifies the path to the new primary domain that is created when you release the secondary domain from the original GroupWise system.

### **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

```
/opt/novell/groupwise/admin/gwadminutil
Script file that runs GWAdminUtil.
```

### **Examples**

This program normally runs as root.

```
gwadminutil release -p /gwsystem/provo1 -d /gwmail/provo4 -n orem1
```

Releases the Provo4 domain from its GroupWise system and creates a new, single-domain GroupWise system named Orem1.

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

#### See Also

gwadminutil(1), gwadminutil-convert(1), gwadminutil-merge(1), gwadminutil-rebuild(1), gwadminutil-reclaim(1), gwadminutil-recover(1), gwadminutil-reindex(1), gwadminutil-release(1), gwadminutil-sync(1), gwadminutil-upgrade(1), gwadminutil-validate(1)

## gwadminutil-sync(1)

#### Name

gwadminutil-sync - The GroupWise Administration Utility database synchronization option

## **Syntax**

gwadminutil sync -d path -p path

## **Description**

Updates the primary domain database from a secondary domain database.

## **Options**

## **Usage Options:**

-d, --domain /path\_to\_secondary\_domain\_database

Specifies the path to the secondary domain database from which you want to synchronize records up to the primary domain.

-p,--primary /path\_to\_primary\_domain\_database

Specifies the path to the primary domain database that needs to be updated with information from the secondary domain.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

/opt/novell/groupwise/admin/gwadminutil

Script file that runs GWAdminUtil.

## **Examples**

This program normally runs as root.

```
gwadminutil sync -p /gwsystem/provo1 -d /gwsystem/provo2
```

Updates the Provo1 primary domain database with records from the Provo2 secondary domain database.

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

## See Also

gwadminutil(1), gwadminutil-convert(1), gwadminutil-merge(1), gwadminutil-rebuild(1), gwadminutil-reclaim(1), gwadminutil-recover(1), gwadminutil-reindex(1), gwadminutil-release(1), gwadminutil-sync(1), gwadminutil-upgrade(1), gwadminutil-validate(1)

## gwadminutil-upgrade(1)

#### Name

gwadminutil-upgrade - The GroupWise Administration Utility database upgrade option.

## **Syntax**

gwadminutil upgrade path

## **Description**

Upgrades the version of a domain or post office database.

The upgrade process copies the data dictionary (.dc) files that match the version of GWAdminUtil into the domain or post office directory, performs a Recover on the database, and then completes the upgrade of the database. In order for the version upgrade to succeed, the following conditions must be met:

- The owning domain must already be upgraded to the GWAdminUtil version.
- The version information from the owning domain must already be replicated into the target database.

This command is the equivalent of using the Installation console to upgrade a domain or post office.

## **Options**

## **Usage Options:**

/path to database

Specifies the path of the database to upgrade to the current GroupWise version.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

/opt/novell/groupwise/admin/gwadminutil

Script file that runs GWAdminUtil.

## **Examples**

This program normally runs as root.

```
gwadminutil upgrade /gwsystem/provo2
```

Upgrades the Provo2 domain to the same GroupWise version that the primary domain, Provo1, has been upgraded to.

## **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

## See Also

gwadminutil(1), gwadminutil-convert(1), gwadminutil-merge(1), gwadminutil-rebuild(1), gwadminutil-reclaim(1), gwadminutil-recover(1), gwadminutil-reindex(1), gwadminutil-release(1), gwadminutil-sync(1), gwadminutil-upgrade(1), gwadminutil-validate(1)

## gwadminutil-validate(1)

#### Name

gwadminutil-validate - The GroupWise Administration Utility database validate option

## **Syntax**

gwadminutil validate path

## **Description**

Checks a database to determine if there are any physical problems with the database.

If there are any physical problems, you can rebuild or recover the database to correct them. You should validate the data in databases on a regular basis. This process takes just a few minutes and does not interrupt normal operation. The frequency can vary depending on the size of your system and the number of changes you make to users, resources, and groups.

## **Options**

### **Usage Options:**

/path\_to\_database

Specifies the path to the domain database to validate.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

/opt/novell/groupwise/admin/gwadminutil Script file that runs GWAdminUtil.

## **Examples**

This program normally runs as root.

```
gwadminutil validate /gwsystem/provo1
```

Validates the Provo1 domain database.

gwadminutil validate /gwsystem/engineering

Validates the Engineering post office database.

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

## See Also

gwadminutil(1), gwadminutil-convert(1), gwadminutil-merge(1), gwadminutil-rebuild(1), gwadminutil-reclaim(1), gwadminutil-recover(1), gwadminutil-reindex(1), gwadminutil-release(1), gwadminutil-sync(1), gwadminutil-upgrade(1), gwadminutil-validate(1)

# 3 GroupWise Administration Utility — Security Options

- "gwadminutil-ca(1)" on page 34
- "gwadminutil-certinst(1)" on page 37
- "gwadminutil-installcfg(1)" on page 39
- "gwadminutil-setadmin(1)" on page 41

## gwadminutil-ca(1)

#### Name

gwadminutil-ca - The GroupWise Administration Utility certificate authority (CA) option

## **Syntax**

## **Description**

Interacts with the GroupWise Admin Service certificate authority (CA) to generate, issue, list, and revoke certificates for use with GroupWise domains, post offices, and agents.

The GroupWise Admin Service CA issues self-signed server certificates for domain and post office servers. The CA certificate for the primary domain server signs the other server certificates. The CA can regenerate itself if necessary.

## **Options**

### **Usage Options:**

#### -d, --domain /primary\_domain\_folder

Specifies the path to the primary domain database.

#### -f, --force

By default, if you specify an existing output file name, you are notified that the certificate file already exists. Use this option to overwrite the existing certificate file.

#### -g, --generate

Generates a certificate and private key for the primary domain.

#### -i, --issue /path\_to\_database

Creates a new certificate for the Admin Service that is running for the domain or post office associated with the specified database.

#### -1, --list

Lists the certificates issued by the GroupWise CA. The list includes the serial number for each certificate.

#### -n, --name poa name

Specifies the object name of the POA when multiple POAs run for a single post office.

#### -p, --print serial number

Displays the information about the certificate that has the specified serial number.

#### -r,--revoke serial\_number

Revokes the certificate with the specified serial number.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

/opt/novell/groupwise/admin/gwadminutil

Script file that runs GWAdminUtil.

/opt/novell/groupwise/certificates/system guid/ca.\*

Files created when a certificate is issued.

ca.crt

CA certificate file.

ca.key

CA private key file.

ca.srl

Certificate serial number list.

ca.crl

Certificate revocation list.

/opt/novell/groupwise/certificates/system guid/issued

Folder for storing copies of all issued certificates.

/opt/novell/groupwise/certificates/system guid/revoked

Folder for storing copies of all revoked certificates. The folder is not created until a certificate is revoked.

## **Examples**

This program normally runs as root.

```
gwadminutil ca -g -d /gwsystem/provo1 -f
```

Generates a new CA certificate and private key for the primary domain. Overwrites the existing CA certificate.

```
gwadminutil ca -i /gwsystem/provo2
```

Generates a new server certificate for a secondary domain server.

```
gwadminutil ca -i /gwsystem/sales
```

Generates a new server certificate for a post office server.

```
gwadminutil ca -1
```

Lists all of the certificates that the GroupWise CA has issued, along with their serial numbers.

```
gwadminutil ca -p 5266AC7B000A
```

Displays detailed information about the certificate whose serial number you have specified.

#### gwadminutil ca -r 5266AC7B000A

Revokes the specified certificate.

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

## **See Also**

gwadminutil(1), gwadminutil-certinst(1), gwadminutil-dbinfo(1), gwadminutil-installcfg(1), gwadminutil-setadmin(1)

# gwadminutil-certinst(1)

#### Name

gwadminutil-certinst - The GroupWise Administration Utility certificate installation option

## **Syntax**

gwadminutil certinst -db path -ca address -a name -p [password] [-n name]

## **Description**

Contacts the primary domain Admin Service certificate authority (CA) and installs a new certificate for the Admin Service on the local domain or post office server.

In order to contact the primary domain Admin Service certificate authority, you must provide the path to the primary domain database, the GroupWise Super Admin user name and password, and the IP address and port number of the Admin Service.

## **Options**

## **Usage Options:**

#### -a, --admin name

Specifies the user name of the GroupWise Super Admin.

#### -ca ip\_address:port

Specifies the IP address and port number of the Admin Service certificate authority (CA) on the primary domain server.

#### -db, --database /path to database

Specifies the path to the domain or post office database for which the local Admin Service is running.

#### -n, --name poa\_name

Specifies the object name of the POA when multiple POAs run for a single post office.

#### -p, --password [password]

Provides the password for the GroupWise Super Admin. Do not specify the password on the command line if you want to be prompted for it.

## **Help Options:**

#### --help, -?

Displays the help information and exits.

#### **Files**

#### /opt/novell/groupwise/admin/gwadminutil

Script file that runs GWAdminUtil.

```
/opt/novell/groupwise/certificates/system guid/admin.*.*
```

Certificate and key files created for domain servers and post office servers.

```
admin.domain.crt
```

Server certificate file for a domain/MTA.

admin.domain.key

Private key file for a domain server certificate.

```
admin.domain.post office.crt
```

Server certificate file for a post office/POA.

admin.domain.post office.key

Private key file for a post office server certificate.

## **Examples**

This program normally runs as root.

```
gwadminutil certinst -db /gwsystem/provol -ca 172.16.5.18:9710 -a admin -p
```

Contacts the Admin Service CA on the primary domain server and installs a new certificate on the local server.

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

## See Also

gwadminutil(1), gwadminutil-certinst(1), gwadminutil-dbinfo(1), gwadminutil-installcfg(1), gwadminutil-setadmin(1)

# gwadminutil-installcfg(1)

#### Name

gwadminutil-installcfg - The GroupWise Administration Utility installation configuration option.

## **Syntax**

```
gwadminutil installcfg -mode user -u user_name -p [password]
gwadminutil installcfg -mode disable | token
```

## **Description**

Sets the authentication mode for the GroupWise Installation console.

By default, the GroupWise Installation Wizard passes a token to the Installation console to allow access. The token is valid for one hour. If the installation process is interrupted and more than an hour passes, your session in the Installation console is terminated. You can start a new session by reusing the Configure option in the Installation Wizard to generate a new token.

As an alternative, you can configure the GroupWise server so that a user name and password can be used to access the Installation console, instead of the token generated by the Installation Wizard. You can also prevent further installations on the GroupWise server until you establish a different authentication mode.

## **Options**

## **Usage Options:**

```
-m, --mode token user disabled
```

Specifies the authentication mode that is required to access the Installation console on the server.

```
-p, --password [password]
```

When the authentication mode is set to user, specifies the password that must be given in order to access the Installation console. Do not specify the password on the command line if you want to be prompted for it.

```
-u, --username user_name
```

When the authentication mode is set to user, specifies the user name that must be given in order to access the Installation console.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

/opt/novell/groupwise/admin/gwadminutil Script file that runs GWAdminUtil.

## **Examples**

This program normally runs as root.

```
gwadminutil installcfg --mode user -u gsmith -p
```

Changes from token authentication to user authentication, and specifies the user name that is required to access the Installation console. Because no password is specified with the -p option, you are prompted to provide the password in order to put the authentication method into affect.

```
gwadminutil installcfg --disabled
```

Prevents future access to the Installation console.

```
gwadminutil installcfg --token
```

Returns to the original authentication method for the Installation console, so that you must use the Configure option in the Installation Wizard in order to access the Installation console.

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

#### See Also

gwadminutil(1), gwadminutil-certinst(1), gwadminutil-dbinfo(1), gwadminutil-installcfg(1), gwadminutil-setadmin(1)

# gwadminutil-setadmin(1)

#### Name

gwadminutil-setadmin-The GroupWise Administration Utility Super Admin user option

## **Syntax**

```
gwadminutil setadmin -d path -p [password] -a user name
```

## **Description**

Changes the user name and password for the GroupWise Super Admin.

## **Options**

## **Usage Options:**

```
-a, --admin user_name
```

Specifies the new user name for the GroupWise Super Admin for your GroupWise system.

```
-d, --domain /path to domain database
```

Specifies the path to the primary domain database.

```
-p, --password [password]
```

Provides the password for the GroupWise Super Admin. Do not specify the password on the command line if you want to be prompted for it.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

```
/opt/novell/groupwise/admin/gwadminutil
```

Script file that runs GWAdminUtil.

## **Examples**

This program normally runs as root.

```
gwadminutil setadmin -d /gwsystem/provol -a supergw -p
```

Specifies the primary domain of the GroupWise system, sets the user name of the GroupWise Super Admin to supergw, and prompts for the password for the new supergw user.

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

## See Also

gwadminutil(1), gwadminutil-certinst(1), gwadminutil-dbinfo(1), gwadminutil-installcfg(1), gwadminutil-setadmin(1)

# 4 GroupWise Administration Utility — Other Options

- "gwadminutil-config(1)" on page 44
- "gwadminutil-dbinfo(1)" on page 46
- "gwadminutil-services(1)" on page 48

# gwadminutil-config(1)

#### Name

gwadminutil-config-The GroupWise Administration Utility configuration option.

## **Syntax**

```
gwadminutil config [-cluster enable] [-defaultport port_number] []
```

## **Description**

Provides configuration alternatives for the following aspects of the GroupWise Admin Service:

- Support in the GroupWise Admin console for clustering of the GroupWise agents
- Default port for the GroupWise Admin console

## **Options**

## **Usage Options:**

#### -cluster enable

Enables the GroupWise Admin Service to run in a clustering environment. You must run this command on each node in the cluster where a domain or post office is located.

This option causes certificate files to be stored under a certificates folder that is a peer to the domain or post office folder (instead of being stored under /opt/novell/groupwise/certificates). It also causes agent log files to be stored under a log folder that is a peer to the domain or post office folder (instead of being stored in /var/log/novell/groupwise). For example, the folder structure for a cluster resource on an NSS volume would be:

```
/media/nss/VOLUME/domain_or_post_office
/media/nss/VOLUME/groupwise/certificates
/media/nss/VOLUME/groupwise/agents/log
```

#### -defaultport admin\_service\_port\_number

Establishes the default port number for the GroupWise Admin console, when the GroupWise Admin Service is installed but is not configured in the Installation console.

Run the command with no options to display the current configuration settings.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

/opt/novell/groupwise/admin/gwadminutil

Script file that runs GWAdminUtil.

## **Examples**

This program normally runs as root.

#### gwadminutil config

Displays the current configuration settings.

#### gwadminutil config -cluster enable

Enables the GroupWise Admin console to manage domains and post offices that are cluster resources located on multiple nodes in a cluster.

```
gwadminutil config -defaultport 9720
```

Establishes the default port number for an unconfigured GroupWise Admin Service that is located on a server where the standard default port of 9710 is already in use.

```
gwadminutil config -cluster []
```

Disables clustering functionality in the Admin console.

```
gwadminutil config -defaultport []
```

Resets the default Admin Service port back to the default of 9710.

### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

## See Also

gwadminutil(1)

# gwadminutil-dbinfo(1)

#### Name

gwadminutil-dbinfo-The GroupWise Administration Utility database information option.

## **Syntax**

gwadminutil dbinfo path [-n name]

## **Description**

Displays information about a GroupWise domain or post office database.

The following information is displayed about the database:

- GroupWise system name and GUID
- Name of the domain or post office
- Database version
- GroupWise Admin Service IP address and port

## **Options**

## **Usage Options:**

```
/path_to_database
```

Specifies the full path to the domain or post office database.

```
-n, --name poa name
```

Specifies the object name of the POA when multiple POAs run for a single post office.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

```
/opt/novell/groupwise/admin/gwadminutil
```

Script file that runs GWAdminUtil.

## **Examples**

This program normally runs as root.

```
gwadminutil dbinfo /gwsystem/provo1
```

Displays database information about the Provo1 domain.

#### /gwadminutil dbinfo /gwsystem/engineering

Displays database information about the Engineering post office.

### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

## See Also

### gwadminutil(1)

# gwadminutil-services(1)

#### Name

gwadminutil-services - The GroupWise Administration Utility agent services option.

## **Syntax**

## Description

Manages the GroupWise agent services. (Some functionality overlaps with the grpwise script.)

- Installs the DVA service on a server where no post office is located.
- Installs the POA service on a server where no post office is located.
- Lists agent service information as it appears in the gwha.conf file.
- Starts and stops the agent services, and lists agent status, similar to the functionality of the grpwise script.
- Starts the agents with a user interface on the server console. An agent that runs with a user interface cannot be managed in the GroupWise Admin console because it is not running as a service.

## **Options**

## **Usage Options:**

```
-dva [object_name] [/path_to_startup_file]
```

Installs the DVA service on a server where no post office is located. Use with the <code>-i</code> option. If there are multiple DVAs for the post office, specify the DVA object name. If the DVA startup file is not local with the running DVA, such as in a clustering environment where the DVA fails over with the POA, specify the path to the DVA startup file. Specify a unique startup file name to accommodate multiple DVAs on a single cluster node.

```
-i, --install /path to database
```

Installs the POA service for a post office database. Installs the MTA service for a domain database. Installs the GWIA software for a GWIA database. Add the -dva option to install the DVA service. You must use the GroupWise Installation Wizard to install the GroupWise Server software on the server, and start the Admin Service, before you can install agent services.

```
-1,--list types
```

Lists agent service information as it appears in the gwha.conf file. Optionally, include one or more agent types in a comma-separated list (POA,MTA,GWIA,DVA).

```
-n, --name poa name
```

Specifies the object name of the POA when multiple POAs run for a single post office.

#### -q, --query name

Displays current status information for all agents on the server. Optionally, specify a service name, partial service name, or wildcard pattern. This is similar to grpwise status.

#### -s, --service name

Specifies an agent service name. Use with the -u option to uninstall a service by its name rather than by its database location.

#### -show

Starts an agent with a user interface. Use with the -start option. An agent that runs with a user interface cannot be managed in the GroupWise Admin console because it is not running as a service.

#### -start agent name

Starts the specified agent service. You can specify a full agent name, a partial agent name, or a wildcard pattern. This is similar to grwpise start *object*, but is more flexible.

#### -stop agent name

Starts the specified agent service. You can specify a full agent name, a partial agent name, or a wildcard pattern. This is similar to grwpise start *object*, but is more flexible.

```
-u, --uninstall /path_to_database | -s agent_service
```

Uninstalls the agent service associated with the specified database or service name. This removes the agent service information from the gwha.conf file. Do this after you have deleted the domain or post office that the agent serviced.

#### -upgrade

Upgrades Windows service definitions for the agents. Not applicable on Linux

## **Help Options:**

#### --help, -?

Displays the help information and exits.

#### **Files**

/opt/novell/groupwise/admin/gwadminutil

Script file that runs GWAdminUtil.

## **Examples**

This program normally runs as root.

#### gwadminutil services -1

Lists all agent information in the gwha.conf file.

#### gwadminutil services -1 mta, poa

Lists MTA and POA information in the gwha.conf file, but not the information for other agents on the server.

#### gwadminutil services -i -dva

Installs the DVA service on a server where no post office is located. You must use the GroupWise Installation Wizard to install the GroupWise Server software on the server, and start the Admin Service, before you can install agent services.

#### gwadminutil services -i -dva /media/nss/VOL1/dva1.dva

Installs a DVA service named dva1 in a Novell Cluster Services cluster where the startup file is located in the /media/nss/VOL1 folder. You must use the GroupWise Installation Wizard to install the GroupWise Server software on the server, and start the Admin Service, before you can install agent services.

#### gwadminutil services -i /gwsystem/engineering

Installs the POA service for the Engineering post office. You must use the GroupWise Installation Wizard to install the GroupWise Server software on the server, and start the Admin Service, before you can install agent services.

If you are installing a second POA service on a different server from where the post office is located, you must be able to specify the post office database location across a file system mount.

#### gwadminutil services -i /gwsystem/provo1

Installs the MTA service for the Provo1 domain. You must use the GroupWise Installation Wizard to install the GroupWise Server software on the server, and start the Admin Service, before you can install agent services.

#### gwadminutil services -i /gwsystem/provo1/wpgate/gwia

Installs the GWIA service for the Provo1 domain. You must use the GroupWise Installation Wizard to install the GroupWise Server software on the server, and start the Admin Service, before you can install agent services.

#### gwadminutil services -q

Displays current status information for all agents on the server. This is similar to grpwise status.

#### gwadminutil services -q poa

Displays current status information for the POA. This is similar to grpwise status engineering.provol.

#### gwadminutil services -start provol

Starts the MTA for the Provo1 domain. This is similar to grpwise start provo1.

#### gwadminutil services -stop engineering

Stops the POA for the Engineering post office. This is similar to grpwise stop provol.engineering.

#### gwadminutil services -u /gwsystem/provo1

Removes the Provo1 MTA information from the gwha.conf file. Do this after you have deleted the Provo1 domain.

#### gwadminutil services -u -s gwia

Removes the GWIA information from the gwha.conf file.

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

## See Also

gwadminutil(1)

# **5** GroupWise Service Control Utility

• "gwsc(1)" on page 54

## gwsc(1)

#### **Name**

gwsc - The GroupWise Service Control Utility

## **Syntax**

gwsc option [arguments]

## **Description**

Provides a short-hand version of the gwadminutil services command.

## **Options**

## **Usage Options:**

```
option [arguments]
```

Accepts all of the same options and arguments as the gwadminutil services command.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

```
/opt/novell/groupwise/admin/gwsc
```

Script file that runs GroupWise Service Control Utility.

## **Examples**

This program normally runs as root.

```
gwsc -1
```

Lists all agent information in the gwha.conf file. Equivalent to gwadminutil services -1.

```
gwsc -i -dva
```

Installs the DVA service on a server where no post office is located. Equivalent to gwadminutil services -i -dva.

```
gwsc -q
```

Displays current status information for all agents on the server. Equivalent to gwadminutil services -q.

```
gwsc -start provol
```

Starts the MTA for the Provol domain. Equivalent to gwadminutil services -start provol.

#### gwsc -stop engineering

Stops the POA for the Engineering post office. Equivalent to gwadminutil services -stop engineering.

## **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

### See Also

gwadminutil(1), gwadminutil-services(1)

# 6 GroupWise Database Utilities

- "gwcheck(1)" on page 58
- "gwcheckt(1)" on page 61
- "dbcopy(1)" on page 63
- "gwtmstmp(1)" on page 67

# gwcheck(1)

#### Name

gwcheck - GroupWise Check Utility

## **Syntax**

## **Description**

GroupWise Check (GWCheck) is a tool provided for GroupWise to check and repair GroupWise user, message, library, and resource databases without needing the Admin console. In addition to checking and repairing databases in the post office, it also checks and repairs users' remote, caching, and archive databases on user workstations or other personal locations.

GWCheck provides a user interface similar to the Mailbox/Library Maintenance feature in the GroupWise Admin console. The list below illustrates the types of database repair that you can perform using GWCheck. Click *Help* in GWCheck for more information about the database repair options that are available.

## **Analyze/Fix Databases**

```
Structure
    Index Check
Contents
    Collect Statistics
    Attachment File Check
Fix Problems
    Update User Disk Space Totals
```

## **Expire/Reduce Messages**

```
Reduce Only
Expire and Reduce
    Items Older Than
    Downloaded Items Older Than
    Items Larger Than
    Trash Older Than
    Reduce Mailbox To
    Reduce Mailbox to Limited Size
Include
    Received Items
    Sent Items
    Calendar Items
    Only Backed-Up Items
    Only Retained Items
```

#### **Mailbox Statistics**

Mailbox Statistics
Box Limit
Expire Statistics
(same as the Expire and Reduce options)

#### **Archive/Delete Documents**

(no options)

## **Delete Activity Logs**

Delete Logs Older Than nn Days

## Analyze/Fix Library

Verify Library
Fix Document/Version/Element
Verify Document Files
Validate All Document Security
Synchronize User Name
Remove Deleted Storage Areas
Move Documents First
Reassign Orphaned Documents
New Author
Reset Word Lists

## **Audit Report**

Log Accounts without Activity for Previous nn Days

## **GWCheck Options File**

If you repeatedly use the same set of database repair options, you can save them in an options file. To create an options file, start GWCheck, select database repair options as needed, then click *Save*. By default, the options file is named <code>gwcheck.opt</code> and is saved in your home folder. You can change the file name and location as needed.

You can retrieve the options file from the user interface or you can specify the options file on the command line. The options file is created in XML format.

After you have created one or more options files, you can run GWCheck as a script, rather than using the user interface.

## **Options**

## **Usage Options:**

--opt=options file

Specifies a database maintenance options file created in a GWCheck session. This starts GWCheck with the same options settings as the session in which the options file was created.

By default, this file is saved in your home folder. If you want to save it to another folder, specify a path relative to your home folder or specify an absolute path.

#### --batch

Runs GWCheck in the background, without a user interface. Use an options file to specify the database repair options.

#### --po=post\_office\_folder

Specifies the path to the post office folder.

#### --pa=archive folder

Specifies the path to the archive folder.

#### --pr=remote mailbox folder

Specifies the path to the remote mailbox folder.

### **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

```
[/path name/]gwcheck.opt
```

Options file. Create this file by setting database repair options in GWCheck, then click *Save*. The options file is created in XML format.

## **Examples**

This program normally runs as root.

/opt/novell/groupwise/gwcheck/bin/gwcheck

Starts the GUI GWCheck.

```
/opt/novell/groupwise/gwcheck/bin/gwcheck --opt=gwcheck.opt --batch
```

Starts GWCheck with an options file that provides default database repair options and runs it in batch mode so that there is no user interface.

/opt/novell/groupwise/gwcheck/bin/gwcheck --opt=gwcheck.opt --pa=/home/gsmith/
gwarchive

Runs GWCheck for an archive mailbox.

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

#### See Also

gwcheckt(1).

## gwcheckt(1)

#### Name

gwcheckt - Text-Based GroupWise Check Utility

## **Syntax**

qwcheckt options file [--dump]

## **Description**

Text-Based GroupWise Check (GWCheckT) is a tool provided for GroupWise to check and repair GroupWise user, message, library, and resource databases without needing the GroupWise Admin console or any GUI environment. Text-Based GWCheckT can perform all of the same types of database repair as the GUI GWCheck, but in a text-only environment.

Text-Based GWCheckT has no user interface. You must create the required options file by using the GUI GroupWise Check (GWCheck), or by using the Mailbox/Library Maintenance feature in the Admin console.

To create the required options file, start the GUI GWCheck in an environment where the X Window System is available, select database repair options as needed, then click *Save*. By default, the options file is named gwcheck.opt and is saved in your home folder. You can change the file name and location as needed.

## **Options**

## **Usage Options:**

```
[/path name/]options file
```

Specifies the name of the options file. By default, this file is saved by the GUI GWCheck in your home folder. If you saved it to another folder, specify a path relative to your home folder or specify an absolute path.

--dump

Displays the contents of the options file so that you can see what database repair options have been selected.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

```
options file
```

(Required) Use the GUI GWCheck to select and save database repair options in the gwcheck.opt file, then run the Text-Based GWCheckT with the options file to execute the database repair options.

## **Examples**

This program normally runs as root.

/opt/novell/groupwise/gwcheck/bin/gwcheckt gwcheck.opt

Runs GWCheckT in a text only environment, based on the database repair options provided in the options file created in the GUI GWCheck.

/opt/novell/groupwise/gwcheck/bin/gwcheckt gwcheck.opt --dump

Lists the settings of the database repair options in the specified options file.

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

#### See Also

gwcheck(1).

# dbcopy(1)

#### Name

dbcopy - GroupWise Database Copy Utility

## **Syntax**

## **Description**

The GroupWise Database Copy utility (DBCopy) copies files from a live GroupWise post office or domain to a static location for backup. During the copy process, DBCopy prevents the files from being modified, using the same locking mechanism used by other GroupWise programs that access databases. This ensures that the backed-up versions are consistent with the originals even when large databases take a substantial amount of time to copy.

In addition to backups, the DBCopy utility is used in conjunction with the GroupWise Server Migration Utility (http://www.novell.com/documentation/groupwise2014), which helps you migrate GroupWise data from NetWare or Windows to Linux. Some startup switches can be used for both backups and migration. Other startup switches are used only for migration.

## **Options**

## **General Usage Options:**

```
source folder
```

Specifies the full path to the domain folder, post office folder, or remote document storage area folder.

```
destination folder
```

Specifies the full path to the folder where you want to copy the domain, post office, or remote document storage area.

## **Usage Option for Backups Only:**

```
-i mm-dd-yyyy, -increment
```

Specifies the date of the previous copy of the data. This causes DBCopy to copy only files that have the specified date or newer, such as an incremental backup. There is no default date; you must specify a date or an increment backward from today. Valid increments are -1 to -31.

-j

Raises the priority of DBCopy processing. By default, if DBCopy detects that a POA is running, it lowers its own priority so that it does not interfere with POA processing. If DBCopy runs at night, when GroupWise users are not active, use the -j switch so that DBCopy does not lower its own priority. This speeds up DBCopy processing.

## **Usage Options for Backups and Migration:**

-b

Indicates that DBCopy is copying a document storage area, which includes BLOB (binary large object) files. Use this switch only when you need to copy BLOB files.

#### -t threads

Specifies the number of threads for DBCopy to start for copying data. The default number of threads is 5. Valid values range from 1 to 10.

-v

Turns on verbose logging, which provides more detail than the default of normal logging. DBCopy creates a log file named <code>mmddgwbk.nnn</code>. The first four characters represent the date. A three-digit extension allows for multiple log files created on the same day. The log file is created at the root of the destination domain, post office, or document storage area folder. In addition to status and error messages, it lists any remote document storage areas associated with a post office.

-w

Turns on continuous logging to the screen.

## **Usage Options for Migration Only:**

-m

Copies all directories and files associated with a domain, post office, or document storage area as part of a migration; also ensures that all folder names and file names are in lowercase.

-d

Indicates migration of a domain.

-p

Indicates migration of a post office.

-f

Indicates that this is the first pass of the migration process.

- s

Indicates that this is the second pass of the migration process.

#### -a ip address

Specifies the IP address to bind to for the migration process. The default is all available IP addresses.

#### -u port number

Specifies the TCP port number for status requests during the migration.

-k

Skips collecting database size information during the migration.

-0

Skips the second copy of the post office offiles folder during the migration.

#### -1 /source folder

Performs the GroupWise Check function of storelowercase on the migrated GroupWise databases. Its purpose is to do an "in-place" conversion of files and directories to lowercase, rather than as part of a copy operation. For a post office, it also updates the guardian database with the new, lowercase names.

For example, you could use this functionality if you have a domain or post office located on a SAN that was mounted for access by the GroupWise NetWare agents, but you now want to run the GroupWise Linux agents for the domain or post office, because NetWare is not supported as of GroupWise 2012.

Do not use other switches with the -l switch.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

#### **Files**

```
/path name/mmddgwbk.nnn
```

Log file created at the root of the destination folder.

## **Examples**

This program normally runs as root.

## **Backup Examples:**

```
/opt/novell/groupwise/agents/bin/dbcopy /gwsystem/acct /backups/acct
    Copies a post office to a backup location.
/opt/novell/groupwise/agents/bin/dbcopy --b /gwsystem/acct_library /backups/acct_library
```

Copies a library to a backup location.

## **Migration Examples:**

```
/opt/novell/groupwise/agents/bin/dbcopy -m -f /post_office_folder /
destination_folder
    Performs the first migration pass for a post office.
/opt/novell/groupwise/agents/bin/dbcopy -m -s /post_office_folder /
destination_folder
    Performs the second migration pass for a post office.
/opt/novell/groupwise/agents/bin/dbcopy -m /domain_folder /destination_folder
    Migrates a domain.
/opt/novell/groupwise/agents/bin/dbcopy -m -b /storage_area_folder /
destination_folder
    Migrates a document storage area.
```

## **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

## See Also

gwtmstmp(1).

# gwtmstmp(1)

#### Name

gwtmstmp - GroupWise Time Stamp Utility

## **Syntax**

## **Description**

The GroupWise Backup Time Stamp utility (GWTMSTMP) places date and time information on user databases (userxxx.db) in order to support message backup, restore, and retention. The time stamp indicates the last time the database was backed up.

If a user deletes an item from his or her mailbox and purges it from the Trash, the item is removed from the user's database only if the time stamp shows that the item has already been backed up. Otherwise, the item remains in the user's database until the database is backed up, at which time it is purged from the database.

You can run GWTMSTMP on all user databases in a post office or on a single user database. No other databases are affected.

## **Backup**

To ensure thorough user database backups, you can ensure that deleted items are not purged from users' databases until they have been backed up. Two conditions must be met in order to provide this level of protection against loss of deleted items:

- The *Do Not Purge Items Until They Are Backed Up* option must be selected for the post office in the Admin console (*post\_office\_object > Client Options > Environment > Cleanup*).
- User databases (userxxx.db) must be time-stamped every time a backup is performed so that items can be purged only after they are backed up.

#### Restore

You can use GWTMSTMP to manually add the restore time stamp to the database. The restore time stamp is not required for any GroupWise feature to work properly. Its primary purpose is informational.

#### Retention

If you use a message retention application, the application should automatically add the retention time stamp after retaining the database's messages. Any messages with dates that are newer than the retention time stamp cannot be purged from the database. You can use GWTMSTMP to manually add a retention time stamp.

### **Modified Retention**

If you use a message retention application, you might need to retain items more than once if you want to capture changes to personal subjects and personal attachments on items. You can use GWTMSTMP to manually update the retention time stamp on modified items, so that they are retained again.

## **Options**

## **Usage Options:**

#### --postpath /post\_office\_folder, -p /post\_office\_folder

(Required) Specifies the full path to the post office folder where the user databases to time-stamp are located.

#### --set, -s

Sets the current date and time (of backup, restore, or retention) on user databases.

#### --get, -g

Lists existing backup, restore, and retention time stamp information for user databases. If no time stamps are set, no times are displayed. If no other operational switch is used, --get is assumed.

#### --clear, -c

Removes time stamps (of backup, restore, or retention) from user databases.

```
--backup, --restore, --retention, --modified retention, -b, -r, -n, -mn
```

Specifies the type of time stamp (backup, restore, retention, or modified retention) on which to perform the get or set operation. If no time stamp type is specified, the operation is performed on the backup time stamp. Multiple time stamp types can be specified.

#### --date mm/dd/yyyy, -d mm/dd/yyyy

Specifies the date that you want placed on user databases. If no date is specified, the current date is used.

Use the format mm/dd/yyyy (for example, 05/18/2014 for May 18, 2014). If your locale does not use the mm/dd/yyyy format, use gwtmstmp --help to determine the format for your locale.

#### --time hh:mm[am|pm],-t hh:mm[am|pm]

Specifies the time that you want placed on user databases. If no time is specified, 00:00 is used.

Use the format hh: mm, expressed in a 24-hour format (for example, 20:45) or expressed with the am or pm option (for example, 8:45pm).

#### -- gmttime seconds, -m seconds

Specifies the number of seconds since midnight on January 1, 1970 Greenwich Mean Time (GMT), that you want placed on the user databases.

```
--userid user name, -u user name
```

Provides a specific GroupWise user name so that an individual user database can be time-stamped.

#### --userdb user database, -e user\_database

Provides a specific user database (userxxx.db) so that an individual user database can be time-stamped.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

## **Examples**

This program normally runs as root.

```
/opt/novell/groupwise/agents/bin/gwtmstmp -p /gwsystem/acct
```

Checks the existing time stamp on all GroupWise user databases in a post office.

/opt/novell/groupwise/agents/bin/gwtmstmp -p /gwsystem/acct --set

Sets a current time stamp on all user databases in a post office.

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

### See Also

dbcopy(1).

# 7 Linux GroupWise Agent Commands

- "grpwise(1)" on page 72
- "grpwise-ma(1)" on page 75
- "gwpoa(1)" on page 77
- "gwmta(1)" on page 79
- "gwia(1)" on page 81
- "gwdva(1)" on page 84
- "gwmon(1)" on page 86

# grpwise(1)

#### Name

grpwise - GroupWise Script

## **Syntax**

```
grpwise start [object]
grpwise status [object]
grpwise stop [object]
grpwise restart [object]
grpwise restartall
grpwise print [object]
```

#### The objects are:

Admin Service: gwadminservice

POA: post office name.domain name

MTA: domain\_name

GWIA: gwia.domain\_name

DVA: gwdva.post office name

**NOTE:** The Monitor Agent is not controlled by the grpwise script. It has its own script named grpwise-ma, which works essentially the same as the grpwise script.

## Description

The grpwise script is created during installation and can control any agents installed on the local server. It is created in the /etc/init.d folder. It works in conjunction with the gwha.conf file, which is created in the /etc/opt/novell/groupwise folder. The gwha.conf file lists the agents installed on the local server so that the grpwise script knows which agents to start.

The GroupWise agents are Run Control compliant. During installation, a symbolic link is created from /etc/init.d/grpwise to /usr/sbin/rcgrpwise. Typically, /usr/sbin is already on your path. This enables you to run rcgrpwise from any folder, rather than changing to /etc/init.d in order to run the grpwise script.

## **Options**

## **Usage Options:**

#### start

Starts all GroupWise agents on the local server or the specific GroupWise agent specified in the grpwise command. A green "done" indicates that an agent is running. If a green "done" does not appear, the agent was unable to start.

#### status

Displays status for all GroupWise agents on the local server or the specific GroupWise agent specified in the <code>grpwise</code> command. A green "running" indicates that an agent is running. A black "unused" indicates that an agent is not running.

#### stop

Stops all GroupWise agents on the local server or the specific GroupWise agent specified in the grpwise command. A green "done" indicates that an agent is stopped. A black "unused" indicates that an agent is not running and therefore cannot be stopped.

#### restart

Restarts all GroupWise agents on the local server or the specific GroupWise agent specified in the grpwise command. A green "done" indicates that an agent is stopped. A black "unused" indicates that an agent is not running and therefore cannot be stopped. The agents then start again with the standard start status indicators.

#### print

Lists settings for all GroupWise agents in the gwha.conf file or for the GroupWise agent specified in the grpwise command.

#### post office name.domain name

Specifies the POA to start or stop. The syntax allows for multiple POAs running on the same server and specifies which POA to start or stop.

#### domain name

Specifies the MTA to start or stop. The syntax allows for multiple MTAs running on the same server and specifies which MTA to start or stop.

#### gwia.domain name

Specifies the GWIA to start or stop. The syntax allows for multiple GWIAs running on the same server and specifies which GWIA to start or stop.

#### gwdva.post office name

Specifies the DVA to start or stop. The syntax allows for multiple DVAs running on the server. Running multiple DVAs on a server is not recommended.

# **Help Options:**

```
--help, -?
```

Displays the help information and exits.

### **Files**

#### /etc/opt/novell/groupwise/gwha.conf

GroupWise High Availability Service (gwha) configuration file. This configuration file lists all information necessary to start and stop each GroupWise agent that is installed on the server. For example, an entry for an MTA might look similar to this:

```
server = /opt/novell/groupwise/agents/bin/gwmta
command = /etc/init.d/grpwise
startup = /gwsystem/provol/provol.mta
delay = 2
wait = 10
```

The server = setting specifies the full path to the agent executable.

The command = setting specifies the full path to the grpwise script.

The startup = setting specifies the name of the agent startup file. Agent startup files are found in the following locations:

```
/post_office_folder/post_office_name.poa
/domain_folder/domain_name.mta
/domain_folder/wpgate/gwia/gwia.cfg
/post office folder/post office name.dva
```

The delay = setting controls the length of time between when the script issues the command to start an agent and when the script displays a message indicating that the agent has started. The default delay time is 2 seconds.

The wait = setting controls the length of time between when the script issues the command to stop an agent and when the script kills the agent if the agent has not yet stopped. The default wait time is 10 seconds.

By default, the grpwise script starts the agents as services with no user interface. If you want a user interface, you can add a show = yes line for each agent that you want to have a user interface. An agent that runs with a user interface cannot be managed in the GroupWise Admin console because it is not running as a service.

## **Examples**

This script must be run as root. If you have configured the GroupWise agents to run as a non-root user, they switch over to that user after they have started.

In all of the examples below, replace /etc/init.d/grpwise with rcgrpwise to run the script from any folder.

```
/etc/init.d/grpwise start
```

Starts all GroupWise agents that are installed on the server.

```
/etc/init.d/grpwise status development.provol
```

Shows the status of the Development post office POA. The Development post office belongs to the Provo1 domain.

```
/etc/init.d/grpwise stop gwia.provo1
```

Stops the GWIA that belongs to the Provo1 domain.

# **Diagnostics**

If a GroupWise agent fails to start when using the grpwise script, try starting the agent manually, as described in the man page for each agent. You might receive an error message indicating why the agent is failing to start.

If you have changed the non-root user that you want the agent to run by modifying the /etc/opt/novell/groupwise/agents/uid.conf file, you might have forgotten to delete the corresponding uid.run file in the domain or post office folder that the agent services. Delete the uid.run file, then use the grpwise script to try to start the agent again.

### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

### See Also

```
gwpoa(1), gwmta(1), gwia(1), gwdav(1).
```

# grpwise-ma(1)

### Name

grpwise-ma - GroupWise Monitor Script

## **Syntax**

grpwise-ma [start] [stop] [status] [restart]

## **Description**

The grpwise-ma script is created during installation and controls the Monitor Agent. (The grpwise script controls the other four GroupWise agents.) The grpwise-ma script is created in the /etc/init.d folder. It works in conjunction with the monitor.xml file, which is created in the /opt/novell/groupwise/agents/share folder. The monitor.xml file points the Monitor Agent to a domain database (wpdomain.db) where it can access a list of agents to monitor in your GroupWise system.

The grpwise-ma script includes an MA\_OPTIONS variable where you can specify Monitor Agent startup switches. This is convenient because the Monitor Agent does not use a startup file as the other GroupWise agents do.

The Monitor Agent is Run Control compliant. During installation, a symbolic link is created from / etc/init.d/grpwise-ma to /usr/sbin/rcgrpwise-ma. Typically, /usr/sbin is already on your path. This enables you to run rcgrpwise-ma from any folder, rather than changing to /etc/init.d in order to run the grpwise-ma script.

# **Options**

# **Usage Options:**

#### start

Starts the Monitor Agent as a service on the local server. A green "done" indicates that an agent is running. If a green "done" does not appear, the agent was unable to start.

#### status

Displays status for the Monitor Agent. A green "running" indicates that an agent is running. A black "unused" indicates that an agent is not running.

#### stop

Stops the Monitor Agent. A green "done" indicates that an agent is stopped. A black "unused" indicates that an agent is not running and therefore cannot be stopped.

#### restart

Stops the Monitor Agent. A green "done" indicates that an agent is stopped. A black "unused" indicates that an agent is not running and therefore cannot be stopped. The Monitor Agent then starts again with the standard start status indicators.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

### **Files**

#### /opt/novell/groupwise/agents/share/monitor.xml

Monitor Agent configuration file. Provides a domain folder where the Monitor Agent can determine what GroupWise agents to monitor. The monitor.xml file is created during installation.

#### /var/opt/novell/groupwise/monitor/gwmonitor.cfg

Monitor Application configuration file. Provides integration information for passing agent status information gathered by the Monitor Agent to your web browser for display in the main Monitor web console.

### **Examples**

This script does not need to be run as root.

In the example below, /etc/init.d/grpwise-ma can be replaced with rcgrpwise-ma to run the script from any folder.

#### /etc/init.d/grpwise-ma start

Starts the Monitor Agent.

You can view the Monitor Agent console at the following URL:

http://localhost:8200

You can view the Monitor console at the following URL:

http://localhost/gwmon/gwmonitor

### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

#### See Also

```
gwmon(1).
```

# gwpoa(1)

### **Name**

gwpoa - GroupWise Post Office Agent

## **Syntax**

```
gwpoa [--show] --home /post_office_folder
gwpoa [--show] @/post office folder/post office name.poa
```

## **Description**

A post office serves as an administrative unit for a group of users and mailboxes. Messages are delivered to mailboxes by the Post Office Agent (POA).

The Post Office Agent (POA) responds to GroupWise client requests for mailbox data and delivers messages between users' mailboxes in a post office. The POA also communicates with the MTA to route messages to and from the post office. In addition, the POA performs a variety of maintenance tasks in the post office.

You can provide POA startup switches on the command line or in a startup file. By default, the startup file is named after the post office and has a .poa extension. It is located in the post office folder.

# **Options**

# **Usage Options:**

```
--home /post office folder
```

Specifies the post office folder, where the POA can access message and user databases. There is no default location. You must use this switch in order to start the POA.

The Installation Wizard automatically sets the --home switch to the post office folder in the POA startup file.

```
@/post offce folder/post office name.poa
```

Specifies the location of the POA startup file. The POA startup file is created in the post office folder and is named after the post office, with a .poa extension. The POA startup file includes the --home switch.

For information about agent startup switches, see the *GroupWise Administration Guide* (http://www.novell.com/documentation/groupwise2014).

### --show

Starts the POA with a server console user interface. The agent user interface requires that the X Window System and Open Motif are running on the Linux server.

By default, no user interface is provided for the agents on Linux. An agent that runs with a user interface cannot be managed in the GroupWise Admin console.

The --show startup switch can be used on the command line or in the gwha.conf file used by the GroupWise High Availability Service. It cannot be placed in the agent startup file.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

### **Files**

```
/post office folder/post office name.poa
```

Startup file where startup switches are specified.

/var/log/novell/groupwise/post office.poa/mmddpoa.nnn

Log file where error messages are written.

### **Examples**

By default, this program runs as root, but it is preferable to run it as a non-root user. See the *GroupWise Installation Guide* (http://www.novell.com/documentation/groupwise2014) to set up the agent to run as a non-root user.

```
/opt/novell/groupwise/agents/bin/gwpoa --home /gwsystem/acct
```

Starts the POA by specifying the post office folder.

/opt/novell/groupwise/agents/bin/gwpoa @/gwsystem/acct/acct.poa

Starts the POA by specifying the POA startup file.

```
/opt/novell/groupwise/agents/bin/gwpoa --show @/gwsystem/acct/acct.poa
```

Starts the POA with a user interface. An agent that runs with a user interface cannot be managed in the GroupWise Admin console because it is not running as a service.

# **Diagnostics**

By default, error messages are written to the POA log file located in the /var/log/novell/groupwise/post\_office\_name.poa folder. You can view agent log files in the agent console.

Typically, you find multiple log files in this folder. The first four characters of each file name represent the date. The next three characters identify the agent. A three-digit extension allows for multiple log files created on the same day. For example, a log file named 0518poa.001 indicates that it is a POA log file created on May 18. If you restart the POA on the same day, a new log file is created, named 0518poa.002.

#### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

#### See Also

grpwise(1)

# gwmta(1)

### Name

gwmta - GroupWise Message Transfer Agent

## **Syntax**

```
gwmta [--show] --home /domain_folder
gwmta [--show] @/domain folder/domain name.mta
```

## **Description**

A domain organizes post offices into a logical grouping for administration and routing purposes in your GroupWise system. Messages are transferred between post offices and domains by the Message Transfer Agent (MTA). Messages are transferred to and from your GroupWise system by the Internet Agent (GWIA).

You can provide MTA startup switches on the command line or in a startup file. By default, the startup file is named after the domain and has a .mta extension. It is located in the domain folder.

## **Options**

### **Usage Options:**

#### --home /domain folder

Specifies the domain folder, where the MTA can access the domain database (wpdomain.db). There is no default location. You must use this switch in order to start the MTA.

The Installation Wizard automatically sets the --home switch to the domain folder in the MTA startup file.

#### @/domain folder/domain name.mta

Specifies the location of the MTA startup file. The MTA startup file is created in the domain folder and is named after the domain, with a .mta extension. The startup file includes the -- home switch.

For information about agent startup switches, see the *GroupWise Administration Guide* (http://www.novell.com/documentation/groupwise2014).

#### --show

Starts the MTA with a server console user interface.

By default, no user interface is provided for the agents on Linux. An agent that runs with a user interface cannot be managed in the GroupWise Admin console.

The --show startup switch can be used on the command line or in the gwha.conf file used by the GroupWise High Availability Service. It cannot be placed in the agent startup file.

### **Help Options:**

```
--help, -?
```

Displays the help information and exits.

### **Files**

```
/domain folder/domain name.mta
```

Startup file where startup switches are specified.

/var/log/novell/groupwise/domain.mta/mmddmta.nnn

Log file where error messages are written.

### **Examples**

By default, this program runs as root, but it is preferable to run it as a non-root user. See the *GroupWise Installation Guide* (http://www.novell.com/documentation/groupwise2014) to set up the agent to run as a non-root user.

```
/opt/novell/groupwise/agents/bin/gwmta --home /gwsystem/provol
```

Starts the MTA by specifying the domain folder.

/opt/novell/groupwise/agents/bin/gwmta @/gwsystem/provo1/provo1.mta

Starts the MTA by specifying the MTA startup file.

/opt/novell/groupwise/agents/bin/gwmta --show @/gwsystem/provo1/provo1.mta

Starts the MTA with a user interface. An agent that runs with a user interface cannot be managed in the GroupWise Admin console because it is not running as a service.

# **Diagnostics**

Error messages are written to the MTA log file located in the /var/log/novell/groupwise/domain name.mta folder. You can view agent log files in the agent console.

Typically, you find multiple log files in this folder. The first four characters of each file name represent the date. The next three characters identify the agent. A three-digit extension allows for multiple log files created on the same day. For example, a log file named 0518mta.001 indicates that it is an MTA log file created on May 18. If you restart the MTA on the same day, a new log file is created, named 0518mta.002.

### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

#### See Also

grpwise(1)

# gwia(1)

### Name

gwia - GroupWise Internet Agent

# **Syntax**

```
gwia [--show] --home /domain_folder/wpgate/gwia
gwia [--show] @/domain_folder/wpgate/gwia_folder/gwia.cfg
gwia [--show] --dhome /domain_folder/wpgate/smtp_folder
gwia [--show] --hn hostname
```

## **Description**

The Internet Agent (GWIA) converts GroupWise messages into SMTP format and transfers them to the Internet SMTP hosts where recipients are located. In reverse, it receives SMTP messages from Internet SMTP hosts and converts them into GroupWise format. The GWIA can also provide access for POP3 and IMAP4 clients to access GroupWise mailboxes.

You can provide GWIA startup switches on the command line or in a startup file. At startup, the GWIA reads its startup file, gwia.cfg. It is located in the /domain\_folder/wpgate/gwia folder.

## **Options**

### **Usage Options:**

#### --home /domain folder/wpgate/gwia

Specifies the GWIA home folder (/domain\_folder/wpgate/gwia), where the GWIA can find its databases, input/output queues, and configuration files. There is no default location. You must use this switch in order to start the GWIA.

The Installation Wizard automatically sets the --home switch to the domain folder in the MTA startup file.

#### @/domain folder/wpgate/gwia/gwia.cfg

Specifies the location of the GWIA configuration file (gwia.cfg). The gwia.cfg file is created in the /domain folder/wpgate/gwia folder. The gwi.cfg file includes the --home switch.

For information about agent startup switches, see the *GroupWise Administration Guide* (http://www.novell.com/documentation/groupwise2014).

### --dhome /domain\_folder/wpgate/SMTP\_folder

Points to the SMTP service work area. This is normally the same as the GWIA folder (/ domain\_folder/wpgate/gwia).

#### --hn hostname

Specifies the hostname that is displayed when someone connects to your GWIA using a Telnet session. You should enter the hostname assigned to you by your Internet service provider.

#### --show

Starts the GWIA with a server console user interface.

By default, no user interface is provided for the agents on Linux. An agent that runs with a user interface cannot be managed in the GroupWise Admin console.

The --show startup switch can be used on the command line or in the gwha.conf file used by the GroupWise High Availability Service. It cannot be placed in the agent startup file.

## **Help Options:**

```
--help, -?
```

Displays the help information and exits.

### **Files**

/domain folder/wpgate/gwia/gwia.cfg

Startup file where startup switches are specified.

/var/log/novell/groupwise/gwia.domain name/mmddgwia.nnn

Log file where error messages are written.

## **Examples**

By default, this program runs as root, but it is preferable to run it as a non-root user. See the *GroupWise Installation Guide* (http://www.novell.com/documentation/groupwise2014) to set up the agent to run as a non-root user.

/opt/novell/groupwise/agents/bin/gwia --home /gwsystem/provol/wpgate/gwia Starts the GWIA by specifying its GWIA folder in the domain.

/opt/novell/groupwise/agents/bin/gwia @/gwsystem/provol/wpgate/gwia/gwia.cfg Starts the GWIA by specifying its startup file.

/opt/novell/groupwise/agents/bin/gwia --show @/gwsystem/provol/wpgate/gwia/
gwia.cfg

Starts the GWIA with a user interface. An agent that runs with a user interface cannot be managed in the GroupWise Admin console because it is not running as a service.

# **Diagnostics**

Error messages are written to the GWIA log file located in the /var/log/novell/groupwise/domain name.gwia folder. You can view agent log files in the agent console.

Typically, you find multiple log files in this folder. The first four characters of each file name represent the date. The next three characters identify the agent. A three-digit extension allows for multiple log files created on the same day. For example, a log file named <code>0518gwia.001</code> indicates that it is a GWIA log file created on May 18. If you restart the GWIA on the same day, a new log file is created, named <code>0518gwia.002</code>.

### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

# See Also

grpwise(1)

# gwdva(1)

### Name

gwdva - GroupWise Document Viewer Agent

# **Syntax**

gwdva [@/post office folder/post office name.dva]

## **Description**

The Document Viewer Agent (DVA) converts attached document files from a wide variety of formats into HTML format for indexing by the POA and for viewing in GroupWise WebAccess. You can run up to three DVAs to service conversion requests for a single instance of the POA. Each DVA must be installed on a different server.

The DVA consists of a master DVA process, and multiple worker DVA processes. The master DVA process communicates with the WebAccess Application and the POA to transfer documents back and forth for conversion. Each worker process converts a single document. Because some documents contain unexpected data, they cannot be successfully converted. Such a conversion failure terminates a worker process, but does not affect the stability of the master DVA process.

You can provide DVA startup switches on the command line or in a startup file. By default, the startup file is named after the post office and has a .dva extension. It is located in the /opt/novell/groupwise/agents/share folder.

## **Options**

# **Usage Options:**

--home folder

Specifies the path to the DVA working folder. The default location is /var/opt/novell/groupwise/gwdva.

#### @startup file

Specifies the location of the DVA startup file. The DVA startup file is created in the <code>/opt/novell/groupwise/agents/share</code> folder and is named after the post office, with a .dva extension.

For information about agent startup switches, see the *GroupWise Administration Guide* (http://www.novell.com/documentation/groupwise2014).

# **Help Options:**

--help, -?

Displays the help information and exits.

### **Files**

```
/opt/novell/groupwise/share/post_office_name.dva
Startup file where startup switches are specified.
/var/log/novell/groupwise/dva/mmdddva.nnn
Log file where error messages are written.
```

### **Examples**

This program must run as root.

```
/opt/novell/groupwise/agents/bin/gwdva
Starts the DVA using its default configuration.
```

```
/opt/novell/groupwise/agents/bin/gwdva --home /var/opt/novell/groupwise/gwdva Starts the DVA and specifies its working folder.
```

```
/opt/novell/groupwise/agents/bin/gwdva @gwdva.dva
Starts the DVA by specifying its startup file.
```

# **Diagnostics**

Error messages are written to the DVA log file located in the /var/log/novell/groupwise/gwdva folder. You can view agent log files in the agent console.

Typically, you find multiple log files in this folder. The first four characters of each file name represent the date. The next three characters identify the agent. A three-digit extension allows for multiple log files created on the same day. For example, a log file named 0518dva.001 indicates that it is a DVA log file created on May 18. If you restart the DVAA on the same day, a new log file is created, named 0518dva.002.

### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

### See Also

grpwise(1)

# gwmon(1)

### Name

gwmon - GroupWise Monitor Agent

## **Syntax**

gwmon --home domain folder

## **Description**

GroupWise Monitor is a monitoring and management tool that allows you to monitor GroupWise agents from any location where you are connected to the Internet and have access to a web browser. Some agent administration can also be performed from your web browser. Monitor provides more detail than is provided on the System page in the GroupWise Admin console.

The Monitor Agent continuously polls the POA, MTA, and GWIA; gathers status information from them; and displays the status information in the Monitor Agent console. The Monitor Agent also services requests for agent status information from the Monitor Application, which displays the Monitor Web console.

Monitor Agent configuration information is stored in the monitor.xml file in the /opt/novell/groupwise/agents/share folder.

# **Options**

# **Usage Options:**

--home domain folder

Specifies a domain folder where the Monitor Agent can access a domain database (wpdomain.db). From the domain database, the Monitor Agent can determine which agents to monitor, what user names and passwords are necessary to access them, and so on.

For information about agent startup switches, see the *GroupWise Administration Guide* (http://www.novell.com/documentation/groupwise2014).

# **Help Options:**

--help, -?

Displays the help information and exits.

### **Files**

/opt/novell/groupwise/agents/share/monitor.xml

Monitor Agent configuration file. Provides a domain folder where the Monitor Agent can determine which GroupWise agents to monitor. The monitor.xml file is created during installation.

/var/log/novell/groupwise/gwmon/mmddmon.nnn

Log file for Monitor Agent events.

/var/log/novell/groupwise/gwmon/mmddhist.nnn

Log file for dumps of monitored agent MIB values.

### **Examples**

This program can run as any user.

/opt/novell/groupwise/agents/bin/gwmon --home /gwsystem/provo1

Starts the Monitor Agent by accessing the domain database in the specified domain folder.

### **Diagnostics**

The Monitor Agent writes to two different types of log files. Event log files record error messages, status messages, and other types of event-related messages. History log files record dumps of all MIB values gathered during each poll cycle of monitored agents. By default, both types of log files are created in the /var/log/novell/groupwise/gwmon folder.

Typically, you find multiple log files in this folder. The first four characters of each file name represent the date. The following characters are mon for event log files and hist for history log files. A three-digit extension allows for multiple log files created on the same day. For example, a log file named 0518mon.001 indicates that it is a Monitor Agent event log file created on May 18. If you restart the Monitor Agent on the same day, a new event log file is created, named 0518mon.002.

### **Authors**

Copyright 2004-2014, Novell, Inc. (http://www.novell.com/home/). All rights reserved.

### See Also

grpwise-ma(1).