

Novell Small Business Suite

6.5

www.novell.com

QUICK START

Installing a New Server

This Quick Start provides basic information for setting up a new server to run products in the Novell Small Business Suite, including NetWare® 6.5 with SP1, GroupWise® 6.5 with SP1, BorderManager® 3.8, and ZENworks® for Desktops 4.0.1.

- ♦ “Installing a New Server” on page 1
- ♦ “Installing Additional Products in the Suite” on page 7
- ♦ “Accessing Administration Utilities” on page 9
- ♦ “Small Business Server Configuration Worksheet” on page 11

PLAN DEPLOYMENT

This new server can be the first server in your network that you set up, or you can install it into an existing network. If you are upgrading the operating system or any of the other products in the suite from a previous version of Novell Small Business Suite, see [Upgrading the Server and Other Products in the Suite](#) in the *Novell Small Business Suite 6.5 Overview and Installation Guide*.

For complete instructions and known and interoperability issues, see the *Novell Small Business Suite 6.5 Overview and Installation Guide* and *Novell Small Business Suite 6.5 Readme*.

You can set up a basic server for file, print, and collaboration fairly quickly on basic hardware. To set up a server that includes the full functionality provided by the suite requires additional planning and setup. For details, see [Planning Your Deployment](#) in the *Novell Small Business Suite 6.5 Overview and Installation Guide*.

Novell®

MEET RECOMMEND SYSTEM REQUIREMENTS

Meet the system requirements for the products you want to deploy. To install all products included in the suite on a single server, make sure the server meets the following recommended requirements.

NOTE: Nterprise™ Branch Office™, DirXML® Starter Pack, and Novell® Cluster Services™ require more than one server.

- A server-class PC with two-way Pentium* III, Pentium III Xeon, Pentium4, or Intel* Xeon 700 MHz or higher processors.
- One or more network boards.
- A bootable CD drive that supports the El Torito specification.
- A USB or PS/2* mouse.
- A Super VGA or higher resolution display adapter.
- 1 GB of RAM. If installing BorderManager Proxy Services, an additional 1 GB of RAM is recommended.
- A boot partition with 1 GB of available space.
- Disk Space:
 - ◆ 8 GB of available, unpartitioned disk space outside the DOS partition for volume sys:
 - ◆ 2 GB for GroupWise (1 GB for the GroupWise file copy directories on volume sys: and 1 GB data volume or an additional 1 GB on volume sys: for user's Post Office directories)
 - ◆ 2 GB minimum dedicated CACHE volume for BorderManager Proxy Services. This volume must be a Traditional volume.

MEET SOFTWARE AND OTHER REQUIREMENTS

Depending on the network configuration, you might need the following:

- Novell Small Business Suite Operating System and Products* CDs and *License* diskette.
- Novell Clients Software* CD.
- Novell GroupWise Admin, Client, and Messenger* CDs (required only when copying GroupWise files).
- Novell Nterprise Branch Office* CD (required only when installing the Branch Office component of NetWare).
- Supervisor right at the [Root] of the eDirectory tree. User Admin or equivalent has this right.

- ❑ If connecting to the Internet: Contract services from an Internet Service Provider (ISP) and get the desired setup and IP information required. If the ISP requires PPPoE handshaking, you need to set up a third-party gateway router.

For details, see the ["Small Business Server Configuration Worksheet"](#) on page 11 and the [Setting Up Internet Connectivity](#) in the *Novell Small Business Suite 6.5 Overview and Installation Guide*.

- ❑ If the drivers are not included in the installation: Know the network board and storage device properties, such as the interrupt and port address.
- ❑ If the computer does not boot from CD: DOS and CD drivers

PREPARE THE NETWORK FOR THE SERVER

If installing into an existing network, prepare the network for the new server by running NetWare Deployment Manager.

- 1 On a Windows* NT*/2000 or Windows XP Professional Edition workstation that has the latest Novell client installed on it, log in to your existing tree as a user with the Supervisor right.
- 2 Insert the *Novell Small Business Suite Operating System* CD and run NetWare Deployment Manager (nwdeploy.exe) located at the root of the CD.
- 3 Complete all the relevant tasks in the Network Preparation section.

INSTALL SERVER SOFTWARE

- 1 Install computer and networking hardware.
- 2 Insert the *Novell Small Business Suite Operating System* CD into the computer and boot the computer.
- 3 Select the operating system settings and configuration options.
- 4 Select the installation type: Default or Manual.
 - ♦ **Default:** Automatically detects drivers and installs the NetWare 6.5 server with default settings. The settings include the following: 8 GB volume sys: with remaining disk space used for a Data volume, LAN and disk drivers auto-discovered and loaded, Video mode: SVGA Plug N Play, Mouse: Auto-discovered and loaded.
 - ♦ **Manual:** Lets you choose specific configuration options for your networking environment and lets you change any of the default settings.
- 5 Choose the server type you want to set up. The following pattern options are recommended.

TIP: To see the individual components selected in a pattern, select it and click Next. Then click Back and choose the Customize option. You will see all the products individually with the pattern defaults checked. However, if you want to install a pattern made sure you select the pattern option before proceeding.

- ♦ **Novell Small Business Collaboration Server with Virtual Office (recommend):** Installs all components for setting up and managing a Novell Small Business server plus components for GroupWise and Virtual Office.

This pattern allows both client-based and Web-based access to file, print, directory, and e-mail services. Local users can access collaboration services through GroupWise and Novell clients; remote users can access those same services through a Virtual Office Web interface.

After the server installation is complete, you can access the Small Business Setup Role in iManager to help you simplify your configuration of Internet Connectivity, GroupWise and Messenger, DNS/DHCP, and iPrint.

Small Business Server components include Novell iManager, Common Mailbox Forwarding, iPrint, Novell DNS/DHCP Services, Apache 2 Web Server and Tomcat 4 Servlet Container, WAN Connectivity, and Small Business specific and basic NetWare files.

The GroupWise and Messenger File Copy for a New GroupWise System component copies files necessary to install and configure a new GroupWise system and GroupWise Messenger.

The Virtual Office components include Novell Virtual Office Framework, Novell eGuide, Novell iFolder® Storage Services, Novell NetStorage, NetWare Web Search Server, OpenSSH, and Refresh Native File Access Login Methods (NFAP).

- ♦ **Novell Small Business Collaboration Server:** Installs all components for setting up and managing a Novell Small Business server with GroupWise.

This pattern allows GroupWise and Novell client-based access to files, printing, and e-mail (both local and Internet).

After the server installation is complete, you can access the Small Business Setup Role in iManager to help you simplify your configuration of Internet Connectivity, GroupWise and Messenger, DNS/DHCP, and iPrint.

Small Business Server components include Novell iManager, Common Mailbox Forwarding, iPrint, Novell DNS/DHCP Services, Apache 2 Web Server and Tomcat 4 Servlet Container, WAN Connectivity, and Small Business specific and basic NetWare files.

The GroupWise and Messenger File Copy for a New GroupWise System component copies files necessary to install and configure a new GroupWise system and GroupWise Messenger.

- ♦ **Customized NetWare Server:** Lets you customize the server to fit your needs. We recommend selecting the following components:

- Apache2 Web Server and Tomcat 4 Servlet Container
- GroupWise and Messenger File Copy for a New GroupWise System
- iPrint
- Novell iManager 2.0
- NetWare Web Search Server
- Novell DNS/DHCP Print Services
- Novell eGuide
- Novell iFolder Storage Services
- Novell NetStorage
- Novell Virtual Office Framework
- Refresh Native File Access Login Methods
- TCP/IP Files for Enabling Novell BorderManager 3.8 VPN
- WAN Connectivity

- 6 Insert additional CDs when prompted and follow the onscreen prompts.
- 7 Complete the installation by rebooting and starting the server.

IMPORTANT: Make sure you reboot the server before starting the Small Business Setup configurations in iManager.

SET UP A WORKSTATION FOR ADMINISTRATION

- 1 Install the Novell Client™ software.

For setup and configuration information, see the [Novell Client online documentation \(http://www.novell.com/documentation/lg/noclienu/index.html\)](http://www.novell.com/documentation/lg/noclienu/index.html).

- 2 Access iManager at the workstation by opening a Web browser and entering either the IP address or DNS name of the server, followed by /nps/iManager.html. For example:

```
http://172.16.135.150/nps/iManager.html
```

or

```
http://myserver.mycompany.com/nps/iManager.html
```

- 3 Set up access to ConsoleOne® from a workstation by mapping a drive letter to the Small Business server and run consoleone.exe stored in the volume:\public\mgmt\consoleone\1.2\bin directory.

If you are planning to use ZENworks for Desktops, you need to install version 1.3.5 of ConsoleOne and set up a drive mapping to it.

COMPLETE THE SERVER SETUP

Use the tasks in the Small Business Setup role in iManager to quickly configure the following:

- ♦ Internet connectivity via broadband methods, phone dial-up, and ISDN
- ♦ Basic DNS
- ♦ DHCP
- ♦ A basic setup of e-mail, instant messaging, collaboration, and common mailbox forwarding (POP Forwarding Agent)
- ♦ Printing, including local printers

Using these tasks lets you get your network set up quickly and gives you the flexibility to perform more advanced configurations with the additional utilities provided in NetWare and GroupWise. For details, see the online help for each task and the applicable section of *Installing Novell Small Business Suite Components* in the *Novell Small Business Suite 6.5 Overview and Installation Guide*.

If you installed the Novell Small Business Collaboration Server with Virtual Office, access the Virtual Office Web page from a browser to complete the final steps for setting up Virtual Office. To access it, open a browser and enter `http://server_ip_address` or `DNS_name` in the Address field.

SETTING UP ADDITIONAL WORKSTATIONS

Workstations can connect to the server using Novell Client software, Novell Native File Access Protocols, or remotely from the Internet using Virtual Private Networking.

For more information, see the [Novell Client online documentation \(http://www.novell.com/documentation/lg/noclienu/index.html\)](http://www.novell.com/documentation/lg/noclienu/index.html).

For more information about the Novell Native File Access Protocols, see the *NetWare 6.5 Native File Access Protocols Guide* (<http://www.novell.com/documentation/lg/nw65/native/data/hz8pck9v.html>).

For more information about the Virtual Private Networking, see [Virtual Private Networks Client in the Novell BorderManager 3.8 Installation and Administration Guide \(http://www.novell.com/documentation/lg/nbm38/inst_admin/data/front.html\)](http://www.novell.com/documentation/lg/nbm38/inst_admin/data/front.html).

Installing Additional Products in the Suite

INSTALLING GROUPWISE

We have provided an integrated method and the traditional method for installing GroupWise to the server. For the integrated method, select one of the Novell Small Business Collaboration Server options or select the required components in the Customized NetWare Server option. After the server installation is complete, access Novell iManager. Click Novell Small Business Setup Role > Setup GroupWise and Messenger, then follow the on screen prompts.

For complete instructions, see the *Novell Small Business Suite 6.5 Overview and Installation Guide*.

The integrated method can only be used for new installations. If you need to update GroupWise from a previous installation, you must use the traditional method and instructions provided in the [Update section of the GroupWise 6.5 Installation Guide \(http://www.novell.com/documentation/lg/gw65/gw65_install/data/a8t9nzp.html\)](http://www.novell.com/documentation/lg/gw65/gw65_install/data/a8t9nzp.html).

INSTALLING BORDERMANAGER

Novell BorderManager 3.8 includes a premier firewall, VPN, and proxy caching technologies that safeguard your network and help you build a secure identity management solution. With the powerful directory-integrated features in Novell BorderManager, you can monitor users' Internet activities and control their remote access to corporate resources.

The BorderManager online documentation refers to a Web download to obtain the installation software. The *Novell BorderManager 3.8* CD provided in the suite contains all the software required for an initial installation of BorderManager 3.8.

System Requirements and installation instructions are in *Installing BorderManager* in the *Novell Small Business Suite 6.5 Overview and Installation Guide*.

If you need some help understanding BorderManager and some tips and tricks for installation in addition to the Installation Guide, *A Beginner's Guide to BorderManager 3.8, Lite Version* is also available in the documents\craig johnson directory of the *Novell BorderManager 3.8* CD.

For complete information about setting up and managing these services, see the [BorderManager 3.8 online documentation \(http://www.novell.com/documentation/lg/nbm38/treetitl.html\)](http://www.novell.com/documentation/lg/nbm38/treetitl.html).

INSTALLING ZENWORKS FOR DESKTOPS

The ZENworks documentation references a Web download of the *ZENworks for Desktop 4.0.1* CD, a Companion CD, and a patch for NetWare 6.5 (zfd401_nw65.exe). The *ZENworks for Desktop 4.0.1* CD included in this suite contains the ZENworks for Desktop installation software and the patch software. The *ZENworks for Desktops Companion* CD also included in this suite contains Console 1.3.5.

For detailed information about the installation, planning, set up, and testing processes that Novell ZENworks for Desktops 4.0.1 customers will typically encounter while implementing this product, see the *ZENworks for Desktops 4 Installation Guide* (<http://www.novell.com/documentation/lg/zdpr/index.html>).

For information about upgrading ZENworks for Desktops 3.x to work in a ZENworks for Desktops 4.0.1 environment, see the *ZENworks for Desktops 4 Upgrade Guide* (<http://www.novell.com/documentation/lg/zdpr/index.html>).

For comprehensive, conceptual information that you can use as you configure and use ZENworks for Desktops 4.0.1 components in your production environment, see the *ZENworks for Desktops 4.0.1 Administration Guide* (<http://www.novell.com/documentation/lg/zdpr/index.html>).

For information about installing, configuring, and testing ZENworks for Desktops 4.0.1 in a Novell Cluster Services environment, see the *ZENworks for Desktops 4.0.1 Clustering Guide* (<http://www.novell.com/documentation/lg/zdpr/index.html>).

For troubleshooting strategies that you can use and error messages that might be displayed for problems that could occur as you use ZENworks for Desktops 4.0.1 in your production environment, see the *ZENworks for Desktops 4.0.1 Troubleshooting Guide* (<http://www.novell.com/documentation/lg/zdpr/index.html>).

SETTING UP CLUSTERING

Novell Small Business Suite includes a two-node version of Novell Cluster Services. For complete information about setting up and configuring additional resources to work with clustering, see the *Cluster Services for NetWare 6.5 online documentation* (<http://www.novell.com/documentation/lg/ncs65/treetitl.html>).

INSTALLING DIRXML STARTER PACK

Novell Small Business Suite includes DirXML Starter Pack software in the suite. For complete information about the installation, see *Installing DirXML Starter Pack* in *Novell Small Business Suite 6.5 Readme*.


INSTALLING NTERPRISE BRANCH OFFICE

Novell Small Business Suite includes Nterprise Branch Office. For complete installation instructions, see the [Nterprise Branch Office \(v 1.0.2\) online documentation \(http://www.novell.com/documentation/lg/nbo/treetitl.html\)](http://www.novell.com/documentation/lg/nbo/treetitl.html)

Accessing Administration Utilities

Novell Small Business Suite includes several administration utilities that let you manage everything in your network from configuring and managing eDirectory to setting up network services and open source software. The following table shows includes a list of some of the most common utilities that you might need to access. For additional details, see [Administration Utilities Overview](#) in the *Novell Small Business Suite 6.5 Overview and Installation Guide*.

Utility	Description	How to Access
iManager	Browser-based network management application for managing the server and network services, eDirectory tree and eDirectory objects.	Open a Web browser and enter: <code>http:// server_ip_address or DNS_name/nps/iManager.html</code>
Welcome Web Site	Browser-based application for accessing information about products distributed with NetWare 6.5 and launching installed applications.	Open a Web browser and enter: <code>https:// server_ip_address or DNS_name:2200</code>
NetWare Remote Manager	Browser-based application for managing NetWare servers from a workstation or a the server console.	Open a Web browser and enter: <code>https:// server_ip_address or DNS_name:8009</code>
ConsoleOne	Java*-based application for managing the network and its resources, eDirectory tree and eDirectory objects.	At a workstation, map a drive letter to the server and run consoleone.exe from <code>sys:\public\mgmt\consoleone\1.2\bin</code> directory.
NetWare Administrator	Windows-based application for managing the network and its resources, eDirectory tree, and eDirectory objects. This utility is required only when managing Proxy Caching services in BorderManager 3.8	At a Windows workstation, map a drive to <code>sys:public</code> and run <code>sys\public\win32\nwadmn32.exe</code>

Utility	Description	How to Access
RConsoleJ	Java-based application for accessing the server remotely and running utilities from a workstation or the server console.	At a workstation, map a drive letter to the server and run rconj.exe from sys:\public\mgmt\consoleone\1.2 directory.
OpenSSH client such a PuTTY, MineTerm, Absolute Telnet, Red-Hat* Linux	OpenSource shell used to access the server and run ssh commands to access files, or access the server and run commands remotely. Can run from the server console to access other servers or run from a workstation to access other servers or workstations.	Product must be installed on the server, then load sshd.nlm on the server. Download client application. Change the Window Row setting from the default to greater than 25. Connect to the server based on the client downloaded.
Apache Manager	Browser-based application used for configuring the Apache Web server. It provides a graphical user interface to most of the Apache directives, making it easier to quickly (and more accurately) configure and manage Apache's behavior and performance. Apache Manager also lets you manage multiple installations of Apache in your network, regardless of what other platforms they are running on.	<ol style="list-style-type: none"> 1. Open a Web browser and enter: <code>http://server_ip_address or DNS_name:2200</code> 2. When prompted, enter the username and password for user Admin and Login. 3. In the left frame of the Welcome Web site home page, click the  icon next to Open Source. 4. Click Apache 2.0. 5. Under Apache 2.0 Links, click either Administer Single Apache Server or Administer Multiple Apache Servers, as applicable.
Internetworking Configuration	Server console application used to manage network and server TCP/IP communications, manage IP addresses, and bind boards.	Load inetcfg.nlm at the System Console prompt, access the server console, then toggle to the screen.
NSS Management Utility	Server console application used to manage the logical file system.	Load nssmu.nlm at the System Console prompt, access the server console, then toggle to the screen
NetWare Configuration	Server console application used to install or upgrade products to the server.	Load nwconfig.nlm at the System Console prompt, access the server console, toggle to the screen.

Small Business Server Configuration Worksheet

Print the PDF version of this worksheet and use it to gather information that you might need as you perform each of these setups.

SERVER INSTALLATION

Network Board 1 Properties (Needed only if drivers are not included in the installation) Name: Interrupt: Port address:	
Network Board 2 Properties (Installing a second board is optional) Name: Interrupt: Port address:	
Server name:	
IP Protocol Information IP address: Subnet mask: Router (gateway):	
DNS Host name:	
Domain name:	
Name server address 1:	
Name server address 2:	
Name server address 3:	
Tree name: (If creating a new tree)	
Context for Server object:	
Name for Admin user (default Admin):	

Context for user Admin: (defaulted to the same context for the server)	
Password for Admin user:	
LDAP Ports (can only change defaults using Manual installation) Clear Text Port (default 389): SSL/TLS Port (default 636):	
DNS/DHCP (will use defaults from previous entries) DNS/DHCP Locator Object NDS Context: DNS/DHCP Group Object NDS Context: RootSrvr Zone NDS Context:	
iFolder Server Options (required only when installing iFolder, will use defaults from previous entries) LDAP host name or IP address: LDAP Port 389 Clear Text, 636 (SSL): LDAP context for admins: iFolder server host name or IP address: iFolder Admin names (admin): User database path (sys: is default; a volume other than sys: is recommended):	
MySQL Database Options (required only when installing MySQL) Data directory: (default sys:/mysql/data) Root password:	
exteNd Application Server Details (required only when installing exteNd) Admin name: Admin password: HTTP Port (default 83):	

<p>exteNd Application Server Database Options (required only when installing exteNd)</p> <p>MySQL Database Host (default, localhost):</p> <p>Admin password:</p> <p>Port (default 3306):</p> <p>DB Username (default, appserver):</p> <p>DB Password:</p> <p>SilverMaster Name (default SilverMaster50):</p>	
<p>Novell Nsure Audit Component Selections (required only when installing Nsure)</p> <p>Secure logging server Address (default, localhost):</p>	
<p>Novell Nsure Audit Component Database Options (required only when installing Nsure)</p> <p>MySQL Database Host (default, localhost):</p> <p>Admin password:</p> <p>Port (default 3306):</p> <p>DB Username (default, audituser):</p> <p>DB Password (default, audituser):</p> <p>Database name (default, naudit):</p> <p>Table name (default, log)</p>	
<p>NetStorage Install (required only when installing NetStorage)</p> <p>DNS name or IP address of Primary eDirectory Server and Context:</p> <p>DNS name or IP address of Alternate eDirectory Server and Context (optional):</p> <p>DNS name or IP address of Alternate eDirectory Server and Context (optional):</p> <p>DNS name or IP address of iFolder server (optional):</p> <p>iFolder port (default 80):</p>	

DIAL-UP INTERNET CONNECTIVITY

Modem type (Hayes will fit a large number of compatible modems):	
Telephone number:	
Username:	
Password:	
IP address/mask (if static):	
Default domain name:	
Name server address 1:	
Name server address 2 (optional):	
Name server address 3 (optional):	

ISDN INTERNET CONNECTIVITY

Device type:	
Protocol (if applicable):	
ISDN and SPID phone number 1 (if applicable): NOTE: A SPID (Service Profile Identifier) is a number assigned by a phone company to a terminal on an ISDN B-Channel.	
ISDN and SPID phone number 2 (if applicable):	
Telephone number:	
Username:	
Password:	
IP address/mask (if static):	
Default domain name:	
Name server address 1:	
Name server address 2 (optional):	
Name server address 3 (optional):	

DSL/CABLE/OTHER INTERNET CONNECTIVITY

A modem/router that converts to Ethernet:	
Ethernet interface in the server connected to the modem/router to the Internet:	
Know which card/board interface:	
IP address must be static, but possibly non-public:	
IP address/mask:	
Default gateway:	
Default domain name:	
Name server address 1:	
Name server address 2 (optional):	
Name server address 3 (optional):	

DNS

TIP: If you run connectivity first, almost everything else is defaulted.	
Internet domain name:	
Other internal names of your server:	
Name server address 1:	
Name server address 2 (optional):	
Name server address 3 (optional):	

DHCP

TIP: If you run DNS first, almost everything else is defaulted.	
Ethernet interface (subnet) that corresponds to the workstations:	
Subnet address, mask:	
Range of address you want workstation to use:	
Default gateway:	
Other internal names of your server:	
Name server address 1:	
Name server address 2 (optional):	
Name server address 3 (optional):	

GROUPWISE AND MESSENGER

eDirectory tree where GroupWise objects will be created (provided by default):	
eDirectory admin username and password for creating and editing GroupWise objects:	
Server and volume where GroupWise domain and post office will be created (defaults to volume Data):	
Internet domain name for your system (if you are installing the Internet Agent):	

PRINTING

Printer attached to the server parallel port or a network-attached printer:	
Printer's IP address (if network-attached printers):	
Printer model to associate the correct print drivers:	

BORDERMANAGER

Location of license diskettes or path to the license file:	
Public and private interfaces and their IP address bindings:	
Domain Name System (DNS) domain name:	
IP addresses for up to three DNS name servers on the network:	
Domain name for Mail Proxy and whether you want to proxy internal mail server or external mail server or both:	
Server certificates (if secure LDAP is to be used for schema extension):	
Default gateway:	
If installing VPN Services: Server certificate to be used for the VPN server: Trusted Root Certificate name: Trusted Root Object names:	

Technical Support

Technical support for Novell Small Business Suite 6.5 includes five free incidents valid for 60 calendar days. This free support is available to both Novell customers and Novell resellers during normal business hours. The 60-day timer starts from the first support call. Any incidents of the five not used within the 60 days will expire. The incidents are intended to cover general installation and configuration issues for all the products and components included in the suite.

Support beyond the levels indicated above will incur support charges. For information on technical support options with Novell including Premium Service, visit the Novell support [Web site \(http://support.novell.com\)](http://support.novell.com).

When you call for this technical support, you need to provide your product serial number. This number is printed on the *License* diskette; or if downloaded, it is the license filename.

This support applies only to the Novell Small Business Suite 6.5 and the Novell Small Business Suite 6.5 Expansion pack. It does not apply to the Novell Small Business Suite Starter Pack.

Contact Novell Technical Support:

- ♦ U.S. and Canada: 1-800-858-4000
- ♦ Latin America
 - ♦ Argentina: 0-800-888-668355 (0-800-888-novell), 800-228-8478, and by e-mail soporte@novell.com
 - ♦ Belize: 800-321-2356
 - ♦ Bolivia: 800-321-2296
 - ♦ Brazil: 800-858-4000
 - ♦ Chile: 800-858-4000
 - ♦ Columbia: 800-858-4000
 - ♦ Costa Rica: 800-858-4000
 - ♦ Ecuador: 800-321-2297
 - ♦ El Salvador: 800-633-4175
 - ♦ Guatemala: 800-858-4000
 - ♦ Guyana: 800-321-2364
 - ♦ Honduras: 800-321-2312

- ◆ Mexico: 800-858-4000
- ◆ Nicaragua: 800-321-2317
- ◆ Paraguay: 800-228-2832
- ◆ Peru: 800-633-4179
- ◆ Uruguay: 800-633-4185
- ◆ All other Spanish-speaking countries 1-800-858-4000 or USA Direct 801-861-4000
- ◆ APAC:
 - ◆ Novell Premium and Channel partners: use your assigned toll numbers
 - ◆ All others: + 61 2 9925-3133
- ◆ Europe:
 - ◆ Austria +49 211 5632 1800
 - ◆ Belgium +31 10 286 47 41
 - ◆ Denmark +31 10 286 47 42
 - ◆ France +31 10 286 47 43
 - ◆ Germany +49 211 5632 1800
 - ◆ Italy +31 10 286 47 44
 - ◆ Netherlands +31 10 286 47 41
 - ◆ Norway +31 10 286 47 42
 - ◆ Sweden +31 10 286 47 42
 - ◆ Switzerland +49 211 5632 1800
 - ◆ Spain +31 10 286 47 45
 - ◆ U.K. +31 10 286 47 46
 - ◆ For any country not listed above, call the U.K. number
 - ◆ Fax +31 10 286 43 33