



## Automatic Workstation Import

This section provides information for ZENworks<sup>®</sup> for Desktops (ZfD) Automatic Workstation Import and Removal:

- ◆ [Chapter 1, “Workstation Registration Files,” on page 19.](#)

For information on deploying Automatic Workstation Import or Removal, see [Upgrading from an Older Version of ZfD in Deployment.](#)



# 1

## Workstation Registration Files

Workstation registration in ZfD involves three executable files: WSREG32.EXE, WSREG.DLL, and WSREG32R.DLL.

The following sections provide information on these files:

- ♦ “Registration File Functions” on page 19
- ♦ “Registration File Locations” on page 19
- ♦ “WSREG.DLL Usage” on page 20

### Registration File Functions

Following are the functions of the registration files:

**WSREG32.EXE:** If executed, calls WSREG.DLL

**WSREG.DLL:** Performs workstation registration tasks.

**WSREG32R.DLL:** Contains strings used by WSREG.DLL. These strings are available for language translation.

### Registration File Locations

Following are the locations of the registration files (by machine):

**NetWare Server:**

*\\server\_name\SYS\PUBLIC\WSREG32.EXE*

*\\server\_name\SYS\PUBLIC\WSREG.DLL*

*\\server\_name\SYS\PUBLIC\NLS\ENGLISH\WSREG32R.DLL*

**Windows 95/98 Client Workstation:**

*drive:\Windows\_95/98\_directory\SYSTEM\WSREG32.EXE*

*drive:\Windows\_95/98\_directory\SYSTEM\WSREG.DLL*

*drive:\Windows\_95/98\_directory\SYSTEM\NLS\ENGLISH\WSREG32R.DLL*

**Windows NT/2000 Client Workstation:**

*drive:\Windows\_NT/2000\_directory\SYSTEM32\WSREG32.EXE*

*drive:\Windows\_NT/2000\_directory\SYSTEM32\WSREG.DLL*

*drive:\Windows\_NT/2000\_directory\SYSTEM32\NLS\ENGLISH\WSREG32R.DLL*

## WSREG.DLL Usage

In addition to being called by executing WSREG32.EXE, WSREG.DLL can be called by Workstation Manager's Scheduler when when one of the following events occurs:

- workstation startup
- user login
- user logout
- registration service shutdown

The sequence of file calls when one of the above events is detected are:

**Windows NT/2000:** WM.EXE > WMRUNDLL.EXE > WSREG.DLL.

**Windows 95/98:** WM95.EXE > WM95SAST.EXE > WSREG.DLL.