Novell Vibe Add-In Readme

March 7, 2013

Novell_®

1 Product Overview

The Novell Vibe Add-in enables you to work with Microsoft Office documents on the Vibe site without ever leaving Microsoft Office. You can easily browse to a document that is located on the Vibe site, open the document, edit it, then save it back to the Vibe site, directly from Microsoft Office.

You can work directly from Microsoft Word, Excel, or PowerPoint documents.

2 Vibe Add-In System Requirements

- Section 2.1, "Office Requirements," on page 1
- Section 2.2, "Operating System Requirements," on page 1
- Section 2.3, "Vibe Requirements," on page 1

2.1 Office Requirements

The Novell Vibe Add-in is supported with the following versions of Microsoft Office:

- Microsoft Office 2013, with the latest support pack
- Microsoft Office 2010, with the latest support pack
- Microsoft Office 2007, with the latest support pack

2.2 Operating System Requirements

The Novell Vibe Add-in is supported for the following versions of the Windows operating system:

- Windows XP SP3 32-bit or later
- Windows Vista SP2 32-bit or 64-bit or later
- Windows 7 SP1 32-bit or 64-bit or later
- Windows 8 32-bit or 64-bit or later

2.3 Vibe Requirements

The Vibe system that you connect to must be Novell Vibe 3.3 or later.

3 Vibe Add-In Issues

- Section 3.1, "The Installer Does Not Automatically Restart after .NET Framework Is Installed," on page 2
- Section 3.2, "Embedded Images in Entry Descriptions Are Not Displayed," on page 2

- Section 3.3, "Vibe Add-In Does Not Work When the Vibe Server Is Configured with Windows Authentication," on page 2
- Section 3.4, "Login Information for the Vibe Desktop Application Is Lost," on page 2

3.1 The Installer Does Not Automatically Restart after .NET Framework Is Installed

If the .NET Framework is not already installed on your workstation, the Vibe Add-in installation program installs it for you. Installation of the .NET Framework requires that your workstation is rebooted. After your workstation reboots, you need to manually restart the Vibe Add-in installation program:

- 1 Navigate to the location where the VibeAddinSetup.exe file was downloaded.
- **2** Run the VibeAddinSetup.exe file.

3.2 Embedded Images in Entry Descriptions Are Not Displayed

Images that are embedded in the *Description* section of an entry are displayed as broken when viewing the entry from Microsoft Office with the Vibe Add-in. However, you can still edit the text of the entry description from Microsoft Office with the Vibe Add-in.

3.3 Vibe Add-In Does Not Work When the Vibe Server Is Configured with Windows Authentication

If your Vibe server is configured with Windows Authentication, the Vibe Add-in cannot open or edit files on your Vibe site because of a port conflict.

For information about how to work around this issue, see "Configuring Integrated Windows Authentication to Support Vibe Desktop and the Vibe Add-In" in the *Novell Vibe 3.3 Administration Guide*.

For more information about configuring Windows Authentication for your Vibe site, see "Configuring Single Sign-On with Internet Information Services for Windows" in the *Novell Vibe 3.3 Installation Guide*.

3.4 Login Information for the Vibe Desktop Application Is Lost

If you are using Vibe Desktop in conjunction with the Vibe Add-in, login information for Vibe Desktop is lost if you configure your account information in the Vibe Add-in to use the system proxy configuration (by selecting *Use system proxy configuration*), then later configure the account to not use the system proxy configuration.

4 Vibe Add-In Documentation

For information about how to install, configure, and use the Novell Vibe Add-in, see the Novell Vibe Add-In Quick Start (http://www.novell.com/documentation/vibe33/vibe33_qs_office/data/vibe33_qs_office.html).

For information on how to enable users to edit Vibe documents with the Novell Vibe Add-in, see "Configuring Vibe Desktop and the Microsoft Office Add-In" in the *Novell Vibe 3.3 Administration Guide*.

5 Legal Notices

Novell, Inc. makes no representations or warranties with respect to the contents or use of this documentation, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. reserves the right to revise this publication and to make changes to its content, at any time, without obligation to notify any person or entity of such revisions or changes.

Further, Novell, Inc. makes no representations or warranties with respect to any software, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. reserves the right to make changes to any and all parts of Novell software, at any time, without any obligation to notify any person or entity of such changes.

Any products or technical information provided under this Agreement may be subject to U.S. export controls and the trade laws of other countries. You agree to comply with all export control regulations and to obtain any required licenses or classification to export, re-export, or import deliverables. You agree not to export or re-export to entities on the current U.S. export exclusion lists or to any embargoed or terrorist countries as specified in the U.S. export laws. You agree to not use deliverables for prohibited nuclear, missile, or chemical biological weaponry end uses. Please refer to the Novell International Trade Services Web page (http://www.novell.com/info/exports/) for more information on exporting Novell software. Novell assumes no responsibility for your failure to obtain any necessary export approvals.

Copyright © 2011-2013 Novell, Inc. All rights reserved. No part of this publication may be reproduced, photocopied, stored on a retrieval system, or transmitted without the express written consent of the publisher.

For Novell trademarks, see the Novell Trademark and Service Mark list (http://www.novell.com/ company/legal/trademarks/tmlist.html).

All third-party trademarks are the property of their respective owners.