Novell GroupWise Mobile Server 3 for Linux, Powered by Intellisync

April 14, 2009

1 Overview

With Novell[®] GroupWise[®] Mobile Server for Linux, you can synchronize e-mail messages and other personal information manager (PIM) data from your GroupWise mailbox to supported mobile devices.

GroupWise Mobile Server for Linux includes the following modules from Intellisync* Mobile Suite:

- Intellisync Wireless Email with the GroupWise Connector
- Intellisync Mobile Gateway
- Intellisync Secure Gateway
- Synchronization software for supported devices

Enhancements for GroupWise Mobile Server 3 include:

- Substantially faster push of data to your device
- Significantly increased battery life

Some Intellisync Mobile Suite modules are not included in GroupWise Mobile Server 3. For supported devices and module details, see the *GroupWise Mobile Server 3 Getting Started Guide* on the GroupWise Mobility Documentation Web site (http://www.novell.com/documentation/gwmobility/index.html).

2 Installing GroupWise Mobile Server for Linux

- Section 2.1, "Installing GroupWise Mobile Server," on page 1
- Section 2.2, "Installing the Palm OS Patch," on page 2
- Section 2.3, "Installing Symbian Client Patch," on page 2

2.1 Installing GroupWise Mobile Server

1 If the server where you are planning to install GroupWise Mobile Server has Apache* and Tomcat running on it, you must stop them before installing GroupWise Mobile Server.

The Secure Gateway Module of GroupWise Mobile Server automatically uses the same port numbers that Apache is configured with.. Initially, the Secure Gateway is installed on the same server where you perform the GroupWise Mobile Server installation, but it can be installed later on additional Linux* servers. For detailed installation instructions, see the *GroupWise Mobile Server 3 Getting Started Guide* and the *Intellisync Mobile Suite Installation Guide* on the GroupWise Mobile Server 3 Documentation Web site (http://www.novell.com/documentation/groupwise_mobile_3).

If you want to continue to run Apache and Tomcat on the same server where you are installing GroupWise Mobile Server, some post-installation reconfiguration is required. For detailed installation instructions, see the *GroupWise Mobile Server 3 Getting Started Guide* and the *Intellisync Mobile Suite Installation Guide* on the GroupWise Mobile Server 3 Documentation Web site (http://www.novell.com/documentation/groupwise_mobile_3).

- 2 Download the GroupWise Mobile Server 3.0.1 for Linux compressed tar file (gms301_linux.tar.gz) from the Novell Downloads Web site (http://www.novell.com/ download) to a temporary directory on your Linux server.
- **3** In a terminal window, change to the temporary directory, then use the following command to extract the gms301_linux.tar.gz file into the temporary directory:

```
tar -xvzf gms301_linux.tar.gz
```

- **4** Become root by entering su and the root password.
- **5** Change to the gms301_linux directory:

cd gms301_linux

6 To start the installer, enter the following command:

sh ims.bin

7 Follow the on-screen instructions to install GroupWise Mobile Server 3 for Linux.

For detailed installation instructions, see the *GroupWise Mobile Server 3 Getting Started Guide* and the *Intellisync Mobile Suite Installation Guide* on the GroupWise Mobile Server 3 Documentation Web site (http://www.novell.com/documentation/groupwise mobile 3).

2.2 Installing the Palm OS Patch

- **1** If the server where you are planning to install the Palm* OS* Patch has Apache and Tomcat running on it, you must stop them before installing the Palm OS Patch.
- 2 Create a backup of opt/ims/lib/pim/pim.jar by copying the file to another location on your server.
- **3** In the temporary directory where you downloaded GroupWise Mobile Server 3.0.1, change to the PalmOSClientPatch/lib/pim directory.
- **4** Copy the pim.jar file to the /opt/ims/lib/pim directory on your server.

2.3 Installing Symbian Client Patch

- **1** If the server where you are planning to install the Symbian* Client Patch has Apache and Tomcat running on it, you must stop them before installing the Symbian Client Patch.
- 2 In the /opt/ims/clientinstalls/SyncClient directory create a backup of the *.xml files and the Symbian60V30, Symbian60V31, and Symbian60V32 directories.
- **3** In the temporary directory where you downloaded GroupWise Mobile Server 3.0.1, change to the SymbianClientPatch/ClientInstalls/SyncClient directory.
- 4 Copy the *.xml files and the Symbian60V30, Symbian60V31, and Symbian60V32 directories to the /opt/ims/clientinstalls/SyncClient directory on your server.

3 Client Installation Instructions for Mobile Devices

For information about installing the GroupWise Mobile Server client software on mobile devices, see the device-specific *Client Guides* on the GroupWise Mobile Server 3 Documentation Web site (http://www.novell.com/documentation/groupwise_mobile_3). Use the GroupWise Mobile Server machine URL and your GroupWise username and password to log in from your mobile device to install the client software.

4 Known Issues

- Section 4.1, "Intellisync Mobile Suite Issues," on page 3
- Section 4.2, "Duplicate Notes when Resetting an Account on a Symbian Device," on page 3
- Section 4.3, "What To Sync Window on WinMobile Devices Does Not Display," on page 3

4.1 Intellisync Mobile Suite Issues

For a list of known issues and fixes in Intellisync Mobile Suite, see the *Intellisync Mobile Server Release Notes* on the GroupWise Mobile Server 3 Documentation Web site (http://www.novell.com/documentation/groupwise_mobile_3).

4.2 Duplicate Notes when Resetting an Account on a Symbian Device

When a user already has previous information syncronized with their device selecting the *Reset Account* option may cause the user Notes to duplicate.

4.3 What To Sync Window on WinMobile Devices Does Not Display

For all WinMobile devices, when you select *What To Sync* in *Intellisync* > *Settings* on your mobile device, no options are displayed. Select *Done* to display a screen where you can synchronize according to current settings. Select *Settings* to display a screen where you can change synchronization settings.

The missing settings are still accessible from the Web PIM and should be used if the settings need to be changed. For more information on using the Web PIM, see the *GroupWise Mobile Server 3 Getting Started Guide* on the GroupWise Mobility Documentation Web site (http://www.novell.com/documentation/gwmobility/index.html).

5 Documentation

The GroupWise Mobile Server 3 for Linux documentation is available at the GroupWise Mobile Server 3 Documentation Web site (http://www.novell.com/documentation/groupwise_mobile_3).

The following documentation is provided by Novell:

GroupWise Mobile Server 3 Product Readme

- GroupWise Mobile Server 3 Support Pack Readmes
- GroupWise Mobile Server 3 Getting Started Guide

The following Linux server documentation is provided by Nokia*:

- Intellisync Mobile Suite Release Notes
- Intellisync Mobile Suite Installation Checklists
- Intellisync Mobile Suite Linux Installation Guide
- Intellisync Mobile Suite Linux Administrator's Guide
- Intellisync Mobile Suite Windows to Linux Server Migration Guide
- Intellisync Mobile Suite Secure Gateway Administrator's Guide
- Online help for the Admin Console

The following client documentation is provided by Nokia:

- Nokia E-Mail Client Release Notes
- Device-specific *Client Guides*
- On-device help for client users

6 Documentation Conventions

In this documentation, a greater-than symbol (>) is used to separate actions within a step and items in a cross-reference path.

A trademark symbol ($^{\mathbb{R}}$, $^{\text{TM}}$, etc.) denotes a Novell trademark; an asterisk (*) denotes a third-party trademark

7 Legal Notices

Novell, Inc. makes no representations or warranties with respect to the contents or use of this documentation, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. reserves the right to revise this publication and to make changes to its content, at any time, without obligation to notify any person or entity of such revisions or changes.

Further, Novell, Inc. makes no representations or warranties with respect to any software, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. reserves the right to make changes to any and all parts of Novell software, at any time, without any obligation to notify any person or entity of such changes.

Any products or technical information provided under this Agreement may be subject to U.S. export controls and the trade laws of other countries. You agree to comply with all export control regulations and to obtain any required licenses or classification to export, re-export, or import deliverables. You agree not to export or re-export to entities on the current U.S. export exclusion lists or to any embargoed or terrorist countries as specified in the U.S. export laws. You agree to not use deliverables for prohibited nuclear, missile, or chemical biological weaponry end uses. Please refer to the Novell International Trade Services Web page (http://www.novell.com/info/exports/) for more information on exporting Novell software. Novell assumes no responsibility for your failure to obtain any necessary export approvals.

Copyright © 2009 Novell, Inc. All rights reserved. No part of this publication may be reproduced, photocopied, stored on a retrieval system, or transmitted without the express written consent of the publisher.

Novell, Inc. has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more of the U.S. patents listed on the Novell Legal Patents Web page (http://www.novell.com/company/legal/patents/) and one or more additional patents or pending patent applications in the U.S. and in other countries.

For Novell trademarks, see the Novell Trademark and Service Mark list (http://www.novell.com/ company/legal/trademarks/tmlist.html).

All third-party trademarks are the property of their respective owners.