

Novell Client Firewall



2.0

www.novell.com

QUICK START

Installing Novell Client Firewall

This document provides instructions for installing Novell® Client Firewall (NCF).

SUPPORTED PLATFORMS

- ♦ Windows* 2000 Professional
- ♦ Windows XP
- ♦ Windows XP Home edition
- ♦ Windows Me
- ♦ Windows NT Support Pack 6

MINIMUM SYSTEM REQUIREMENTS

- ♦ 166 MHz Intel* Pentium* processor or compatible CPU
- ♦ 128 MB of RAM
- ♦ 512 MB of hard disk space

NOTE: There is no special network card, modem or special configuration settings of these boards needed for the normal operation of the software.

BEFORE YOU START

Before you install and configure NCF, you must

- ♦ Have administrator rights.
- ♦ Uninstall any other firewall software on your computer and reboot before installing NCF.
- ♦ Close all open applications.

INSTALLING NCF

- 1 At the root of the Novell BorderManager 3.8 product CD, go to CL_INST\NCF, and copy NCFInstall.exe to the local drive of the machine where you want to install the Novell Client Firewall.
- 2 Double-click NCFInstall.exe.

Novell®

This invokes the NCF setup program.

If the setup program has detected a previous installation of NCF on your system, you are prompted to discontinue the setup program because the setup does not uninstall the previous installation present on your system. You need to manually uninstall the previous installation and run the NCF setup program again.

- 3 Select the language for the setup program, then click OK.

The Welcome screen appears.

- 4 Click Next to continue installation.

- 5 Read the license agreement and click Yes to accept it.

- 6 Specify the path where you want to install the files, then click Next.

- 7 Specify the program folder name, then click Next.

The setup program installs NCF on your system.

- 8 Do one of the following:

- If you want to automatically configure NCF rules for applications and network settings, click Next and continue with Step 9.
- If you do not want to auto-configure the NCF rules, click Skip and go to Step 11.

NOTE: The Back button is disabled in this screen.

- 9 Complete the applications rule configuration.

9a Click Details and view/edit the applications list.

9b Keep the option Apply the auto-configured rules checked, then click Next.

- 10 Complete the network configuration.

10a Click Details and view/edit the network settings.

10b Keep the option Apply the auto-configured rules checked, then click Next.

- 11 To view the Readme, click Next.

- 12 Scroll down to view the complete Readme, then click File > Exit.

- 13 Check the Yes, I want to restart my computer now option, then click OK.

NOTE: NCF should be up and running when you restart your system. The system tray should show NCF icon. If you have chosen auto-configured rules during installation, services or applications detected by NCF during installation will be allowed. For any new traffic, NCF pops up a dialog box (as no rule is defined) asking you to select appropriate action for that traffic. Refer Novell Client Firewall 2.0 User Guide for details.