GroupWise Async Gateway 2.0

June 15, 2004

1.0 Product Overview

GroupWise[®] Async Gateway 2.0 provides the following improvements over the previous version:

- The Async Gateway has been updated to match GroupWise 6.x functionality in several areas.
- The Async Gateway snap-in to ConsoleOne[®] works with the GroupWise 6.5 snap-ins. In addition, the Async Gateway Installation program lets you select the ConsoleOne snap-in to match the specific version of the GroupWise snap-ins.
- The Windows* Async Gateway can run as a Windows service as well as an application.
- SNMP is supported for the NetWare[®] Async Gateway, so that the Async Gateway can be monitored from SNMP management and monitoring programs.
- A Web console is provided, so that the Async Gateway can be monitored from any location where you have access to a Web browser and the Internet.
- The Web Console Log Files page now includes the capability of searching multiple log files for a specified string.

2.0 Installation Instructions

- **1** Make sure that the MTA for the domain where you want to install the Async Gateway is running.
- **2** Run the self-extracting executable setupasy.exe, click Yes to confirm that you want to install the gateway, then click Next to continue.
- **3** Click Accept to accept the license agreement.

The default installation option, GroupWise Async Gateway, includes installation of the Gateway Administrator snap-in to ConsoleOne.

- 4 Click Next to continue.
- **5** Follow the on-screen instructions to complete the installation.
- 6 If you are updating an existing installation of the Async Gateway, check in ConsoleOne to make sure that the Database Version field on the Async Gateway Identification page is set to 4.x.

For detailed installation instructions, see the *GroupWise Async Gateway Installation and Administration Guide* on the GroupWise 6.5 Documentation page (http://www.novell.com/ documentation/gw65).

3.0 Changes Since the Last Release

- Unconfigured ports no longer display garbage characters.
- Fixed several abends and memory leaks.

4.0 Additional Documentation

In addition to this Readme, see the *GroupWise Async Gateway Installation and Administration Guide* on the GroupWise 6.5 Documentation (http://www.novell.com/documentation/gw65) page for complete information about the Async Gateway.

5.0 Documentation Conventions

In this documentation, a greater-than symbol (>) is used to separate actions within a step and items in a cross-reference path.

A trademark symbol ([®], [™], etc.) denotes a Novell trademark; an asterisk (*) denotes a third-party trademark.

6.0 Legal Notices

Novell, Inc. makes no representations or warranties with respect to the contents or use of this documentation, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. reserves the right to revise this publication and to make changes to its content, at any time, without obligation to notify any person or entity of such revisions or changes.

Further, Novell, Inc. makes no representations or warranties with respect to any software, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. reserves the right to make changes to any and all parts of Novell software, at any time, without any obligation to notify any person or entity of such changes.

You may not export or re-export this product in violation of any applicable laws or regulations including, without limitation, U.S. export regulations or the laws of the country in which you reside.

Copyright © 2004 Novell, Inc. All rights reserved. No part of this publication may be reproduced, photocopied, stored on a retrieval system, or transmitted without the express written consent of the publisher.

ConsoleOne, NetWare, Novell, and GroupWise are registered trademarks of Novell, Inc. in the United States and other countries.

All third-party trademarks are the property of their respective owners.