
GroupWise 2014 R2

Installation Guide

June 2016

Legal Notices

For information about legal notices, trademarks, disclaimers, warranties, export and other use restrictions, U.S. Government rights, patent policy, and FIPS compliance, see <https://www.novell.com/company/legal/>.

Copyright © 2016 Novell, Inc, a Micro Focus company. All Rights Reserved.

Contents

About This Guide	11
Part I GroupWise Product Overview	13
1 GroupWise Features and Benefits	15
1.1 Essential Communication and Collaboration Services	15
1.2 Available Anytime	16
1.3 Accessible Anywhere	16
1.4 Always Secure	17
1.5 Competitive Performance	17
1.6 Evaluation Version Available	17
2 GroupWise Components	19
3 GroupWise System Architecture	21
3.1 Agent Architecture	21
3.2 Administration Service Architecture	22
3.3 WebAccess Architecture	22
3.4 Calendar Publishing Host Architecture	23
3.5 Monitor Architecture	23
Part II GroupWise System Requirements	25
4 GroupWise Administration Requirements	27
4.1 Hardware and Operating System Requirements	27
4.2 Directory Requirements	28
4.3 Web Server Requirements	28
4.4 Web Browser Requirements Administrators	29
4.5 Internet Agent Functional Requirements	29
4.6 Sample Agent Memory Requirements	30
4.6.1 Sample POA Memory Requirements Based on Post Office Size	30
4.6.2 Sample Memory Requirements for Other GroupWise Agents and Applications	30
5 GroupWise User Requirements	31
5.1 GroupWise Client User Requirements	31
5.2 GroupWise WebAccess User Requirements	31
5.3 GroupWise WebAccess Mobile User Requirements	31
6 Supported Environments	33
6.1 IPv6 Support	33
6.2 Clustering Support	33
6.3 Xen Virtualization Support	33

6.4	VMware Support	33
6.5	Hyper-V / Cloud Server Support	34
6.6	Citrix Support	34
6.7	Domain Services for Windows Support	34
6.8	File System Support	34
Part III GroupWise System Creation		35
7	GroupWise System Overview	37
7.1	Simple GroupWise System	37
7.2	Typical GroupWise System	37
7.3	GroupWise Users	38
7.4	GroupWise Agents	38
8	Planning Your GroupWise System	41
8.1	Planning GroupWise System Information	41
8.1.1	GroupWise System Name	41
8.1.2	GroupWise Internet Domain Name	42
8.2	Planning a Domain	42
8.2.1	Domain Server	42
8.2.2	Domain Name	43
8.2.3	Domain Folder	43
8.2.4	Domain Language	43
8.2.5	Domain Time Zone	44
8.2.6	Domain Link (Secondary Domain Only)	44
8.2.7	Agents for the Domain	44
8.2.8	Administrator Access for Domain Creation	45
8.3	Planning a Post Office	47
8.3.1	Post Office Server	47
8.3.2	Post Office Name	47
8.3.3	Post Office Folder	47
8.3.4	Post Office Language	48
8.3.5	Post Office Time Zone	48
8.3.6	Agents in the Post Office	49
8.3.7	Administrator Access for Post Office Creation	50
8.4	Planning Users	50
8.4.1	Manually Created Users	51
8.4.2	Imported Users	51
8.5	GroupWise System Worksheets	51
8.5.1	Simple GroupWise System Worksheet	52
8.5.2	Primary Domain Worksheet	54
8.5.3	Secondary Domain Worksheet	54
8.5.4	Post Office Worksheet	55
9	Installing the GroupWise Server Software	59
9.1	Linux: Installing the GroupWise Server Software	59
9.1.1	Preparing the Linux Server for Your GroupWise System	59
9.1.2	Running the Linux GroupWise Installation Wizard	59
9.2	Windows: Installing the GroupWise Server Software	60
9.2.1	Preparing the Windows Server	60
9.2.2	Running the Windows GroupWise Installation Wizard	60

10 Creating a Simple GroupWise System	63
11 Creating a Typical GroupWise System	65
11.1 Creating the Primary Domain	65
11.2 Adding a Secondary Domain	66
11.3 Adding a Post Office	67
11.4 Handling an Installation Timeout	68
11.5 Changing the Authentication Mode for the Installation Console	69
12 Adding Users to Your GroupWise System	71
12.1 Manually Adding Users to the Internal GroupWise Directory	71
12.2 Importing Users from an LDAP Directory	71
12.2.1 Providing LDAP Directory Information	71
12.2.2 Importing Users	72
12.3 Testing the Users	72
13 Working with the GroupWise Administration Console	73
13.1 Accessing the Admin Console	73
13.2 Making the Most of the System Overview	73
13.3 Finding Objects in Object Lists	74
13.4 Finding Frequently Used Objects Quickly	74
13.5 Working with Objects and Object Properties	75
13.6 Using System Tools	75
14 Working with the GroupWise Agents	77
14.1 Linux: Managing the GroupWise Agents	77
14.1.1 Manually Starting and Stopping the Linux GroupWise Agents	77
14.1.2 Running the Linux GroupWise Agents as a Non-root User	80
14.1.3 Automatically Restarting the Linux GroupWise Agents with the GroupWise High Availability Service	83
14.1.4 Using the Linux GroupWise Agent Log Files	89
14.1.5 Uninstalling the Linux GroupWise Agents and Applications	89
14.2 Windows: Managing the GroupWise Agents	90
14.2.1 Manually Starting and Stopping the Windows GroupWise Agents	90
14.2.2 Using the Windows GroupWise Agent Log Files	92
14.2.3 Uninstalling the Windows GroupWise Agents and Applications	92
14.3 Monitoring the Agents from Your Web Browser	92
15 What's Next	95
Part IV GroupWise Component Installation and Setup	97
16 Setting Up GroupWise WebAccess	99
16.1 GroupWise WebAccess Overview	99
16.1.1 GroupWise WebAccess Functionality	99
16.1.2 GroupWise WebAccess Components	99
16.1.3 WebAccess Security Requirements	100
16.2 GroupWise WebAccess System Requirements	102
16.2.1 Hardware and Operating System Requirements	102
16.2.2 Web Server Requirements	102

16.2.3	GroupWise Requirements	103
16.2.4	User Requirements	103
16.3	Planning GroupWise WebAccess	104
16.3.1	Selecting the WebAccess Application Platform	104
16.3.2	Gathering Web Server Information	104
16.3.3	Determining the WebAccess Application's Configuration	105
16.3.4	Connecting the WebAccess Application with Supporting Agents	105
16.4	Installing the GroupWise WebAccess Software	106
16.4.1	Linux: Installing the GroupWise WebAccess Software	106
16.4.2	Windows: Installing the GroupWise WebAccess Software	107
16.5	Testing GroupWise WebAccess	108
16.5.1	Testing WebAccess on a Workstation	108
16.5.2	Testing WebAccess on a Tablet Device	108
16.5.3	Testing the WebAccess Basic Interface on a Mobile Device	109
16.5.4	Assisting Users with Login Problems	109
16.5.5	Monitoring the WebAccess Application	109
16.6	What's Next	110
16.7	GroupWise WebAccess Installation Worksheet	110

17 Setting Up the GroupWise Calendar Publishing Host 113

17.1	GroupWise Calendar Publishing Host Overview	113
17.1.1	GroupWise Calendar Publishing Host Functionality	113
17.1.2	GroupWise Calendar Publishing Host Components	113
17.1.3	GroupWise Calendar Publishing Host Security Requirements	114
17.2	GroupWise Calendar Publishing Host System Requirements	115
17.2.1	Hardware and Operating System Requirements	115
17.2.2	Web Server Requirements	116
17.2.3	Web Browser Requirements	117
17.3	Planning a GroupWise Calendar Publishing Host	117
17.3.1	Selecting the Calendar Publishing Host Application Platform	117
17.3.2	Gathering Web Server Information	117
17.3.3	Choosing the Calendar Publishing Host Name	118
17.3.4	Determining the URL of the Calendar Publishing Host	118
17.3.5	Selecting a Calendar Publishing Host Administrator	119
17.3.6	Connecting the Calendar Publishing Host to a POA	119
17.3.7	Designing Your Calendar Browse List	120
17.3.8	Selecting Calendar Publishing Settings	120
17.4	Installing the GroupWise Calendar Publishing Host	121
17.4.1	Linux: Installing the Calendar Publishing Host Software	121
17.4.2	Windows: Installing the Calendar Publishing Host Software	122
17.5	Configuring GroupWise to Support the Calendar Publishing Host	123
17.5.1	Configuring the Calendar Publishing Host in the GroupWise Admin Console	123
17.5.2	Enabling Calendar Publishing	124
17.5.3	Configuring a POA for Calendar Publishing	125
17.5.4	Setting Up Calendar Publishing Administration	125
17.5.5	Using the Published Calendar Browse List	126
17.6	Testing GroupWise Calendar Publishing	126
17.6.1	Publishing a Personal Calendar	126
17.6.2	Displaying the Browse List of Calendars	127
17.6.3	Publishing Free/Busy Information	127
17.7	What's Next	127
17.8	GroupWise Calendar Publishing Host Worksheets	128
17.8.1	Calendar Publishing Host Installation Worksheet	128
17.8.2	Calendar Publishing Host Configuration Worksheet	129

18 Setting Up GroupWise Monitor	131
18.1 GroupWise Monitor Overview	131
18.1.1 GroupWise Monitor Functionality	131
18.1.2 GroupWise Monitor Components	132
18.1.3 One Monitor Server versus Two	132
18.1.4 Monitor Security Requirements	132
18.1.5 Monitor and the GroupWise High Availability Service on Linux	134
18.2 GroupWise Monitor System Requirements	134
18.2.1 Hardware and Operating System Requirements	134
18.2.2 Web Server Requirements	135
18.2.3 Web Browser Requirements	135
18.3 Planning GroupWise Monitor	136
18.3.1 Deciding Where to Install the GroupWise Monitor Components	136
18.3.2 Determining the Monitor Agent's Configuration	137
18.3.3 Determining the Monitor Application's Configuration	138
18.4 Installing the GroupWise Monitor Software	138
18.4.1 Linux: Installing the GroupWise Monitor Software	139
18.4.2 Windows: Installing the GroupWise Monitor Software	141
18.5 Testing GroupWise Monitor	143
18.5.1 Using the Monitor Web Console	143
18.5.2 Using the Monitor Agent Console	143
18.5.3 Using the Windows Monitor Agent Server Console	143
18.6 GroupWise Monitor Installation Worksheets	144
18.6.1 GroupWise Monitor Agent Installation Worksheet	144
18.6.2 GroupWise Monitor Application Installation Worksheet	145
19 Setting Up GroupWise Calendar Server	147
19.1 GroupWise Calendar Server Overview	147
19.2 GroupWise Calendar Server System Requirements	147
19.2.1 Server Requirements	147
19.2.2 Configuration Requirements	147
19.3 Planning GroupWise Calendar Server	147
19.3.1 Gathering the Primary Domain Information	147
19.3.2 Gathering the Server Information	148
19.3.3 Specifying the Application Admin	148
19.3.4 Gathering SOAP Information	149
19.3.5 Gathering the Novell Push Notification Certificate	149
19.4 Installing the Calendar Server Software	149
19.5 Configuring Auto-Discovery of GroupWise Calendar Server	150
19.6 Testing GroupWise Calendar Server	150
19.6.1 Calendar Server Service Name	150
19.6.2 Testing Calendar Server on a Workstation	150
19.6.3 Troubleshooting Calendar Server Configuration Errors	150
19.6.4 Resolving an Untrusted CA	151
19.7 GroupWise Calendar Server Worksheet	152
20 Installing the GroupWise Client	153
20.1 GroupWise Client Overview	153
20.2 GroupWise Client Workstation Requirements	153
20.3 Installing the GroupWise Client	154
20.3.1 Installing the GroupWise Client	154
20.3.2 Implementing System-Wide GroupWise Client Rollouts	155
20.4 Starting the Groupwise Client	155
20.5 What's Next	156

21 Using Other Novell Products with GroupWise	157
21.1 Using the GroupWise Mobility Service to Synchronize GroupWise Data to Mobile Devices	157
21.2 Using Novell Messenger to Provide Secure Instant Messaging for GroupWise Users	157
21.3 Using Novell Vibe to Provide Team Workspaces for GroupWise Users.	158
 Part V GroupWise System Upgrade	 159
 22 What's New in GroupWise 2014 R2	 161
 23 Understanding the Upgrade Process	 163
23.1 Domain and Post Office Upgrades.	163
23.2 Agent Upgrades	164
23.3 Monitor Upgrades.	165
23.4 WebAccess Upgrades	165
23.5 Calendar Publishing Host Upgrades	165
23.6 GroupWise Client Upgrades	165
23.7 Obsolete eDirectory Schema Extensions.	166
23.8 Obsolete Software Distribution Directories.	166
23.9 Obsolete GroupWise Gateways.	166
23.10 NetWare Compatibility	166
 24 Preparing Your Existing GroupWise System for the Upgrade	 169
 25 Installing the GroupWise 2014 Software	 171
25.1 Linux: Installing the GroupWise 2014 Software	171
25.2 Windows: Installing the GroupWise 2014 Software	172
 26 Upgrading the Primary Domain Server	 175
 27 Upgrading a Secondary Domain Server	 179
 28 Upgrading a Post Office Server	 183
 29 Upgrading GroupWise Agents and Applications	 185
29.1 Upgrading the Document Viewer Agent.	185
29.2 Upgrading GroupWise WebAccess	185
29.2.1 Preparing to Upgrade the WebAccess Application	186
29.2.2 Installing the GroupWise 2014 WebAccess Application	186
29.2.3 Clearing User Browser Caches to Display GroupWise 2014 WebAccess Correctly	187
29.3 Upgrading the Calendar Publishing Host.	187
29.3.1 Installing the GroupWise 2014 Calendar Publishing Host Application.	187
29.3.2 Clearing User Browser Caches to Display Published Calendars Correctly.	188
29.4 Upgrading GroupWise Monitor.	188
29.4.1 Preparing to Upgrade GroupWise Monitor.	188
29.4.2 Installing the Monitor Software.	188
29.4.3 Clearing Browser Caches to Display GroupWise 2014 Monitor Correctly.	189
29.4.4 Reconfiguring the GroupWise High Availability Service	189
29.5 Implementing SSL Encryption	189

30 Upgrading Users' GroupWise Client Software	191
31 Transitioning from ConsoleOne	193
32 Upgrading the GroupWise/Exchange Coexistence Solution	195
Part VI Appendixes	197
A GroupWise Version Compatibility	199
A.1 GroupWise 2014 with Earlier GroupWise Versions	199
A.1.1 Compatibility with GroupWise 2012	199
A.1.2 Compatibility with GroupWise 8	201
A.2 GroupWise 2014 in a Cross-Platform Environment	202
A.2.1 GroupWise 2014 Administrative Components and Databases	202
A.2.2 GroupWise 2014 Agents on Linux and Windows	202
B Attributes, Operators, and Values for Object Filters	205
B.1 Attributes	205
B.2 Logical Operators	206
B.3 Grouping Operators	207
B.4 Wildcard Characters	207
B.5 Literal Values	207
B.6 Date Specifications	208
C Invalid Characters in GroupWise Object Names and Email Addresses	209
C.1 Invalid Characters in GroupWise Object Names	209
C.2 Invalid Characters in Internet Email Addresses	209
D Cross-Platform Connections	211
D.1 Setting up Samba on OES	211
D.1.1 Configuring NetWare Core Protocol (NCP)	211
D.1.2 Installing Samba	212
D.1.3 Logging In to iManager	212
D.1.4 Creating a User to Manage the Samba Share	212
D.1.5 Configuring the eDirectory Universal Password for Samba	213
D.1.6 Setting the eDirectory Universal Password for the Samba Administrator User	213
D.1.7 Creating a Samba Share	213
D.1.8 Setting the eDirectory Rights for the Samba Share	213
D.1.9 Testing Samba on the OES Server	214
D.2 Mapping a Drive to a Samba Share on an OES Server	214
D.3 Setting Up Samba on SLES	214
D.3.1 Preparing Your Firewall to Allow Samba Connections	215
D.3.2 Configuring the Samba Server	215
D.3.3 Configuring the Samba Web Administration Tool (SWAT)	215
D.3.4 Accessing SWAT	215
D.3.5 Setting the Samba User Name and Password	216
D.3.6 Creating a Samba Share	216
D.4 Mapping a Drive to a Samba Share on a SLES Server	216

E	Third-Party Materials	217
E.1	Apache	217
E.2	BLT	218
E.3	GD Graphics Library	218
E.4	getopt.h	219
E.5	iCal4j - License	220
E.6	ICU License - ICU 1.8.1 and Later	220
E.7	JRE	221
E.8	NET-SNMP Open Source Package	221
E.8.1	---- Part 1: CMU/UCD copyright notice: (BSD like) ----	221
E.8.2	---- Part 2: Networks Associates Technology, Inc copyright notice (BSD) ----	222
E.8.3	---- Part 3: Cambridge Broadband Ltd. copyright notice (BSD) ----	222
E.8.4	---- Part 4: Sun Microsystems, Inc. copyright notice (BSD) ----	223
E.9	ODMA 2.0	223
E.10	OpenLDAP	224
E.11	OpenSSL	225
E.12	Oracle Outside In Technology	226
E.13	Python 2.2	227
E.14	Yahoo! UI Library	227
F	ISAPI Configuration	229
F.1	Windows 2012 R2	229
G	Documentation Updates	231

About This Guide

This Novell *GroupWise 2014 Installation Guide* helps you install a new GroupWise system or upgrade an existing GroupWise 8 or 2012 system to GroupWise 2014.

The following resources provide additional information about using GroupWise 2014:

- ♦ [Novell Support and Knowledgebase \(http://www.novell.com/support/\)](http://www.novell.com/support/)

To search the GroupWise documentation from the Novell Support website, click **Advanced Search**, select **Documentation** in the **Search In** drop-down list, select **GroupWise** in the **Products** drop-down list, type the search string, then click **Search**.

- ♦ [GroupWise Support Forums \(https://forums.novell.com/forumdisplay.php/356-GroupWise\)](https://forums.novell.com/forumdisplay.php/356-GroupWise)
- ♦ [GroupWise Support Community \(http://www.novell.com/support/kb/product.php?id=GroupWise\)](http://www.novell.com/support/kb/product.php?id=GroupWise)
- ♦ [GroupWise Cool Solutions \(https://www.novell.com/communities/cool solutions/category/groupwise/\)](https://www.novell.com/communities/cool solutions/category/groupwise/)

Audience

This guide is intended for network administrators who install and administer GroupWise.

Feedback

We want to hear your comments and suggestions about this manual and the other documentation included with this product. Please use the User Comment feature at the bottom of each page of the online documentation.

Additional Documentation

For additional GroupWise documentation, see the [Novell GroupWise 2014 R2 Documentation website \(http://www.novell.com/documentation/groupwise2014r2/\)](http://www.novell.com/documentation/groupwise2014r2/).

GroupWise Product Overview

Novell GroupWise is an enterprise collaboration system that provides the following secure services:

- ♦ Email
- ♦ Calendaring
- ♦ Scheduling
- ♦ Task management
- ♦ Contact management
- ♦ Document management
- ♦ Additional productivity tools

Companion products provide additional capabilities:

- ♦ **GroupWise Mobility Service:** Synchronization of GroupWise data to mobile devices
- ♦ **Novell Messenger:** Secure instant messaging
- ♦ **Novell Vibe:** Team workspaces, document management, and other collaboration tools

GroupWise 2014 can be used in a variety of environments:

- ♦ **Your Windows Desktop:** Windows XP, 7, and 8
- ♦ **Web Browsers:** Mozilla Firefox, Google Chrome, and Microsoft Internet Explorer
- ♦ **Tablets:** Apple, Android, Kindle, and RIM
- ♦ **Mobile Devices:** Apple, Android, BlackBerry, and Windows

The following sections include more details about the benefits that GroupWise provides and the steps you need to perform to set up your GroupWise system to best meet your users' needs.

- ♦ [Chapter 1, "GroupWise Features and Benefits," on page 15](#)
- ♦ [Chapter 2, "GroupWise Components," on page 19](#)
- ♦ [Chapter 3, "GroupWise System Architecture," on page 21](#)

1 GroupWise Features and Benefits

GroupWise provides communication and collaboration services that are secure, highly available, and easily accessible:

- ♦ [Section 1.1, “Essential Communication and Collaboration Services,” on page 15](#)
- ♦ [Section 1.2, “Available Anytime,” on page 16](#)
- ♦ [Section 1.3, “Accessible Anywhere,” on page 16](#)
- ♦ [Section 1.4, “Always Secure,” on page 17](#)
- ♦ [Section 1.5, “Competitive Performance,” on page 17](#)
- ♦ [Section 1.6, “Evaluation Version Available,” on page 17](#)

1.1 Essential Communication and Collaboration Services

GroupWise provides a variety of tools to enable users to work together and to work smarter:

- ♦ **Messaging:** Send and receive mail messages, phone messages, and reminder notes. A mail message is for general correspondence. A phone message is for those who take phone messages for others. A reminder note includes a start date and, when accepted by the recipient, is posted to the recipient's Calendar.
- ♦ **Scheduling:** Schedule both appointments and tasks. When you schedule an appointment, you can search other users' Calendars to find free times for the appointment. When you schedule a task, you can assign a priority and due date to the task. If the recipient accepts an appointment or task, it is automatically added to his or her Calendar.
- ♦ **Calendaring:** View and manage your appointments, tasks, and reminder notes in a Calendar view. You can create multiple calendars. You can create multi-user calendars. You can also publish calendars and free/busy status to the web so that non-GroupWise users can conveniently schedule meetings with you.
- ♦ **Task Management:** Create and schedule tasks for others. Accept or decline the tasks you receive, and track accepted tasks through to completion. You can turn any message into a task. You can also organize, schedule, and monitor tasks in your Tasklist folder.
- ♦ **Contact Management:** Manage information for your contacts, groups, resources, and organizations, including being able to view, update, delete, and add information to the contacts in your personal address books and Contacts folders. In addition, you can view a history of messages sent to and received from individual contacts, and compile notes on interactions with contacts.
- ♦ **Document Management:** Store documents in GroupWise libraries. In a library, documents, are compressed to save disk space and encrypted to maintain security. With document management, you can check in, check out, share, and create multiple versions of documents.
- ♦ **Mobile Device Synchronization:** Receive and respond to GroupWise messages, appointments, tasks, and notes on your mobile device. You can also send new items of all types and manage contacts on your mobile device.

- ♦ **Instant Messaging:** Communicate in real time with other GroupWise users through Novell Messenger. Messenger lets you know when other users are online, busy, or away from their desks and displays this status in the GroupWise client. Messenger also allows you to save conversations.
- ♦ **Teaming:** Collaborate on a Novell Vibe website where personal, team, and global workspaces can include discussion folders, shared calendars, shared documents, blogs, wikis, surveys, and more. Powerful search capabilities make finding information quick and easy. GroupWise includes integration with Vibe, so that you can access a Vibe site from the GroupWise client.

1.2 Available Anytime

GroupWise ensures that your essential communication tools are always available:

- ♦ **Caching:** The GroupWise client includes a Caching mode that allows you to cache GroupWise information to your local drive and continue to work even when you are not logged in to your Online mailbox.
- ♦ **LDAP Pooling:** If you are using LDAP authentication for GroupWise mailbox authentication, LDAP pooling ensures that there is always an LDAP server through which authentication can be performed.
- ♦ **Clustering:** To ensure that GroupWise data is always available and GroupWise components are always running, you can install GroupWise in a cluster on Linux or Windows.

1.3 Accessible Anywhere

GroupWise lets you communicate and collaborate with other people by using the device that is most convenient:

- ♦ **Personal Computers:** To access your GroupWise mailbox with the most robust functionality, you can run the GroupWise client on any workstation that uses Windows XP, 7, or 8.
- ♦ **Web Browsers:** When you are away from your office, or when you prefer a platform other than Windows, you can access your GroupWise mailbox from a variety of desktop web browsers by using GroupWise WebAccess.
- ♦ **Tablet Computers:** For those who prefer a more mobile computer, you can access your GroupWise mailbox from a tablet computer by using GroupWise WebAccess Mobile.
- ♦ **Mobile Devices:** If you want to access email messages, calendar items, tasks, and so on from a handheld mobile device such as your cell phone, you have several options:
 - ♦ **GroupWise Mobility Service:** The GroupWise Mobility Service, available free of charge to GroupWise customers with maintenance contracts, synchronizes GroupWise data to most popular mobile devices.
 - ♦ **BlackBerry Enterprise Server for GroupWise:** This solution from Research in Motion provides synchronization of GroupWise data for BlackBerry users with devices that are older than the BlackBerry Z10. Newer BlackBerry devices are fully supported by the GroupWise Mobility Service.
 - ♦ **GroupWise WebAccess Basic Template:** GroupWise WebAccess includes a basic template customized for use on the small display available on a typical mobile device.

NOTE: GroupWise WebAccess Mobile is intended for use on tablets, not on smaller mobile devices such as cell phones.

- ♦ **Other Email Clients:** GroupWise enables you to access your mailbox with any POP3, IMAP4, or SOAP email client.

1.4 Always Secure

GroupWise provides extensive security measures to protect your information:

- ♦ **Native GroupWise Encryption:** To protect your information as it is stored in the various GroupWise databases and moved across the network, GroupWise automatically encrypts the information. Each piece of information is encrypted differently through the use of randomly generated encryption keys.
- ♦ **Open Security Standards:** To further ensure that your information is secure while moving across your internal network and across the Internet, GroupWise supports open security standards such as Secure Sockets Layer (SSL), Secure Multipurpose Internet Mail Extension (S/MIME), Public Key Infrastructure (PKI), and Transport Layer Security (TLS).
- ♦ **Spam Protection:** To protect you from seeing unwanted messages, the GroupWise client includes a Junk Mail Handling feature that lets you control unwanted Internet email messages. In addition, you can configure the GroupWise Internet Agent (GWIA) to reject messages from known open relay hosts and spam hosts. GroupWise also works with partner products that provide additional anti-spam solutions.
- ♦ **Virus Protection:** GroupWise works with partner products to provide solutions that detect and eliminate viruses.

For information about additional security solutions available for GroupWise through GroupWise partners, see the [Novell Partner Product Guide \(http://www.novell.com/partnerguides/\)](http://www.novell.com/partnerguides/).

1.5 Competitive Performance

GroupWise functionality compares very favorably with popular email solutions:

- ♦ [Novell GroupWise and Microsoft Exchange/Outlook \(http://www.novell.com/products/groupwise/features/groupwise-vs-outlook.html\)](http://www.novell.com/products/groupwise/features/groupwise-vs-outlook.html)
- ♦ [Novell GroupWise and Google Gmail \(http://www.novell.com/products/groupwise/features/groupwise-vs-gmail.html\)](http://www.novell.com/products/groupwise/features/groupwise-vs-gmail.html)

1.6 Evaluation Version Available

An evaluation version of GroupWise is available on the [Novell Downloads website \(http://download.novell.com\)](http://download.novell.com). With the evaluation version of GroupWise, you can create a test GroupWise system that includes any number of domains, post offices, and users. The evaluation version does not expire. However, the evaluation software cannot legally be installed and run in a production environment.

2 GroupWise Components

GroupWise includes multiple components that you need to install to realize the full benefits of GroupWise. However, some components might not be necessary, depending on your needs. The following table outlines the components, what they provide, and where to find instructions for installing them.

Component	What it does	Go to
GroupWise Server: <ul style="list-style-type: none">♦ Administration Service♦ Message Transfer Agent♦ Post Office Agent♦ Internet Agent♦ Document Viewer Agent	Required for any GroupWise system. These components must be installed before any other components.	Chapter 10, “Creating a Simple GroupWise System,” on page 63 Chapter 11, “Creating a Typical GroupWise System,” on page 65
WebAccess WebAccess Mobile	Provides access to mailboxes through desktop web browsers, tablet computers, and mobile devices.	Chapter 16, “Setting Up GroupWise WebAccess,” on page 99
Calendar Publishing Host	Provides web-based public access to GroupWise calendars and free/busy availability to Internet users.	Chapter 17, “Setting Up the GroupWise Calendar Publishing Host,” on page 113
Monitor	Provides administrative monitoring of the GroupWise agents.	Chapter 18, “Setting Up GroupWise Monitor,” on page 131
GroupWise Client	Provides access to mailboxes from the Windows desktop; can be easily rolled out to all GroupWise users on a convenient schedule.	Chapter 20, “Installing the GroupWise Client,” on page 153

In addition to the sections referenced in the above table, this *Installation Guide* includes the following supplemental sections:

- ♦ [Section 21.1, “Using the GroupWise Mobility Service to Synchronize GroupWise Data to Mobile Devices,” on page 157](#)
- ♦ [Section 21.2, “Using Novell Messenger to Provide Secure Instant Messaging for GroupWise Users,” on page 157](#)
- ♦ [Section 21.3, “Using Novell Vibe to Provide Team Workspaces for GroupWise Users,” on page 158](#)


The information in these sections is provided as a reference for installing additional products after you have created your GroupWise system.

3 GroupWise System Architecture

Your GroupWise system consists of multiple components. The better you understand each component, the more effectively you can manage your GroupWise system.


3.1 Agent Architecture

The GroupWise agents move email throughout your GroupWise system, as well as to and from the Internet.



The Post Office Agent (POA) runs for each post office. The POA delivers email to users' mailboxes. The Message Transfer Agent (MTA) runs for each domain. The MTA transfers email between post offices and other domains.


The Internet Agent (GWIA) runs for at least one domain in your GroupWise system. The GWIA communicates with SMTP hosts across the Internet, sending and receiving email for users who are not part of your GroupWise system.



The Document Viewer Agent (DVA) runs for at least one post office. The DVA converts attached document files from a wide variety of formats into HTML format for indexing by the POA and for viewing in GroupWise WebAccess.

3.2 Administration Service Architecture


The GroupWise Administration Service provides the GroupWise Administration console in your web browser. The Admin console provides the global view of your GroupWise system. It enables you to configure and customize all GroupWise objects (Domain, Post Office, User, MTA, POA, GWIA, DVA, and so on). It also provide a number of administrative tools for managing your GroupWise system.



The Admin Service runs on each domain server and post office server. The Admin Service communicates with Admin Services on other GroupWise servers and with the agents that run on its local server. You can access the Admin console on any domain server. For post office access, you access the Admin console for the domain that owns the post office.

3.3 WebAccess Architecture


WebAccess enables GroupWise users to access their mailboxes from their web browser.



Externally, the WebAccess Application, which integrates with your web server, communicates with the user's web browser across the Internet. Internally, the WebAccess Application communicates with the Post Office Agent (POA) to request mailbox data and with the Document Viewer Agent (DVA) for conversion of attached documents into HTML for viewing.

3.4 Calendar Publishing Host Architecture


The Calendar Publishing (CalPub) Host enables GroupWise users and non-GroupWise users to view GroupWise users' calendars from their web browser.




Externally, the CalPub Host Application, which integrates with your web server, communicates with the user's web browser across the Internet. Internally, the CalPub Host Application communicates with the Post Office Agent (POA) to request calendar data from the user's mailbox. The CalPub Host requires access to an LDAP server such as NetIQ eDirectory or Microsoft Active Directory for administrator authentication to the CalPub Admin console.

3.5 Monitor Architecture

Monitor enables you to monitor the GroupWise agents from your web browser when you are not working behind your firewall.



Internally, the Monitor Agent gathers status information from GroupWise agents. Externally, the Monitor Application, which integrates with your web server, communicates with your web browser across the Internet to provide a Monitor console that is available outside your firewall. The Monitor Agent also provides its own internal Monitor console independent of your web server, which is available inside your firewall.



GroupWise System Requirements

You, as a GroupWise administrator, must ensure that your system meets GroupWise system requirements, so that your GroupWise system can be set up successfully. After your GroupWise system is set up, you must ensure that users' workstations meet GroupWise client requirements, so that users can run the GroupWise clients successfully.

- ♦ [Chapter 4, "GroupWise Administration Requirements," on page 27](#)
- ♦ [Chapter 5, "GroupWise User Requirements," on page 31](#)
- ♦ [Chapter 6, "Supported Environments," on page 33](#)

4 GroupWise Administration Requirements

4.1 Hardware and Operating System Requirements

- ☐ x86-64 processor
- ☐ Any of the following server operating systems for the GroupWise agents (Post Office Agent, Message Transfer Agent, Document Viewer Agent, Internet Agent, Monitor Agent):
 - ♦ Novell Open Enterprise Server (OES) 11 or Novell Open Enterprise Server (OES) 2015, plus the latest Support Pack
 - ♦ SUSE Linux Enterprise Server (SLES) 11 or SUSE Linux Enterprise Server (SLES) 12 plus the latest Service Pack

NOTE: On Linux, the X Window System and Open Motif are required by the GUI GroupWise agent server consoles for the Post Office Agent, the Message Transfer Agent, and the Internet Agent.

By default, the GroupWise Linux agents run as services without user interfaces. Starting and stopping the agents when they are running with a user interface is not supported in the GroupWise Administration console.

- ♦ Windows Server 2012 R2, plus the latest Service Pack
- ☐ Adequate server memory as required by the operating system

Depending on the anticipated load on the GroupWise agents, additional memory might be required. For details, see [Section 4.6, “Sample Agent Memory Requirements,” on page 30](#).
- ☐ Adequate server disk space as required by each GroupWise component:
 - ♦ **Domain Folder:** 100-200 MB for the domain database, plus 1 GB or more for message queues when links are down
 - ♦ **Post Office Folder:** 5 MB per user (minimum); 100 MB or more per user (recommended); plus 100-300 MB for the post office database; plus 500 MB or more for message queues when links are down
 - ♦ **GroupWise Server Installation:** Approximately 885 MB (GroupWise Administration Service, Message Transfer Agent, Post Office Agent, Internet Agent, and Document Viewer Agent combined; varies by platform)

For additional Internet Agent requirements, including Internet connectivity requirements, see [Section 4.5, “Internet Agent Functional Requirements,” on page 29](#).
 - ♦ **WebAccess Installation:** Approximately 525 MB (shared with the Calendar Publishing Host Application and the Monitor Application when they are installed on the same web server; varies by platform)
 - ♦ **Calendar Publishing Host Installation:** Approximately 525 MB (shared with the WebAccess Application and the Monitor Application when they are installed on the same web server; varies by platform), plus 50 KB per published calendar and 50 KB per user for free/busy searching

- ♦ **Monitor Installation:** Approximately 40 MB for the Monitor Agent (varies by platform); approximately 525 MB for the Monitor Application (shared with the WebAccess Application and the Calendar Publishing Host Application when they are installed on the same web server; varies by platform)

4.2 Directory Requirements

One or more of the following directories:

- ☐ NetIQ eDirectory 8.8.7 or later, plus the latest Support Pack, with LDAP enabled (optional)

You can download eDirectory from the [Novell Downloads site \(http://download.novell.com\)](http://download.novell.com).

- ☐ Microsoft Active Directory (optional)
- ☐ Native GroupWise directory (internal; required)

4.3 Web Server Requirements

The web server that is supported for your operating system, for use with the GroupWise Administration console, the agent consoles, WebAccess, Monitor, and the Calendar Publishing Host:

- ☐ x86-64 or x86-32 processor
- ☐ OES 11 / OES 2015 / SLES 11

Apache 2.2 plus:

- ♦ Tomcat 7
- ♦ ModProxy Module
- ♦ **OES11 / OES 2015 / SLES 11:** IBM Java 8 Runtime Environment (JRE)
- ♦ **SLES 12:** OpenJDK 7

A Linux repository should be available when you run the GroupWise Installation Wizard. Apache, Tomcat, the JRE or JDK, and the ModProxy Module are automatically installed from the Linux repository if they are not already present on the Linux server.

If no Linux repository is available during the GroupWise installation, you are prompted to manually install these required components from the Linux media, and then restart the GroupWise installation.

- ☐ Windows Server 2012 R2

Microsoft Internet Information Server (IIS) 7 or later plus:

- ♦ Tomcat 7
- ♦ Oracle Java 8 Runtime Environment (JRE)
- ♦ Jakarta Connector 1.2

Tomcat, Oracle JRE, and Jakarta Connector are automatically installed along with the GroupWise software if they are not already present on the Windows server.

- ♦ ISAPI support

ISAPI support is no longer installed by default when you install Windows Server 2008 R2 or later and Internet Information Services (IIS). If ISAPI support was not manually selected when IIS was installed, you can add it after the fact. See

4.4 Web Browser Requirements Administrators

Any of the following web browsers for the GroupWise Administration console and agent consoles:

- ☐ Linux: Mozilla Firefox; Google Chrome
- ☐ Windows: Microsoft Internet Explorer 10 or later; Mozilla Firefox; Windows Edge
- ☐ Macintosh: Mozilla Firefox; Google Chrome; Safari

NOTE: The web browser requirements for GroupWise WebAccess are different from the web browser requirements for the Admin and agent consoles. For those user requirements, see [Section 5.2, “GroupWise WebAccess User Requirements,” on page 31](#).

The Admin and agent consoles are not supported on tablet devices. For those user requirements, see [Section 5.3, “GroupWise WebAccess Mobile User Requirements,” on page 31](#).

4.5 Internet Agent Functional Requirements

The following additional requirements apply when you install the Internet Agent:

The GroupWise system in which you install the Internet Agent (GWIA) must meet the following requirements:

- ☐ The domain's version must be equal to or later than the GWIA's version. The domain's version is determined by the Message Transfer Agent (MTA) version running for it.
- ☐ The versions of any post offices that the GWIA accesses on behalf of POP3 or IMAP4 clients must be equal to or later than the GWIA's version. A post office's version is determined by the Post Office Agent (POA) version running for it.
- ☐ The POA and MTA need to be accessible to the GWIA for IMAP, POP, and ICAL.

Before you install the Internet Agent (GWIA), ensure that your network is configured for Internet connectivity.

- ☐ **Internet Connection:** You can connect to the Internet by using a direct connection over a leased line or a standard switched telephone line.
- ☐ **Internet Domain Name:** You must have an Internet domain name. The domain name must be defined by an MX RR (mail exchanger resource record) in DNS.
- ☐ **DNS Server Access or Relay Host Access:** If you want the GWIA to send messages directly to other SMTP hosts, it requires access to a DNS server for address resolution. Otherwise, it requires access to a relay host that can perform the address resolution and message routing. Ensure the server where you plan to install the GWIA is configured to access a DNS server or can access your relay host. For specific details, refer to your server documentation.
- ☐ **IP Address:** The GWIA's server requires a static IP address and a fully qualified DNS hostname.

4.6 Sample Agent Memory Requirements

4.6.1 Sample POA Memory Requirements Based on Post Office Size

The amount of memory used by the POA depends on the number of active users, as illustrated by the table below. The POA typically performs best with abundant cache memory available.

Concurrent Users	Minimum Memory Required	Recommended Memory for Best Performance
100 active users (100-250 users in post office)	400 MB	2 GB
250 active users (250-500 users in post office)	600 MB	4 GB
500 active users (500-1000 users in post office)	800 MB	4 GB
1000 active users (1000 - 1500 users in post office)	1 GB	8 GB - 12 GB
1500 active users (1500 - 3000 users in post office)	2 GB	12 GB

4.6.2 Sample Memory Requirements for Other GroupWise Agents and Applications

Agent/Application	Minimum Memory Required	Recommended Memory for Best Performance
Routing MTA	200 MB	2 GB
DVA	100 MB	1 GB
GWIA and its MTA	400 MB	4 GB
Monitor	100 MB	1 GB
WebAccess Application	400 MB	4 GB
Calendar Publishing Host Application	200 MB	1 GB
WebAccess and Calendar Publishing Host Applications together	600 MB	4 GB

5 GroupWise User Requirements

5.1 GroupWise Client User Requirements

- ☐ x86-32 processor or x86-64 processor

On a 64-bit processor, GroupWise still runs as a 32-bit application.

- ☐ Any of the following desktop operating systems for the GroupWise client:
 - ♦ Windows 7 on a 1 GHz or higher workstation with at least 1 GB of RAM
 - ♦ Windows 8 or Windows 8.1 on a 1 GHz or higher workstation with at least 1 GB of RAM
 - ♦ Windows 10 on a 1 GHz or higher workstation with at least 1 GB of RAM
- ☐ Microsoft Internet Explorer 9 or later
- ☐ Any of the following word processors for use as the GroupWise editor:
 - ♦ LibreOffice 3.6 or later
 - ♦ Microsoft Word 2007 or later
- ☐ Approximately 200 MB of free disk space on each user's workstation to install the GroupWise client.

5.2 GroupWise WebAccess User Requirements

- ☐ Any of the following web browsers:
 - ♦ Linux: Mozilla Firefox; Google Chrome
 - ♦ Windows: Microsoft Internet Explorer 9 or later; Mozilla Firefox; Google Chrome; Windows Edge
 - ♦ Macintosh: The latest version of Safari for your version of Mac OS; Mozilla Firefox; Google Chrome
- ☐ Any mobile device that supports Wireless Access Protocol (WAP) and has a microbrowser that supports Hypertext Markup Language (HTML) 4.0 or later

5.3 GroupWise WebAccess Mobile User Requirements

Any of the following tablet operating systems and tablets:

- ☐ Android 4.1, 5.0, or later, with Google Chrome, on any Android device
- ☐ Apple iOS 7.x, 8.x, or later, with Apple Safari
- ☐ Kindle Fire, with Amazon Silk
- ☐ Windows Mobile 8.0 or later Pro, with Microsoft Internet Explorer, on any Windows device (full WebAccess, no template)

6 Supported Environments

6.1 IPv6 Support

The Post Office Agent, the Message Transfer Agent, the Internet Agent, and the Monitor Agent support the IPv6 protocol when it is available on the server. If IPv6 is available, the agent detects it and supports it by default, along with IPv4. The Document Viewer Agent does not support IPv6.

As you configure your GroupWise system and specify the network address of an IPv6 server in the GroupWise Administration console, you must specify its DNS hostname. **IP Address** fields in the Admin console do not accommodate IPv6 address format.

6.2 Clustering Support

You can set up your GroupWise system in the following clustering environments:

- ♦ Novell Cluster Services on Linux
- ♦ Microsoft Clustering on Windows

If you are using one of these clustering environments, see “[Clustering](#)” in the *GroupWise 2014 R2 Interoperability Guide* before using the installation instructions in this guide.

6.3 Xen Virtualization Support

You can install components of your GroupWise system in virtual environments where a software program enables one physical server to function as if it were two or more physical servers. Xen virtualization technology in Open Enterprise Server (OES) 11 and SUSE Linux Enterprise Server (SLES) 11 is supported. For more information, see:

- ♦ [Open Enterprise Server 11 Virtualization documentation \(http://www.novell.com/documentation/oes11/#cat_virtualization\)](http://www.novell.com/documentation/oes11/#cat_virtualization)
- ♦ [SLES Virtualization Technology documentation \(https://www.suse.com/documentation/sles11/#additional\)](https://www.suse.com/documentation/sles11/#additional)

Large post offices with busy Post Office Agents are not good candidates for Xen virtualization. Specialized Post Office Agents, such as an indexing Post Office Agent with no mailboxes and users, could be virtualized using Xen. Other GroupWise components such as the Message Transfer Agent and the Internet Agent do well when virtualized using Xen.

6.4 VMware Support

GroupWise is supported on VMWare ESX and ESXi. For more information, see the [VMware website \(http://www.vmware.com\)](http://www.vmware.com).

All GroupWise components are good candidates for VMware virtualization.

6.5 Hyper-V / Cloud Server Support

GroupWise is supported on Hyper-V Server 2012 R2. For more information, see the [Microsoft Hyper-V Server website \(http://www.microsoft.com/en-us/server-cloud/products/windows-server-2012-r2/default.aspx\)](http://www.microsoft.com/en-us/server-cloud/products/windows-server-2012-r2/default.aspx).

All GroupWise components are good candidates for Hyper-V / Cloud Server virtualization.

6.6 Citrix Support

Any version of the GroupWise client runs successfully on any 32-bit version of Citrix terminal services.

The GroupWise agents run successfully on Citrix XenServer.

For more information, see the [Citrix website \(http://www.citrix.com\)](http://www.citrix.com).

6.7 Domain Services for Windows Support

GroupWise can be used with Domain Services for Windows (DSfW) in your NetIQ eDirectory tree. GroupWise accounts can be added to User objects in the DSfW partition, but all other GroupWise objects (Domain, Post Office, Agent, and so on) must be created in the eDirectory partition.


IMPORTANT: Do not install GroupWise on the same server with DSfW.

6.8 File System Support

GroupWise is supported on any file system supported by the server OS.

Using an NFS mount to the file system where the GroupWise system is located is not supported.

NOTE: If you choose to use the NSS file system, turn off Salvage for best performance. For more information, see the [Novell Open Enterprise Server Documentation \(https://www.novell.com/documentation/oes11/\)](https://www.novell.com/documentation/oes11/).



GroupWise System Creation

- ♦ [Chapter 7, “GroupWise System Overview,” on page 37](#)
- ♦ [Chapter 8, “Planning Your GroupWise System,” on page 41](#)
- ♦ [Chapter 9, “Installing the GroupWise Server Software,” on page 59](#)
- ♦ [Chapter 10, “Creating a Simple GroupWise System,” on page 63](#)
- ♦ [Chapter 11, “Creating a Typical GroupWise System,” on page 65](#)
- ♦ [Chapter 12, “Adding Users to Your GroupWise System,” on page 71](#)
- ♦ [Chapter 13, “Working with the GroupWise Administration Console,” on page 73](#)
- ♦ [Chapter 14, “Working with the GroupWise Agents,” on page 77](#)
- ♦ [Chapter 15, “What’s Next,” on page 95](#)


7 GroupWise System Overview

Your GroupWise system can be structured in a variety of ways. Some decisions must be made in the beginning. Other decisions can be made as your GroupWise system grows.

7.1 Simple GroupWise System

A simple GroupWise system is installed on a single server. A simple GroupWise system would be appropriate only for a very small number of users working in a single geographic location or for temporary use in a lab environment.

A simple GroupWise system consists of a single domain (the primary domain) with one post office, and several users, as shown below:



A domain organizes post offices into a logical grouping for administration and routing purposes in your GroupWise system. Messages are transferred between post offices and domains by the Message Transfer Agent (MTA). Messages are transferred to and from your GroupWise system by the Internet Agent (GWIA).


A post office serves as an administrative unit for a group of users and mailboxes. Messages are delivered to mailboxes by the Post Office Agent (POA).

7.2 Typical GroupWise System

In contrast to a simple GroupWise system, a typical GroupWise system is installed on multiple servers, perhaps across multiple geographic locations.

- ♦ **Primary Domain:** The primary domain would be created on its own server and would not own post offices.
- ♦ **Secondary Domains:** Secondary domains would each be created on their own servers and would own multiple post offices.

- ♦ **Post Offices:** Depending on server capacity, post offices could be created on domain servers or could be created on their own servers.
- ♦ **Internet Agents:** One or more Internet Agents would be set up for the GroupWise system. An Internet Agent could be set up in a domain that owns post offices, or a separate domain could be created specifically to house one or more Internet Agents.



7.3 GroupWise Users

You can add users to your GroupWise system in two different ways:

- ♦ Manually create users in the internal GroupWise directory
- ♦ Import users from an LDAP directory such as NetIQ eDirectory or Microsoft Active Directory

Each GroupWise user has a mailbox in the post office. Users can access their mailboxes in several ways:

- ♦ GroupWise client on a Windows desktop
- ♦ GroupWise WebAccess in a supported web browser
- ♦ GroupWise WebAccess Mobile on a supported tablet

Users can also synchronize mailbox data with mobile devices using the GroupWise Mobility Service.

7.4 GroupWise Agents

Domains, post offices, and mailboxes are supported by four GroupWise agents:

- ♦ The Post Office Agent (POA) responds to GroupWise client requests for mailbox data and delivers messages between users' mailboxes in a post office. The POA also communicates with the MTA to route messages to and from the post office. In addition, the POA performs a variety of maintenance tasks in the post office.
- ♦ The Message Transfer Agent (MTA) transfers messages between post offices and domains, and performs a variety of other functions in the domain.

- ♦ The Internet Agent (GWIA) converts GroupWise messages into SMTP format and transfers them to the Internet SMTP hosts where recipients are located. In reverse, it receives SMTP messages from Internet SMTP hosts and converts them into GroupWise format. The GWIA can also provide access for POP3 and IMAP4 clients to access GroupWise mailboxes.
- ♦ The Document Viewer Agent (DVA) converts attached document files from a wide variety of formats into HTML format for indexing by the POA and for viewing in GroupWise WebAccess. You can run up to three DVAs to service conversion requests for a single instance of the POA. Each DVA must be installed on a different server.

8 Planning Your GroupWise System

The GroupWise Installation Wizard helps you install the GroupWise software on GroupWise servers. The GroupWise Installation console helps you create domains and post offices and configure the GroupWise agents.

Print the following worksheets and fill them out as you plan your GroupWise system:

- ☐ Simple, single-server GroupWise system

[Simple GroupWise System Worksheet](#)

- ☐ Typical, multiple-server GroupWise system

[Primary Domain Worksheet](#)

[Secondary Domain Worksheet](#) (one for each secondary domain)

[Post Office Worksheet](#) (one for each post office)

The topics in this section present the required information in a convenient planning sequence. The worksheets organize the information in the order in which you need it during installation and setup. As you review the planning information, record the specific details for your GroupWise system on the appropriate worksheet.

8.1 Planning GroupWise System Information

To identify your GroupWise system as a whole, the Installation console prompts you for the following information:

- ♦ [GroupWise System Name](#)
- ♦ [GroupWise Internet Domain Name](#)

8.1.1 GroupWise System Name

You must provide a name for your GroupWise system. The system name can be your company name (for example, Novell), GroupWise, or anything else that fits the naming scheme you want to use. The system name is displayed only in the Admin console, so any characters can be used. You cannot change the name after your GroupWise system is created.

WORKSHEET

Under **System Settings**, specify the name for your GroupWise system.

8.1.2 GroupWise Internet Domain Name

Your GroupWise system also needs an Internet domain name. The Internet domain name is used after the @ sign in GroupWise users' email addresses. You should already have obtained an Internet domain name from your Internet service provider (ISP).

WORKSHEET

Under **GroupWise System Settings**, specify the Internet domain name.

Under **Create Internet Agent**, specify the host name of the GWIA server as it appears in its DNS record.

8.2 Planning a Domain

The primary domain functions as the main administration unit for your GroupWise system.

In a simple, single-server GroupWise system, the primary domain owns one or more post offices and a GWIA. In a typical, multiple-server GroupWise system, the primary domain can function as a hub for the secondary domains where post offices and GWIAs are located, or it can own post offices that are located on other servers.

As you create a domain, the Installation console prompts you for the following information about the domain:

- ♦ [Domain Server](#)
- ♦ [Domain Name](#)
- ♦ [Domain Folder](#)
- ♦ [Domain Language](#)
- ♦ [Domain Time Zone](#)
- ♦ [Domain Link \(Secondary Domain Only\)](#)
- ♦ [Agents for the Domain](#)
- ♦ [Administrator Access for Domain Creation](#)

8.2.1 Domain Server

You can create a domain on Linux or Windows. Your GroupWise system can include both Linux servers and Windows servers.

WORKSHEET

Under **Platform**, mark the operating system (Linux or Windows) that you plan to use for the domain.

Under **Host**, specify the IP address or DNS hostname of the server where you plan to create the domain.

8.2.2 Domain Name

The name of the primary domain might reflect a company name (such as Novell). The name of a secondary domain might reflect a location (such as Provo), a department (such as Engineering), or some other element that makes sense for your organization. The name is used as the Domain object's name in the Admin console.

The name should consist of a single string. Do not use any of the characters listed in [Section C.1, "Invalid Characters in GroupWise Object Names,"](#) on page 209.

WORKSHEET

Under **Domain Settings**, specify the domain name.

8.2.3 Domain Folder

The domain requires a folder structure in which to store database files and temporary files that are created during message routing. If you want, the folder name can reflect the domain name you chose.

You must specify an empty folder. If the folder does not already exist, it is automatically created. The installation process can proceed more smoothly if you create the folder in advance.

Use the following platform-specific naming conventions for the folder name:

Linux: Use only lowercase characters.

Windows: No limitations.

WORKSHEET

Under **Domain Settings**, specify the full path for the domain folder.

8.2.4 Domain Language

The domain language determines the sort order for object lists in the Admin console. The primary domain language becomes the default language for secondary domains. The owning domain language becomes the default language for the domain's post offices.

WORKSHEET

Under **Primary Domain Settings**, specify the language for the domain.

NOTE: The languages listed for selection in the Installation console includes more languages than GroupWise supports. See ["Multilingual GroupWise Systems"](#) in the *GroupWise 2014 R2 Administration Guide* for a list of valid languages.

8.2.5 Domain Time Zone

When a message is sent from a user in one time zone to a user in another time zone, GroupWise adjusts the message's time so that it is correct for the recipient's time zone. For example, if a user in New York (GMT -05:00, Eastern Time) schedules a user in Los Angeles (GMT -08:00, Pacific Time) for a conference call at 4:00 p.m. Eastern Time, the appointment is scheduled in the Los Angeles user's calendar at 1:00 p.m. Pacific Time.

The primary domain time zone becomes the default time zone for secondary domains. The owning domain time zone becomes the default time zone for the domain's post offices.

WORKSHEET

Under **Domain Settings**, specify the time zone for the domain.

8.2.6 Domain Link (Secondary Domain Only)

When you add a new domain to your GroupWise system, links define how messages are routed from one domain to another. When you add the first secondary domain, the links between the primary and secondary domains are very simple. As the number of domains grows, the links among them can become quite complex. For more information, see “[Managing the Links between Domains and Post Offices](#)” in the *GroupWise 2014 R2 Administration Guide*.

SECONDARY DOMAIN WORKSHEET

Under **Domain Settings**, specify the domain that you want to link the new secondary domain to.

8.2.7 Agents for the Domain

Two agents run for a domain. As you configure the agents for the domain, the Installation console prompts you for the following information:

- ♦ [MTA Configuration](#)
- ♦ [GWIA Configuration](#)

The agent consoles are automatically available in the GroupWise Admin console. The agents are configured to start automatically when the server restarts.

MTA Configuration

The Message Transfer Agent (MTA) transfers messages between post offices and domains, and performs a variety of other functions in the domain.

The MTA requires a TCP/IP connection with POAs in the domain and with MTAs in other domains. In order to configure the MTA, you need to plan the following port numbers:

- ♦ **Message Transfer Protocol Port:** Used to communicate with the POA. The default MTP port for the MTA is 7100.
- ♦ **HTTP Port:** Used to communicate with your web browser to provide the MTA console. The default HTTP port for the MTA is 7180.

Use the default port number unless it is already in use on the server.

WORKSHEET

Under **MTA Settings**, specify the required port numbers.

For a complete list of default port numbers used by the GroupWise agents, see “[GroupWise Port Numbers](#)” in the *GroupWise 2014 R2 Administration Guide*.

GWIA Configuration

The Internet Agent (GWIA) converts GroupWise messages into SMTP format and transfers them to the Internet SMTP hosts where recipients are located. In reverse, it receives SMTP messages from Internet SMTP hosts and converts them into GroupWise format. The GWIA can also provide access for POP3 and IMAP4 clients to access GroupWise mailboxes.

The GWIA requires that you provide the fully qualified Internet hostname of the server where the GWIA runs, such as `gwia.example.com`, or the name of the "A record" in your DNS table that associates the hostname with the server's IP address.

WORKSHEET

Under **Create Internet Agent**, specify the hostname of the GWIA server as it appears in its DNS record if you want to run the GWIA for this domain.

As your GroupWise system grows, you might want to set up a standalone GWIA in a domain that does not own post offices.

8.2.8 Administrator Access for Domain Creation

The GroupWise Administration Service provides the GroupWise Administration console for managing your GroupWise system. For background information, see [Section 3.2, “Administration Service Architecture,” on page 22](#).

As you configure the domain, the Installation console prompts you for the following information:

- ♦ [Domain Admin Port](#)
- ♦ [Primary Domain: Super Admin Creation](#)
- ♦ [Secondary Domain: Primary Domain Access](#)

Domain Admin Port

An instance of the Admin Service runs on each GroupWise domain server so that you can access the Admin console at the following URL:

`https://domain_server_address:9710/gwadmin-console`

Replace *domain_server_address* with the IP address or DNS hostname of the domain server. The default Admin port for a domain is 9710.

The Admin Service also uses the Admin port to communicate with the MTA for the domain.

WORKSHEET

Under **MTA Settings**, specify the Admin port for the domain.

Use the default port number unless it is already in use on the server.

Primary Domain: Super Admin Creation

When you create the primary domain of a new GroupWise system, you create a GroupWise Super Admin user. The Super Admin has all administrative rights throughout your GroupWise system. The Super Admin can designate other Admin users with lesser rights, perhaps for specific domains or post offices. For more information, see “[GroupWise Administrators](#)” in the *GroupWise 2014 R2 Administration Guide*.

WORKSHEET

Under **Credential Settings**, specify the name for the GroupWise Super Admin user and the accompanying password.

If you need to reset the Super Admin password at a later time, you can use the GroupWise Administration utility (GWAdminUtil). For more information, see “[Using the GroupWise Administration Utility](#)” in the *GroupWise 2014 R2 Administration Guide*.

Secondary Domain: Primary Domain Access

When you create a secondary domain, you must be the GroupWise Super Admin or a GroupWise system administrator, and know the associated password. For more information, see “[GroupWise Administrators](#)” in the *GroupWise 2014 R2 Administration Guide*.

WORKSHEET

Under **System Settings**, specify the administrator user name and password that provide access to the primary domain in the Admin console.

You also need to know the network address of the primary domain server and the Admin port number for the domain. You must be connected to the primary domain in order to create a secondary domain.

WORKSHEET

Under **System Settings**, specify the IP address or DNS hostname of the primary domain server and the Admin port.

8.3 Planning a Post Office

A post office contains users' mailboxes. Like a domain, a post office requires a name and has a folder structure.

As you create the post office, the Installation console prompts you for the following information:

- ♦ [Post Office Server](#)
- ♦ [Post Office Name](#)
- ♦ [Post Office Folder](#)
- ♦ [Post Office Language](#)
- ♦ [Post Office Time Zone](#)
- ♦ [Agents in the Post Office](#)
- ♦ [Administrator Access for Post Office Creation](#)

8.3.1 Post Office Server

You can create a post office on Linux or Windows. Your GroupWise system can include both Linux servers and Windows servers.

WORKSHEET

Under **Platform**, mark the operating system (Linux or Windows) that you plan to use for the post office.

Under **Host**, specify the IP address or DNS hostname of the server where you plan to create the post office.

8.3.2 Post Office Name

A post office, like a domain, requires a unique name. The name can reflect any element that makes sense for your organization. For example, you could use a location (such as Provo) or a department (such as Engineering).

The name is used as the Post Office object's name in the Admin console. It can appear in the GroupWise Address Book.

The name should consist of a single string. Do not use any of the characters listed in [Section C.1, "Invalid Characters in GroupWise Object Names,"](#) on page 209.

WORKSHEET

Under **Post Office Settings**, specify the post office name.

8.3.3 Post Office Folder

A post office requires a folder structure in which to store database files and temporary files that are created during message routing and delivery. If you want, the folder name can reflect the post office name you chose.

You must specify an empty folder. If the folder does not already exist, it is automatically created. The installation process can proceed more smoothly if you create the folder in advance.

Use the following platform-specific naming conventions for the folder name:

Linux: Use only lowercase characters.

Windows: No limitations.

WORKSHEET

Under **Post Office Settings**, specify the full path for the post office folder.

8.3.4 Post Office Language

The post office language determines the sort order for items in the GroupWise Address Book.

The post office assumes the same language as its domain unless you specify otherwise. For example, if you set the domain and post office language to English, the GroupWise Address Book items are sorted according to English sort order rules. This is true even if some users in the post office are running non-English GroupWise clients such as German or Japanese. Their client interface and help files are in German or Japanese, but the sort order in the GroupWise Address Book is according to English standards. Time, date, and number formats for the non-English clients default to the workstation language.

WORKSHEET

Under **Post Office Settings**, specify the language for the post office.

NOTE: The languages listed for selection in the Installation console includes more languages than GroupWise supports. See “[Multilingual GroupWise Systems](#)” in the *[GroupWise 2014 Administration Guide](#)* for a list of valid languages.

8.3.5 Post Office Time Zone

When a message is sent from a user in one time zone to a user in another time zone, GroupWise adjusts the message’s time so that it is correct for the recipient’s time zone. For example, if a user in New York (GMT -05:00, Eastern Time) schedules a user in Los Angeles (GMT -08:00, Pacific Time) for a conference call at 4:00 p.m. Eastern Time, the appointment is scheduled in the Los Angeles user’s calendar at 1:00 p.m. Pacific Time.

In a simple, single-server GroupWise system, the post office is automatically created with the same time zone as the primary domain. In a typical, multiple-server GroupWise system, the post office time zone defaults to the domain time zone, but you can change it as you create the post office.

WORKSHEET

Under **Post Office Settings**, specify the time zone where the post office is located.

8.3.6 Agents in the Post Office

Two agents run for a post office. As you configure the agents for the post office, the Installation console prompts you for the following information:

- ♦ [POA Configuration](#)
- ♦ [DVA Configuration](#)

The agent consoles are automatically available in the GroupWise Admin console. The agents are configured to start automatically when the server restarts.

POA Configuration

The Post Office Agent (POA) responds to GroupWise client requests for mailbox data and delivers messages between users' mailboxes in a post office. The POA also communicates with the MTA to route messages to and from the post office. In addition, the POA performs a variety of maintenance tasks in the post office.

The POA requires a TCP/IP connection with the domain's MTA. It also requires TCP/IP connections with GroupWise clients. In order to configure the POA, you need to plan the following port numbers:

- ♦ **Client/Server Port:** Used to communicate with GroupWise clients. The default client/server port is 1677.
- ♦ **Message Transfer Port:** Used to communicate with the MTA. The default MTP port for the POA is 7101.
- ♦ **HTTP Port:** Used to communicate with your web browser to provide the POA console. The default HTTP port for the POA is 7181.
- ♦ **SOAP Port:** Used to communicate with SOAP clients such as WebAccess and the GroupWise Mobility Service. The default SOAP port for the POA is 7191.

Use the default port number unless it is already in use on the server.

WORKSHEET

Under **POA Settings**, specify the required port numbers.

For a complete list of default port numbers used by the GroupWise agents, see "[GroupWise Port Numbers](#)" in the *[GroupWise 2014 Administration Guide](#)*.

DVA Configuration

The Document Viewer Agent (DVA) converts attached document files from a wide variety of formats into HTML format for indexing by the POA and for viewing in GroupWise WebAccess. You can run up to three DVAs to service conversion requests for a single instance of the POA. Each DVA must be installed on a different server.

The DVA requires a TCP/IP connection with a POA. The default DVA port is 8301. Typically, the DVA is set up along with a post office.

WORKSHEET

Under **Create Document Viewer Agent**, mark **Yes** or **No**.

If you need to create a DVA on a server that does not have a post office and POA on it, see “[Scaling Your DVA Installation](#)” in the *GroupWise 2014 R2 Administration Guide*.

8.3.7 Administrator Access for Post Office Creation

In order to create a new post office, you need access to the owning domain.

- ♦ [Owning Domain Access](#)
- ♦ [Post Office Admin Port](#)

Owning Domain Access

When you create a post office, you must be the GroupWise Super Admin, a GroupWise system administrator, or a domain administrator for the owning domain, and you must know the associated password. For more information, see “[GroupWise Administrators](#)” in the *GroupWise 2014 R2 Administration Guide*.

WORKSHEET

Under **System Settings**, specify the administrator user name and password that provide access to the owning domain in the Admin console.

You also need to know the network address of the primary domain server or the owning domain server, and the Admin port number for the domain.

WORKSHEET

Under **System Settings**, specify the IP address or DNS hostname of the domain server and the Admin port for the domain.

Post Office Admin Port

An instance of the Admin Service runs on each GroupWise post office server. You never use this port when you connect to the Admin console, but the Admin Service uses it to communicate with the POA for the post office. The default Admin port for a post office is 9711.

WORKSHEET

Under **POA Settings**, specify the Admin port for the post office.

Use the default port number unless it is already in use on the server.

8.4 Planning Users

When you create a new GroupWise system, you can manually add a few users in order to test your new system. When you see that everything is working smoothly, you can add all of the users to your GroupWise system.

For a simple, single-server GroupWise system, you might want to add the users to the internal GroupWise directory. For a larger number of users, you can import them from an LDAP directory such as NetIQ eDirectory or Microsoft Active Directory.

8.4.1 Manually Created Users

You manually create GroupWise users in the Admin console. You can manually create users specifically for testing a new GroupWise system, or you can initially create users in the internal GroupWise directory and then later associate them with users in an LDAP directory.

WORKSHEET

Under **Users**, list any users that you want to create for testing purposes in your new GroupWise system.

8.4.2 Imported Users

In order to import users from an LDAP directory into GroupWise, you need to gather the following information about the LDAP directory so that GroupWise agents can access it:

- ♦ **Type:** NetIQ eDirectory or Microsoft Active Directory.
- ♦ **Address:** The IP address or DNS hostname of the LDAP server.
- ♦ **Port:** 636 if the LDAP server requires SSL; 389 if SSL is not required.
- ♦ **SSL Certificate:** The location of the LDAP root certificate file on the LDAP server.
- ♦ **LDAP User:** The user name for accessing the LDAP directory.

The user must have sufficient rights to read the LDAP User and Group objects that you plan to import. Specify the information in the format used by the LDAP server. For example:

```
cn=user_name,ou=org_unit,o=organization|  
cn=user_name,ou=users,dc=server_name,dc=company_name,dc=com
```

- ♦ **Password:** The password for the LDAP user.
- ♦ **Base DN:** (Optional) The LDAP context under which User and Group objects are located.

You must also establish a name for the LDAP directory to be known in your GroupWise system. The name should be clear and easy to remember, especially if you plan to have multiple GroupWise administrators.

WORKSHEET

Under **LDAP Directory Information**, specify the name for the LDAP directory and list the required information for connecting to the LDAP server.

8.5 GroupWise System Worksheets

- ♦ [Section 8.5.1, “Simple GroupWise System Worksheet,” on page 52](#)
- ♦ [Section 8.5.2, “Primary Domain Worksheet,” on page 54](#)
- ♦ [Section 8.5.3, “Secondary Domain Worksheet,” on page 54](#)
- ♦ [Section 8.5.4, “Post Office Worksheet,” on page 55](#)

8.5.1 Simple GroupWise System Worksheet

Installation Console Field	Value for Your Simple GroupWise System	Explanation
Platform		“Domain Server” on page 42
	<ul style="list-style-type: none">♦ Linux♦ Windows	
Folders		“Domain Folder” on page 43
	<ul style="list-style-type: none">♦ Domain folder♦ Post office folder	“Post Office Folder” on page 47
System Settings		“GroupWise System Name” on page 41
	<ul style="list-style-type: none">♦ System Name♦ Internet Domain Name♦ Host	“GroupWise Internet Domain Name” on page 42
	<ul style="list-style-type: none">♦ IP address♦ DNS hostname	“Domain Server” on page 42
Primary Domain Settings		“Planning a Domain” on page 42
	<ul style="list-style-type: none">♦ GroupWise Domain Name♦ Domain Folder♦ Language♦ Time zone	
MTA Settings		“MTA Configuration” on page 44
	<ul style="list-style-type: none">♦ MTP Port <p>(default 7100)</p>	“Domain Admin Port” on page 45
	<ul style="list-style-type: none">♦ HTTP Port <p>(default 7180)</p>	
	<ul style="list-style-type: none">♦ Admin Port <p>(default 9710)</p>	
Create Internet Agent		“GWIA Configuration” on page 45
	<ul style="list-style-type: none">♦ Hostname/DNS “A Record” Name	
Create Post Office		“Planning a Post Office” on page 47
	<ul style="list-style-type: none">♦ Post Office Name♦ Post Office Folder	
Create Document Viewer Agent		“DVA Configuration” on page 49
	<ul style="list-style-type: none">♦ Yes♦ No	

Installation Console Field	Value for Your Simple GroupWise System	Explanation
POA Settings		“POA Configuration” on page 49
♦ Client/Server Port (default 1677)		“Post Office Admin Port” on page 50
♦ MTP Port (default 7101)		
♦ HTTP Port (default 7181)		
♦ SOAP Port (default 7191)		
♦ Admin Port (default 9711)		
Credential Settings		“Primary Domain: Super Admin Creation” on page 46
♦ Admin Name		
♦ Password		
Users		“Planning Users” on page 50
♦ GroupWise Directory		
♦		
♦		
♦ LDAP Directory		
♦ eDirectory		
♦ Active Directory		
LDAP Directory Information		“Imported Users” on page 51
♦ Name		
♦ Type		
♦ eDirectory		
♦ Active Directory		
♦ Address		
♦ Port		
♦ Use SSL		
♦ No		
♦ Yes		
SSL Certificate		
♦ LDAP User		
♦ LDAP User Password		

8.5.2 Primary Domain Worksheet

Installation Console Field	Value for the Primary Domain	Explanation
Primary Domain Platform <ul style="list-style-type: none">♦ Linux♦ Windows		“Domain Server” on page 42
Primary Domain Folder <ul style="list-style-type: none">♦		“Domain Folder” on page 43
System Settings <ul style="list-style-type: none">♦ System Name♦ Internet Domain Name♦ Host<ul style="list-style-type: none">♦ IP address♦ DNS hostname		“GroupWise System Name” on page 41 “GroupWise Internet Domain Name” on page 42 “Domain Server” on page 42
Domain Settings <ul style="list-style-type: none">♦ GroupWise Domain Name♦ Domain Folder♦ Language♦ Time zone		“Planning a Domain” on page 42
MTA Settings <ul style="list-style-type: none">♦ MTP Port (default 7100)♦ HTTP Port (default 7180)♦ Admin Port (default 9710)		“MTA Configuration” on page 44 “Domain Admin Port” on page 45
Credential Settings <ul style="list-style-type: none">♦ Admin Name♦ Password		“Primary Domain: Super Admin Creation” on page 46

8.5.3 Secondary Domain Worksheet

Installation Console Field	Value for the Secondary Domain	Explanation
Domain Platform <ul style="list-style-type: none">♦ Linux♦ Windows		“Domain Server” on page 42

Installation Console Field	Value for the Secondary Domain	Explanation
Domain Folder		"Domain Folder" on page 43
♦		
System Settings		Secondary Domain: Primary Domain Access
♦ Primary Domain Host		
♦ Primary Domain Admin Port		
♦ Admin Name		
♦ Password		
Domain Settings		"Planning a Domain" on page 42
♦ GroupWise Domain Name		
♦ Domain Folder		
♦ Host		
♦ Link to Domain		
♦ Language		
♦ Time zone		
MTA Settings		"MTA Configuration" on page 44
♦ MTP Port		"Domain Admin Port" on page 45
(default 7100)		
♦ HTTP Port		
(default 7180)		
♦ Admin Port		
(default 9710)		
Create Internet Agent		"GWIA Configuration" on page 45
♦ Hostname/DNS "A Record" Name		

8.5.4 Post Office Worksheet

Installation Console Field	Value for the Post Office	Explanation
Post Office Platform		"Post Office Server" on page 47
♦ Linux		
♦ Windows		
Post Office Folder		"Post Office Folder" on page 47
♦		

Installation Console Field	Value for the Post Office	Explanation
System Settings		“Owning Domain Access” on page 50
<ul style="list-style-type: none"> ♦ Owning Domain Host ♦ Owning Domain Admin Port ♦ Admin Name ♦ Password 		
Post Office Settings		“Planning a Post Office” on page 47
<ul style="list-style-type: none"> ♦ Post Office Name ♦ Host ♦ Post Office Folder ♦ Language ♦ Time zone 		
Create Document Viewer Agent		“DVA Configuration” on page 49
<ul style="list-style-type: none"> ♦ Yes ♦ No 		
POA Settings		“POA Configuration” on page 49
<ul style="list-style-type: none"> ♦ Client/Server Port (default 1677) ♦ MTP Port (default 7101) ♦ HTTP Port (default 7181) ♦ SOAP Port (default 7191) ♦ Admin Port (default 9711) 		“Post Office Admin Port” on page 50
Users		“Planning Users” on page 50
<ul style="list-style-type: none"> ♦ GroupWise Directory <ul style="list-style-type: none"> ♦ ♦ ♦ LDAP Directory <ul style="list-style-type: none"> ♦ eDirectory ♦ Active Directory 		

Installation Console Field	Value for the Post Office	Explanation
LDAP Directory Information		Section 8.4.2, "Imported Users," on page 51
♦ Name		
♦ Type		
♦ eDirectory		
♦ Active Directory		
♦ Address		
♦ Port		
♦ Use SSL		
♦ No		
♦ Yes		
SSL Certificate		
♦ LDAP User		
♦ LDAP User Password		

9 Installing the GroupWise Server Software

You should have already reviewed [Chapter 8, “Planning Your GroupWise System,” on page 41](#) and filled out the appropriate [GroupWise System Worksheets](#). The following sections step you through using the GroupWise Installation Wizard to install the GroupWise Server software.

9.1 Linux: Installing the GroupWise Server Software

9.1.1 Preparing the Linux Server for Your GroupWise System

- 1 Ensure that the server for your GroupWise system meets the system requirements listed in [Chapter 4, “GroupWise Administration Requirements,” on page 27](#).
- 2 Ensure that the Linux operating system media is available, either physically or in a repository, in case the Installation Wizard needs to install supporting packages on the Linux server.
- 3 Ensure that the server has a static IP address.
- 4 (Optional) Ensure that the folders exist where you want to create your domain and post office folder structures, as described in [“Domain Folder” on page 43](#) and [“Post Office Folder” on page 47](#).
- 5 Continue with [Running the Linux GroupWise Installation Wizard](#).

9.1.2 Running the Linux GroupWise Installation Wizard

- 1 Download and extract the GroupWise 2014 R2 software to a temporary location on your server.
- 2 In a terminal window, become `root` by entering `su -` and the `root` password.
- 3 Browse to the location of the extracted software, and run the following command to start the install:

```
./install.sh
```

- 4 Type the number for the language in which you want to run the GroupWise Installation Wizard, then press Enter to select **OK**.
- 5 (Optional) Type **1** for **Documentation**, then press Enter to review the Readme, Quick Start, and Installation Guide to better prepare yourself for the installation.
- 6 Type **2** for **Installation**, then press Enter.
- 7 Type **a** to accept the License Agreement and display the Software list.
- 8 Type **1** for **GroupWise Server**, then press Enter to display the Actions list.
- 9 Type **1** for **Install**, then press Enter to install the GroupWise Server component.

The packages for the GroupWise Server component (Admin Service and agents) are installed on the server. If any supporting packages are not available on the server, the Installation Wizard automatically installs them from the operating system media.

- 10 When the installation is finished, press any key to return to the Installation Options list.

All of the GroupWise agents are installed on every GroupWise server. The MTA and, optionally, the GWIA are configured to run on a domain server. The POA and the DVA are configured to run on a post office server.

- 11 Type 2 for **Configure**, then press Enter to start the GroupWise Admin Service and display instructions for accessing the Installation console to create a new GroupWise system.
- 12 Right-click the URL under **To install or configure a new GroupWise server**, then click **Open Link** to open your web browser.

If your web browser does not offer this functionality, open your web browser, then copy the URL into it.

- 13 Accept the self-signed certificate that the Installation Wizard has automatically provided for accessing the Installation console.

The browser session will then authorize for the next hour to perform installation console tasks. If the browser does not automatically authorize the session, you must manually authorize it by running in a terminal the **gwsadmin-ipc authorize** command specified in your web browser.

- 14 Continue with the instructions for the type of GroupWise system that you want to create:

- ♦ [Chapter 10, “Creating a Simple GroupWise System,” on page 63](#)
- ♦ [Chapter 11, “Creating a Typical GroupWise System,” on page 65](#)

9.2 Windows: Installing the GroupWise Server Software

You should have already reviewed [Chapter 8, “Planning Your GroupWise System,” on page 41](#) and filled out the appropriate [GroupWise System Worksheets](#). The following sections step you through using the GroupWise Installation Wizard to install the GroupWise Server software.

9.2.1 Preparing the Windows Server

- 1 Ensure that the server for your GroupWise system meets the system requirements listed in [Chapter 4, “GroupWise Administration Requirements,” on page 27](#).
- 2 Ensure that the server has a static IP address.
- 3 Ensure that the firewall on the server has the ports open that are used by the GroupWise agents.
For assistance, see [“GroupWise Port Numbers”](#) in the *GroupWise 2014 R2 Administration Guide*.
- 4 (Optional) Ensure that the folders exist where you want to create your domain and post office folder structures, as described in [“Domain Folder” on page 43](#) and [“Post Office Folder” on page 47](#).
- 5 Continue with [Running the Windows GroupWise Installation Wizard](#).

9.2.2 Running the Windows GroupWise Installation Wizard

- 1 Log in to Windows as an Administrator-equivalent user.
- 2 Download and extract the contents of the GroupWise 2014 R2 software to a temporary location on your server.

- 3 Run `setup.exe` at the root of the extracted GroupWise software to start the GroupWise Installation Wizard.
- 4 (Optional) Review the Readme, Quick Start, and Installation Guide to better prepare yourself for the installation.
- 5 Click **GroupWise Server** to install the GroupWise Server component.
- 6 Select the language in which you want to perform the installation, then click **OK** to start the GroupWise Server Setup Wizard.
- 7 Click **Next** to continue.
- 8 Accept the **License Agreement**, then click **Next** to display the Custom Setup page.

The following components are available for installation:

- ♦ **GroupWise Server:** (Required) Consists of the Admin Service, the POA, the MTA, the GWIA, and the DVA.
All of the GroupWise agents are installed on every GroupWise server. The MTA and, optionally, the GWIA are configured to run on a domain server. The POA and the DVA are configured to run on a post office server.

- ♦ **Client Auto-Update Repository:** (Optional) Helps you distribute the GroupWise client software to users' Windows workstations.

For usage instructions, see ["Using Client Auto-Update to Distribute the GroupWise Client Software"](#) in the *GroupWise 2014 R2 Administration Guide*.

- 9 (Optional) Click **Browse** to change the default location where the GroupWise software is installed.
- 10 Click **Next** to continue, then click **Install** to install the GroupWise software.
- 11 When the GroupWise software has been installed, click **Finish** to return to the main page of the Installation Wizard, then close the Installation Wizard.

The Installation Wizard has created two new icons on your Windows desktop.

- 12 On your Windows desktop, double-click **GroupWise Install** to open your web browser and access the Installation console.

This starts the GroupWise Admin Service and launches the GroupWise Installation console in your web browser.

After installation, use **GroupWise Admin Console** to access the Admin console for ongoing GroupWise system administration.

- 13 Accept the self-signed certificate that the Installation Wizard has automatically provided for accessing the Installation console.

The browser session will then authorize for the next hour to perform installation console tasks. If the browser does not automatically authorize the session, you must manually authorize it by running in a command prompt the `gwadmin-ipc authorize` command specified in your web browser.

- 14 Continue with the instructions for the type of GroupWise system that you want to create:

- ♦ [Chapter 10, "Creating a Simple GroupWise System," on page 63](#)
- ♦ [Chapter 11, "Creating a Typical GroupWise System," on page 65](#)

10 Creating a Simple GroupWise System

Before you create your simple GroupWise system, you should have reviewed the following sections and completed the associated tasks:

- ☐ [“GroupWise System Overview” on page 37](#)
- ☐ [“Planning Your GroupWise System” on page 41](#)
- ☐ [“Simple GroupWise System Worksheet” on page 52](#)
- ☐ [“Installing the GroupWise Server Software” on page 59](#)

You are ready to use the Installation console to create your simple GroupWise system.

IMPORTANT: As a security feature, the Installation console times out after one hour. For instructions to renew the session, see [Section 11.4, “Handling an Installation Timeout,” on page 68](#).

- 1 In the GroupWise Installation console, click **Create a New GroupWise System** to display the System Settings page.
- 2 Fill in the following fields from the [Simple GroupWise System Worksheet](#):

[System Name](#)

[Internet Domain Name](#)

[Host](#)

[GroupWise Domain Name](#)

[Domain Folder](#)

[Language](#)

[Time Zone](#)

MTA Settings

[MTA MTP Port](#)

[MTA HTTP Port](#)

[Admin Port](#)

Internet Agent Settings

[Create Internet Agent](#)

[Hostname/DNS “A Record” Name](#)

Post Office Settings

[Create Post Office](#)

[Post Office Name](#)

[Post Office Folder](#)

[Create Document Viewer Agent](#)

[POA Client/Server Port](#)

[POA HTTP Port](#)

[POA MTP Port](#)

[Admin Port](#)

You can click **Help** for more information about the fields.

- 3 Click **Next** to display the Credential Settings page:
- 4 Fill in the following fields from the [Simple GroupWise System Worksheet](#):

 [Admin Name](#)
 [Password](#)

 You can click **Help** for more information about the fields.
- 5 Click **Next** to display the Summary page.
- 6 Review the information that you have provided, then click **Finish** to create your simple GroupWise system.
- 7 Click **GroupWise Administration Console** to log in to the GroupWise Admin console.
- 8 Specify the GroupWise Super Admin user name and password, then click **Login**.
- 9 Continue with [Chapter 12, "Adding Users to Your GroupWise System,"](#) on page 71.

11 Creating a Typical GroupWise System

Before you create your GroupWise system, you should have reviewed the following sections and completed the associated tasks:

- ☐ “GroupWise System Overview” on page 37
- ☐ “Planning Your GroupWise System” on page 41
- ☐ “Primary Domain Worksheet” on page 54
- ☐ “Secondary Domain Worksheet” on page 54
- ☐ “Post Office Worksheet” on page 55
- ☐ “Installing the GroupWise Server Software” on page 59

You are now ready to create your GroupWise system.

IMPORTANT: If you plan to install GroupWise in a clustered server environment, see “[Clustering](#)” the *GroupWise 2014 R2 Interoperability Guide* before starting to set up your GroupWise system.

11.1 Creating the Primary Domain

When you are finished installing the GroupWise Server software, the Installation Wizard automatically displays the GroupWise Installation console.

IMPORTANT: As a security feature, the Installation console times out after one hour. For instructions to renew the session, see [Section 11.4, “Handling an Installation Timeout,”](#) on page 68.

- 1 In the GroupWise Installation console, click **Create a New GroupWise System** to display the System Settings page.

NOTE: The following steps assume that you do not want to run the Internet Agent in the primary domain and that you do not want to create a post office on the same server with the primary domain.

- 2 Fill in the following fields from the [Primary Domain Worksheet](#):

System Name

Internet Domain Name

Host

GroupWise Domain Name

Domain Folder

Language

Time Zone

MTA Settings

MTA MTP Port

MTA HTTP Port

Admin Port

You can click **Help** for more information about the fields.

- 3 Click **Next** to display the Credential Settings page:
- 4 Fill in the following fields from the [Primary Domain Worksheet](#):

Admin Name

Password

You can click **Help** for more information about the fields.

- 5 Click **Next** to display the Summary page.
- 6 Review the information that you have provided, then click **Finish** to create the primary domain for your GroupWise system.
- 7 (Optional) Click **GroupWise Administration Console** to display the GroupWise Admin console and administer the domain.

For usage instructions, see [Chapter 13, "Working with the GroupWise Administration Console," on page 73](#).

- 8 Continue with the task that you want to do next:
 - ♦ [Section 11.2, "Adding a Secondary Domain," on page 66](#)
 - ♦ [Section 11.3, "Adding a Post Office," on page 67](#)

11.2 Adding a Secondary Domain

- 1 Install the GroupWise Server software on the domain server that you listed on the [Secondary Domain Worksheet](#).

For instructions, see [Chapter 9, "Installing the GroupWise Server Software," on page 59](#).

When you are finished installing the GroupWise Server software, the Installation Wizard automatically displays the GroupWise Installation console.

IMPORTANT: As a security feature, the Installation console times out after one hour. For instructions to renew the session, see [Section 11.4, "Handling an Installation Timeout," on page 68](#).

- 2 In the GroupWise Installation console, click **Add a New Domain** to display the System Settings page.
- 3 Fill in the following fields from the [Secondary Domain Worksheet](#):

Primary Domain Host

Primary Domain Admin Port

Admin Name

Password

You can click **Help** for more information about the fields.

- 4 Click **Next**.

Because no GroupWise software is yet installed on the new GroupWise server, the connection between it and the owning domain server is not yet trusted. This is normal.

- 5 Click **Trust Connection** to display the Domain Settings page.
- 6 Fill in the following fields from the [Secondary Domain Worksheet](#):

GroupWise Domain Name

[Domain Folder](#)
[Host](#)
[Link to Domain](#)
[Language](#)
[Time Zone](#)

MTA Settings

[MTA MTP Port](#)
[MTA HTTP Port](#)
[Admin Port](#)

Internet Agent Settings

[Hostname/DNS “A Record” Name](#) (optional)

You can click **Help** for more information about the fields.

- 7 Click **Next** to display the Summary page.
- 8 Review the information that you have provided, then click **Finish** to create a secondary domain in your GroupWise system.
- 9 (Optional) Click **GroupWise Administration Console** to display the GroupWise Admin console and administer the domain.

For usage instructions, see [Chapter 13, “Working with the GroupWise Administration Console,” on page 73](#).
- 10 Continue with [Adding a Post Office](#).

11.3 Adding a Post Office

- 1 Install the GroupWise Server software on the post office server that you listed on the [Post Office Worksheet](#).

For instructions, see [Chapter 9, “Installing the GroupWise Server Software,” on page 59](#).

When you are finished installing the GroupWise Server software, the Installation Wizard automatically displays the GroupWise Installation console.

IMPORTANT: As a security feature, the Installation console times out after one hour. For instructions to renew the session, see [Section 11.4, “Handling an Installation Timeout,” on page 68](#).

- 2 In the GroupWise Installation console, click **Add a New Post Office** to display the System Settings page.
- 3 Fill in the following fields from the [Post Office Worksheet](#):

[Owning Domain Host](#)
[Owning Domain Admin Port](#)
[Admin Name](#)
[Password](#)

You can click **Help** for more information about the fields.

- 4 Click **Next**.

Because no GroupWise software is yet installed on the new GroupWise server, the connection between it and the owning domain server is not yet trusted. This is normal.

5 Click **Trust Connection** to display the Post Office Settings page.

6 Fill in the following fields from the [Post Office Worksheet](#):

[Post Office Name](#)

[Host](#)

[Post Office Folder](#)

[Language](#)

[Time Zone](#)

POA Settings

[POA Client/Server Port](#)

[POA MTP Port](#)

[POA HTTP Port](#)

[Admin Port](#)

[Create Document Viewer Agent](#)

You can click **Help** for more information about the fields.

7 Click **Next** to display the Summary page.

8 Review the information that you have provided, then click **Finish** to create a new post office in your GroupWise system.

9 Click **GroupWise Administration Console** to display the GroupWise Admin console.

10 Continue with [Chapter 12, "Adding Users to Your GroupWise System,"](#) on page 71.

11.4 Handling an Installation Timeout

As a security feature, the Installation console times out after one hour. This helps prevent access by unauthorized persons if the Installation console is left unattended. When an installation session times out, you see the authorization page.

You then run the following command to obtain a new security token:

Linux: `/opt/novell/groupwise/admin/gwadmin-ipc authorize token_string`

Windows: `c:\Program Files\Novell\GroupWise Server\admin\gwadmin-ipc.exe
authorize token_string`

If the Timeout page does not provide a token string, use the following method to gain access to the Installation console:

Linux: Reselect **Configure** in the Installation Wizard to authorize the Installation console session.

Windows: Close the existing browser window.

Double-click **GroupWise Install** on the desktop to start a new authorized Installation console session.

11.5 Changing the Authentication Mode for the Installation Console

By default, the Installation console uses token-based authentication. After initial installation, you can change the authentication method as needed.

To configure the Installation console to prompt for a user name and password to allow access, use the following command:

```
gwadminutil installcfg -m user -u user_name -p
```

To configure the Installation console to not allow logins so that the configuration of your GroupWise system cannot be changed by unauthorized users, use the following command:

```
gwadminutil installcfg -m disabled
```

To re-enable logins, specify an authentication method:

```
gwadminutil installcfg -m token  
gwadminutil installcfg -m user -u user_name -p
```

12 Adding Users to Your GroupWise System

You can add users to your new GroupWise system by manually typing the user information or by importing the user information from an LDAP directory such as NetIQ eDirectory or Microsoft Active Directory. You use the Admin console for either approach. You need to create at least two users in order to test your new GroupWise system.

12.1 Manually Adding Users to the Internal GroupWise Directory

- 1 In the [GroupWise Admin console](#), click **Users > New**.
- 2 Specify the user's GroupWise user name, along with the user's first name and last name.
- 3 In the **Post Office** field, start typing the name of the post office to select it.
or
Select the post office from the drop-down list.
- 4 Select **Create Another User** to create at least one more user in your new GroupWise system.
For more detailed information about planning and adding users, see “[Creating GroupWise Accounts](#)” in the *[GroupWise 2014 R2 Administration Guide](#)*.
- 5 To provide additional information for each user, click **Users**, then click each user to display and edit the properties of each User object.
- 6 After you have created at least two users, continue with [Section 12.3, “Testing the Users,” on page 72](#).

12.2 Importing Users from an LDAP Directory

In order to add users to your new GroupWise system from an LDAP directory such as NetIQ eDirectory or Microsoft Active Directory, you must first provide configuration information about the LDAP directory, and then import the users.

12.2.1 Providing LDAP Directory Information

- 1 In the [GroupWise Admin console](#), click **System > LDAP Servers > New Directory**.
- 2 Fill in the following fields from the [Simple GroupWise System Worksheet](#) or the [Post Office Worksheet](#):
[Name](#)
[Type](#)
[Address](#)
[Port](#)
[SSL Certificate](#) (if needed)
[LDAP User](#)

LDAP User Password

Base DN (optional)

You can click **Help** for more information about the fields. For more detailed instructions, see “Setting Up an LDAP Directory” in the *GroupWise 2014 R2 Administration Guide*.

- 3 Click **Test Connection** to verify that you have specified the required information correctly.
- 4 Click **OK** to save the LDAP directory information and add the LDAP directory to the list of LDAP directories.
- 5 Click **Close** to close the list and return to the main Admin console window.
- 6 Continue with [Importing Users](#).

12.2.2 Importing Users

- 1 In the [GroupWise Admin console](#), click **System > User Import**.
- 2 Select the post office to import the users into.
- 3 Click **Preview** to list the users to import.
- 4 (Conditional) If there are individual users that you do not want to import, delete them from the list.
- 5 (Conditional) If the list is too long, use the **Context** and **LDAP Filter** fields to restrict the list, then click **Update Preview**.

You can click **Help** for more information about the fields.

- 6 When the list contains the correct set of users, click **Import Users** to perform the import.
- 7 Click **Close**.
- 8 To see that the users have been imported, click **Users**.
- 9 Continue with [Testing the Users](#).

12.3 Testing the Users

- 1 Install the GroupWise client in order to provide mailbox access on a Windows workstation.
See [Chapter 20, “Installing the GroupWise Client,” on page 153](#) for workstation system requirements and installation instructions.
- 2 Log in as each test user and exchange email messages in order to test the POA and the MTA.
- 3 Exchange email messages with colleagues whose email systems are across the Internet from your GroupWise system in order to test the GWIA.

13 Working with the GroupWise Administration Console

The GroupWise Administration console enables you to perform GroupWise administration anywhere you have a web browser and an Internet connection.

13.1 Accessing the Admin Console

When you complete a session in the Installation console, you can go immediately into the Admin console.

NOTE: If your installation session times out before you access the Admin console, see [Section 11.4, “Handling an Installation Timeout,”](#) on page 68.

To access the Admin console directly:

- 1 Click the Admin console icon on your desktop.

or

Enter the following URL in your web browser:

```
https://groupwise_server_address:admin_port/gwadmin-console
```

Replace *groupwise_server_address* with the IP address or DNS hostname of the GroupWise server. If you are not using the default Admin port, replace *admin_port* with the Admin port number. If you are using the default Admin port number, you do not need to specify it.

13.2 Making the Most of the System Overview

On the System Overview page, you can quickly view and configure all domains, post offices, and agents in your GroupWise system. The System Overview page also provides status information for all GroupWise agents, with easy access to their agent consoles and to the controls for starting and stopping them.

Domains are automatically added to the System Overview page when you create them.

- 1 If you do not want a specific domain to be displayed, simply close it.
- 2 To display it again, click **Options > Add Domains**.
- 3 Click a domain, post office, or agent to view its properties.

Agents display status indicators to show whether they are running.

To stop or start an agent:


- 1 Click **Running** or **Stopped**.
- 2 Click the name of the agent to display agent properties.

3 Click **Stop Agent** or **Start Agent**.

The agent consoles can also be displayed from the status icons and from the agent properties pages when the agents are running.

13.3 Finding Objects in Object Lists

Click any object type in the **Administration** panel to list all objects of that type in your GroupWise system.



13.4 Finding Frequently Used Objects Quickly

When you are not quite sure what you are looking for, the object lists available from the **Administration** panel can help you find it. After you have gone to the same object many times, there are faster ways to display the object that you want.

Global Search As you start typing in the **Global Search** field, the Admin console starts building a list of objects that match. When you see what you want, click the object in order to go to its property page.

Recent Every object that you go to is added to your **Recent** list, with the most recent object at the top of the list. This makes it very easy to return to any object that you have worked with recently.

Favorites Any object you go to can be added to your **Favorites** list. Click ☆ in the upper-right corner of any object property page to add it to your **Favorites** list. Favorite objects are alphabetized in the list so that your **Favorites** list has a predictable order.

A ★ on an object property page shows that it is on your **Favorites** list. Click ★ to remove that object from your **Favorites** list.

13.5 Working with Objects and Object Properties

You can edit the properties of any GroupWise objects that you have rights to modify. If you are logged in to the GroupWise Admin console as the GroupWise Super Admin, you can edit all objects. If you are logged in as a subordinate administrator, objects that you do not have rights to modify are dimmed. GroupWise tools on the System page are dimmed if you do not have rights to use them.

Usually, when you work with objects, your changes are saved immediately. Sometimes, changes need to replicate throughout your GroupWise system before the change is complete. When that happens, the object is dimmed and you cannot make further changes to the object until replication is finished.

13.6 Using System Tools

You can find all of the GroupWise system operations and object-specific utilities on the System page.

The System tools are described in detail in the [GroupWise 2014 R2 Administration Guide](#):

14 Working with the GroupWise Agents

The GroupWise agent software is automatically installed when you create domains and post offices. For a domain, you run the MTA and optionally the GWIA. For a post office, you run the POA and optionally the DVA. All of the agents are configured to automatically restart whenever the server restarts.

Basic agent monitoring and management is most easily performed on the System Overview page in the Admin console. For instructions, see [Section 13.2, “Making the Most of the System Overview,” on page 73](#).

For detailed configuration information about each agent, see the following sections in the *GroupWise 2014 R2 Administration Guide*:

- ♦ “[Post Office Agent](#)”
- ♦ “[Message Transfer Agent](#)”
- ♦ “[Internet Agent](#)”
- ♦ “[Document Viewer Agent](#)”

14.1 Linux: Managing the GroupWise Agents

Basic agent monitoring and management is most easily performed on the System Overview page in the Admin console. For instructions, see [Section 13.2, “Making the Most of the System Overview,” on page 73](#). Refer to the following additional tasks as you maintain all the GroupWise agents on Linux:

If you are new to Linux, you might want to review “[Linux Basics for GroupWise Administration](#)” in the *GroupWise 2014 Administration Guide* before you work with the GroupWise agents on Linux.

14.1.1 Manually Starting and Stopping the Linux GroupWise Agents

Starting and Stopping the Linux Agents as Services

- ♦ “[Using the grpwise Script](#)” on page 78
- ♦ “[Using the gwsc Command](#)” on page 78

Using the grpwise Script

All of the Linux GroupWise agents except the Monitor Agent can be started as services by using the `grpwise` script. The Monitor Agent uses its own customized `grpwise-ma` script that works essentially the same way. When the agents run as services, they do not have a user interface.

In the `grpwise` script, each agent is designated in terms of the name of the domain and post office associated with it, in the following format:

```
POA:      post_office.domain
MTA:      domain
GWIA:     gwia.domain
DVA:      gwdva
```

Use the following set of `rcgrpwise` commands to start and stop the agents as services and verify their status:

<code>rcgrpwise status</code>	Displays the status of the GroupWise agents that are configured to run on the server.
<code>rcgrpwise status agent_location_name</code>	Displays the status of the specified agent.
<code>rcgrpwise start</code> <code>rcgrpwise restart</code>	Starts/restarts the GroupWise agents that are configured to run on the server.
<code>rcgrpwise start agent_location_name</code> <code>rcgrpwise restart agent_location_name</code>	Starts/restarts the specified agent.
<code>rcgrpwise stop</code>	Stops the GroupWise agents that are configured to run on the server.
<code>rcgrpwise stop agent_location_name</code>	Stops the specified agent. If an agent does not respond to the <code>rcgrpwise stop</code> command, you can use the Linux <code>kill pid_number</code> command to stop it.
<code>rcgrpwise print</code>	Lists the contents of the <code>gwha.conf</code> file where the agents are configured. For information about the <code>gwha.conf</code> file, see Section 14.1.3, “Automatically Restarting the Linux GroupWise Agents with the GroupWise High Availability Service,” on page 83.

When the agents run without a user interface, you can monitor them by using their agent consoles. See [Section 14.3, “Monitoring the Agents from Your Web Browser,”](#) on page 92.

Using the gwsc Command

You can also manage the GroupWise agents by using the `gwsc` command, which is short for the `gwaadminutil services` command.

For the `gwsc` command, each agent is designated in terms of its object name or of the name of the domain and post office associated with it:

POA: `poa_object_name` or `post_office_name`
MTA: `mta_object_name` or `domain_name`
GWIA: `gwia_object_name`
DVA: `dva_object_name`

Use the following set of `gwsc` commands to start and stop the agents as services and verify their status:

<code>gwsc -query</code>	Displays the status of the GroupWise agents that are configured to run on the server.
<code>gwsc -query name</code>	Displays the status of the specified agent.
<code>gwsc -start</code>	Starts the GroupWise agents that are configured to run on the server.
<code>gwsc -start name</code>	Starts the specified agent.
<code>gwsc -stop</code>	Stops the GroupWise agents that are configured to run on the server.
<code>gwsc -stop name</code>	Stops the specified agent.
<code>gwsc -list</code>	Lists the agent services that are configured on the server.

Starting the Linux Agents with a User Interface for Troubleshooting

In general, you should run the Linux agents as services without a user interface, so that they can be managed in the Admin console.

Occasionally, when troubleshooting a problem that occurs at agent startup, the problem can occur before the agent console can be displayed and before error messages can be written to the agent log file. Under such circumstances, you can start an agent with a user interface in order to view any errors that the agent displays on the server console before the agent stops again.

IMPORTANT: When an agent is running with a user interface, it cannot be managed in the Admin console.

- 1 In a terminal window, become `root` by entering `su -` and the `root` password.
- 2 Change to the GroupWise agent bin directory.
`cd /opt/novell/groupwise/agents/bin`
- 3 Enter one of the following commands to start an agent with a user interface:

Syntax:

```
./gwpoa --show --home /post_office_folder &  
./gwmta --show --home /domain_folder &  
./gwia --show --home /gwia_folder &
```

Example:

```
./gwpoa --show --home /mail/polnx &  
./gwmta --show --home /mail/domlnx &  
./gwia --show --home /mail/domlnx/gwia &
```

The `--show` startup switch starts the agent with a server console interface. This user interface requires that the X Window System and Open Motif be running on the Linux server.

The `--home` startup switch specifies the directory that is required to start the agent.

The ampersand (&) causes the agent to run in the background, so that the terminal window you started it in is again available for use.

NOTE: The DVA cannot be started with a user interface.

14.1.2 Running the Linux GroupWise Agents as a Non-root User

For security reasons, it is preferable that the GroupWise agents do not run with `root` user privileges. For example, if an intruder manages to assume the identity of a GroupWise agent, the intruder gains all the privileges of the commandeered process. If the process is running with `root` user privileges, then the intruder has `root` access to your system. If the process is running as a user with minimal privileges, then the intruder has only restricted access to your system. Therefore, your system is more secure if the GroupWise agents do not run as `root`.

The `root` user still needs to start the agents, because the agents do need to access some `root`-only resources on startup. However, you can configure the agents to switch to a different user after they start. After the agents are running as the non-`root` user, they need adequate access to the locations where each domain, post office, and library is located.

- ♦ [“Setting Up Typical Non-root Access” on page 80](#)
- ♦ [“Setting Up Non-root Access on an NSS Volume on Novell Open Enterprise Server” on page 81](#)
- ♦ [“Changing the Non-root User” on page 82](#)

NOTE: You can configure the POA, MTA, and GWIA to run as a non-`root` user. The DVA must still run as `root`. Unlike the other agents, the Monitor Agent can be started as a non-`root` user by default, so no setup is required for it to run as a non-`root` user.

Setting Up Typical Non-root Access

To configure the GroupWise agents to switch users after startup:

- 1 Ensure that you are logged in as `root`.
- 2 Select a Linux user for the agents to run as, and ensure that the user is listed in the `/etc/passwd` file.

You might want to create a new user specifically for this purpose, perhaps named `gwagents`. The user name must not match any local user names on the Linux server.

IMPORTANT: All agents running on the same server must run as the same user.

- 3 Change to the `groupwise` folder under `/etc`:

```
cd /etc/opt/novell/groupwise
```

- 4 Create a new `agents` folder, then change to that folder:


```
mkdir agents
cd agents
```

- 5 Create a file named `uid.conf`.
- 6 Type the selected user name in the file, for example:

```
gwagents
```

- 7 Stop and then start the agents.

While starting as `root`, the agents automatically change the ownership of the domain and post office folder structures from `root` to the user you specified in the `uid.conf` file. Then they switch users and run as the user you specified, rather than as `root`.

IMPORTANT: The first time you start an agent as a non-`root` user (or if you change from one non-`root` user to another), the agent might take longer than usual to start, because of the change in ownership of the directories and files accessed by that agent. This is especially true of a POA that services a large post office and that requires access to a restore area, especially a restore area on a remote server.

- 8 (Optional) List the agent processes to see that they are no longer running as `root`.

```
ps -eaf | grep gw
```

- 9 Repeat [Step 1](#) through [Step 8](#) on each domain and post office server.

Later on, if you want to change the user that the agents are running as, follow the instructions in [“Changing the Non-root User” on page 82](#).

Setting Up Non-root Access on an NSS Volume on Novell Open Enterprise Server

When your domains, post offices, and libraries are located on a Novell Open Enterprise Server (OES) NSS volume, you must set up an eDirectory user for the agents to run as and you must Linux-enable that user. On OES, you can use NetIQ iManager to accomplish these tasks.

To configure the agents to switch users after startup and provide access to an NSS volume:

- 1 Select or create an eDirectory user for the agents to run as.

You might want to create a new user specifically for this purpose, perhaps named `gwagents`. The user name must not match any local user names on the Linux server.

- 1a From the Open Enterprise Server Welcome page in your web browser, click the **Management Services** tab, then click **iManager**.
- 1b To log in to iManager, specify a user name, a password, and a tree.
- 1c In the left pane, expand **Users**, then click **Create User**.
- 1d Provide the required information, then click **OK**.

The user does not need a password

IMPORTANT: All agents running on the same server must run as the same user.

- 2 Linux-enable the user you just created:
 - 2a In the left pane, expand **Linux User Management**, then click **Enable User for Linux**.
 - 2b Browse to and select the user you just created, then click **OK**.
 - 2c Select the primary group for the user to belong to (for example, `admingroup`).

2d Change `/bin/bash` to `/bin/false` because the user does not need a shell.

2e Click **OK** to Linux-enable the user.

3 Ensure that you are logged in as `root`.

4 Change to the `groupwise` folder under `/etc`:

```
cd /etc/opt/novell/groupwise
```

5 Create a new `agents` folder, then change to that folder:

```
mkdir agents
cd agents
```

6 Create a file named `uid.conf`.

7 Type the selected user name in the file, for example:

```
gwagents
```

8 Use the following command to grant the user the required rights to the folders that the agents need to access on the local server:

```
rights -f /folder_name -r rwcemf trustee user.context.tree
```

The POA needs access to the post office folder. The MTA and the GWIA need access to the domain folder.

9 Stop and then start the agents.

While starting as `root`, the agents automatically change the ownership of the domain and post office folder structures from `root` to the user you specified in the `uid.conf` file. Then they switch users and run as the user you specified, rather than as `root`.

IMPORTANT: The first time you start an agent as a non-`root` user (or if you change from one non-`root` user to another), the agent might take longer than usual to start, because of the change in ownership of the directories and files accessed by that agent. This is especially true of a POA that services a large post office and that requires access to a restore area, especially a restore area on a remote server.

10 (Optional) List the agent processes to see that they are no longer running as `root`.

```
ps -eaf | grep gw
```

11 Repeat [Step 3](#) through [Step 10](#) on each domain and post office server.

Later on, if you want to change the user that the agents are running as, follow the instructions in [“Changing the Non-root User” on page 82](#).

Changing the Non-root User

To prevent an agent from running as a different user than the one for which it was originally configured, the GroupWise agents create a `uid.run` file in the domain or post office folder that they service. The GWIA creates the `uid.run` file in its `gwia` directory (typically `domain/wpgate/gwia`).

If, for any reason, the user specified in the `uid.run` file does not match the user specified in the `uid.conf` file, the agent displays the following message:

```
Error: Running the agent with conflicting effective users
```

This could happen if the user specified in the `uid.conf` file is manually edited, or if the `uid.conf` file is deleted, thus changing or removing the information about the user that the agent should run as. If this message appears, verify that the `uid.conf` file specifies the desired user, then delete the `uid.run` file.

After displaying the message, the agent does not start, because it no longer has appropriate permissions in the domain or post office folder that it needs to service. By deleting the `uid.run` file, you enable the agent to reset the permissions in the domain or post office folder to the appropriate user and then start successfully.

After configuring an agent to run as a specific non-root user:

- If you want the agent to run as a different non-root user, modify the `uid.conf` file in the `/etc/opt/novell/groupwise/agents` folder to specify the desired non-root user. Then delete the `uid.run` file from the folder serviced by the agent.
- If you want the agent to run as root again, delete the `uid.conf` file from the `/etc/opt/novell/groupwise/agents` folder, and delete the `uid.run` file from the folder serviced by the agent.

14.1.3 Automatically Restarting the Linux GroupWise Agents with the GroupWise High Availability Service

You can use the GroupWise High Availability Service (gwha), in conjunction with GroupWise Monitor, to detect when a Linux GroupWise agent has stopped unexpectedly and to restart it automatically.

NOTE: On Windows, Microsoft Clustering Services can automatically restart a GroupWise agent service that is not responding. However, on Linux, some clustering environments do not include this capability, so it is provided by the GroupWise High Availability Service.

The GroupWise High Availability Service is installed automatically. After you enable it, it automatically starts when your server starts.

The High Availability Service relies on the Monitor Agent to detect when a Linux GroupWise agent is no longer running. The Monitor Agent notifies the GroupWise High Availability Service of any problem. Then the GroupWise High Availability Service then issues the command by using the `grpwise` script to start the problem agent. The GroupWise High Availability Service runs as root, as configured in the `/etc/xinetd.d/gwha` file.

A single Monitor Agent can service multiple instances of the GroupWise High Availability Service on multiple servers, as long as all instances use the same user name and password to communicate with the Monitor Agent.

NOTE: You can use either the Linux Monitor Agent or the Windows Monitor Agent to monitor the Linux GroupWise agents. However, you cannot use the GroupWise High Availability Service to restart the Windows GroupWise agents.

- [“Reconfiguring the GroupWise High Availability Service \(Optional\)” on page 84](#)
- [“Enabling the GroupWise High Availability Service” on page 86](#)
- [“Creating a GroupWise High Availability Service User” on page 86](#)
- [“Configuring the Monitor Agent to Communicate with the GroupWise High Availability Service” on page 87](#)
- [“Testing the High Availability Service” on page 89](#)

Reconfiguring the GroupWise High Availability Service (Optional)

The default configuration of the High Availability Service is often appropriate, but you can optionally edit its configuration files to customize its functionality:

- ♦ [“Editing the gwha File to Change the Port Number \(Optional\)” on page 84](#)
- ♦ [“Editing the gwha.conf File to Enable SSL and Customize Agent Management \(Optional\)” on page 84](#)

Editing the gwha File to Change the Port Number (Optional)

The basic configuration for the GroupWise High Availability Service is contained in the `/etc/xinetd.d/gwha` file:

```
socket_type = stream
user = root
server = /opt/novell/groupwise/agents/bin/gwha
wait = no
instances = 1
protocol = tcp
type = UNLISTED
port = 8400
disable = yes
```

The only option you can change in this file is the port number. By default, the GroupWise High Availability service listens on port 8400. If that port number is already in use on the server where you are setting up the GroupWise High Availability service, you can change the port number in the `gwha` file.

IMPORTANT: The GroupWise High Availability service must use the same port number on all servers where you want it to restart the GroupWise agents.

- 1 In a terminal window, become `root` by entering `su -` and the `root` password.
- 2 Edit the `gwha` file in an ASCII text editor.
- 3 Change the port number as needed.

IMPORTANT: Do not change any other options in this file.

- 4 Save the file, then exit the text editor.
- 5 Continue with [Editing the gwha.conf File to Enable SSL and Customize Agent Management \(Optional\)](#).

or

Continue with [“Enabling the GroupWise High Availability Service” on page 86](#).

Editing the gwha.conf File to Enable SSL and Customize Agent Management (Optional)

The interaction between the GroupWise High Availability service and the GroupWise agents is controlled by the following file:

`/etc/opt/novell/groupwise/gwha.conf`

You can reconfigure the following functionality:

- ♦ Enable SSL between the High Availability Service and the Monitor Agent.

- Change the length of time between when the `grpwise` script issues the command to start an agent, and when the script displays a message indicating that the agent has started.
- If you changed the port number in the `/etc/xinetd.d/gwha` file, make the corresponding change in the `gwha.conf` file.

At the top of the `gwha.conf` file, in the `[gwha]` section, is a section for configuring SSL for communication between the GroupWise High Availability service and the Monitor Agent. After the `[gwha]` section are sections for each agent that is configured to run on the server, as shown. The headings for the agent sections match the agent designations listed in [“Starting and Stopping the Linux Agents as Services” on page 77](#).

```
[gwha]
ssl          = no
key          =
cert         =
password     =

[domain_name]
server       = /opt/novell/groupwise/agents/bin/gwmta
command      = /etc/init.d/grpwise
startup      = domain_name.mta
delay        = 2
wait         = 10

[post_office_name.domain_name]
server       = /opt/novell/groupwise/agents/bin/gwpoa
command      = /etc/init.d/grpwise
startup      = post_office_name.poa
delay        = 2
wait         = 10

[gwia.domain_name]
server       = /opt/novell/groupwise/agents/bin/gwia
command      = /etc/init.d/grpwise
startup      = gwia.cfg
delay        = 2
wait         = 10

[gwdva]
server       = /opt/novell/groupwise/agents/bin/gwdva
command      = /etc/init.d/grpwise
startup      = gwdva.dva
delay        = 2
wait         = 10
```

To reconfigure the GroupWise High Availability service in the `gwha.conf` file:

- 1 In a terminal window, become `root` by entering `su -` and the `root` password.
- 2 Edit the `gwha.conf` file in an ASCII text editor.
- 3 (Conditional) If you use SSL, fill in the following fields in the `[gwha]` section:

```
[gwha]
ssl          = yes
key          = file_name.key
cert         = file_name.crt
password     = password
```

- 4 (Conditional) If you changed the port number for the GroupWise High Availability service, as described in [“Reconfiguring the GroupWise High Availability Service \(Optional\)” on page 84](#), add the following line to the [gwha] section:

```
port = port_number
```

Replace `port_number` with the new port number you specified in the `gwha` file.

- 5 (Optional) If you want to control how the `grpwise` script manages starting and stopping the agents, modify the `delay =` and `wait =` settings.

The `delay =` setting controls the length of time between when the script issues the command to start an agent and when the script displays a message indicating that the agent has started. The default delay time is 2 seconds. Under certain circumstances, an agent could encounter a problem and fail to start after 2 seconds. In this case, you would receive the success message, but the agent would not be running. You need to increase the `delay =` setting to accommodate the length of time it typically takes for the agent to start successfully on your system.

The `wait =` setting controls the length of time between when the script issues the command to stop an agent and when the script kills the agent if the agent has not yet stopped. The default wait time is 10 seconds. Under certain circumstances, an agent could take longer than 10 seconds to perform a normal shutdown, and killing the agent under those circumstances would not be appropriate. You need to increase the `wait =` setting to accommodate the length of time it usually takes for the agent to shut down. A message notifies you if the script kills an agent because its shutdown exceeds the `wait =` setting.

The default settings are usually appropriate, so you do not need to change them unless you frequently encounter problems with starting or stopping an agent with the script.

- 6 Save the file, then exit the text editor.
- 7 Continue with [Enabling the GroupWise High Availability Service](#).

Enabling the GroupWise High Availability Service

- 1 In YaST, click **Network Services > Network Services (xinetd)**.
- 2 (Conditional) If necessary, select **Enable** to activate the list of services.
- 3 Scroll down to the `gwha` line, select it, then click **Toggle Status (On or Off)** to change the status to **On**.
- 4 Click **Finish**.
- 5 Repeat [Step 1](#) through [Step 4](#) on all servers where you want the GroupWise High Availability service to restart the GroupWise agents.
- 6 Continue with [Creating a GroupWise High Availability Service User](#).

Creating a GroupWise High Availability Service User

The GroupWise High Availability service needs a login user on each server where GroupWise agents need to be restarted.

- 1 Create a new user and associated password on the local Linux server to represent the GroupWise High Availability service.

You might name it `gwhauser`.

IMPORTANT: Use a local user account for use only by the GroupWise High Availability service. Do not use a Novell Linux-enabled user. Do not use `root`.

- 2 Create the same user on each Linux server where you want the GroupWise High Availability service to restart the GroupWise agents.
- 3 On each Linux server, configure the `gwha.allow` file for the new user:
 - 3a Change to the following folder:

```
/etc/opt/novell/groupwise
```
 - 3b Edit the `gwha.allow` file in an ASCII text editor.
 - 3c Specify the user that you created in [Step 1](#).
 - 3d Save the file, then exit the text editor.
- 4 Continue with [Configuring the Monitor Agent to Communicate with the GroupWise High Availability Service](#).

Configuring the Monitor Agent to Communicate with the GroupWise High Availability Service

After you have the GroupWise High Availability service set up and working correctly on all Linux servers where you want it to restart the GroupWise agents, you need to configure the Monitor Agent to communicate with it, and then test it to ensure that you can rely on it in the future.

IMPORTANT: Although you need a GroupWise High Availability service running on each Linux server where there are GroupWise agents, you need only one Monitor Agent to monitor all agents in your GroupWise system.

- ♦ [“Configuring the Linux Monitor Agent” on page 87](#)
- ♦ [“Configuring the Windows Monitor Agent” on page 88](#)

Configuring the Linux Monitor Agent

- 1 Install the Linux Monitor Agent.
For installation instructions, see [Chapter 18, “Setting Up GroupWise Monitor,” on page 131](#).
- 2 Configure the Linux Monitor Agent with the `--hauser`, `--hapassword`, and `--hapoll` startup switches.

The Monitor Agent uses the `--hauser` and `--hapassword` switches to communicate with the GroupWise High Availability service on port 8400, as configured in the `/etc/xinetd.d/gwha` file. When the Monitor Agent notices that a GroupWise agent has stopped, it notifies the GroupWise High Availability Service. Then the GroupWise High Availability Service issues the command to restart the problem agent.

For more information, see [“Using Monitor Agent Startup Switches”](#) in the *GroupWise 2014 R2 Administration Guide*.
 - 2a In YaST, click **System > /etc/sysconfig Editor**.
 - 2b Expand **Network > Mail > GroupWise**.
 - 2c Click **GROUPWISE_MA_OPTIONS**.
 - 2d In the **Setting** field, set the `--hauser` and `--hapassword` switches for the user that you created in [“Creating a GroupWise High Availability Service User” on page 86](#).

TIP: An easy way to create the string is to copy the example at the bottom of the **Description** paragraph and replace `username` and `password` as needed.

- 2e In the **Setting** field, set the --hapoll switch for the number of seconds in the poll cycle on which the Monitor Agent contacts the GroupWise High Availability Service to provide agent status information.
- 2f Click **OK** to save the settings.
- 2g Click **OK** again to save the change.
- 2h Exit YaST.
- 3 Start the Monitor Agent.


```
rcgrpwise-ma start
```
- 4 Continue with [“Testing the High Availability Service” on page 89.](#)

Configuring the Windows Monitor Agent

- 1 Install the Windows Monitor Agent as either an application with a server console UI on the server or as a Windows service without UI on the server.
For installation instructions, see [Chapter 18, “Setting Up GroupWise Monitor,” on page 131.](#)

NOTE: The Windows Monitor Agent provides a server console that is not available on Linux. For more information, see [“Comparing the Monitor Consoles” in the *GroupWise 2014 R2 Administration Guide*.](#)

- 2 Configure the Windows Monitor Agent with the [/hauser](#), [/hapassword](#), and [/hapoll](#) startup switches.

The Monitor Agent uses the --hauser and --hapassword switches to communicate with the GroupWise High Availability service on port 8400, as configured in the `/etc/xinetd.d/gwha` file. When the Monitor Agent notices that a GroupWise agent has stopped, it notifies the GroupWise High Availability Service. Then the GroupWise High Availability Service issues the command to restart the problem agent.

For more information, see [“Using Monitor Agent Startup Switches” in the *GroupWise 2014 Administration Guide*.](#)

- 3 (Conditional) If you installed the Windows Monitor Agent as an application:

- 3a Create a batch file similar to the following example:

```
c:\Program Files\Novell\GroupWise Server\Monitor\gwmon.exe
/hauser-gwha /hapassword-gwha /hapoll-60
```

- 3b Create a desktop icon for running the batch file.

- 3c To start the Monitor Agent, run the batch file.

- 4 (Conditional) If you installed the Windows Monitor Agent as a Windows service:

- 4a In the Control Panel, click **Administrator Tools > Services**.

- 4b Right-click **GroupWise Monitor**, then click **Properties**.

- 4c In the **Start Parameters** field, specify the required Monitor Agent startup switches, then click **OK**. For example:

```
/hauser-gwha /hapassword-gwha /hapoll-60
```

- 4d To start the Monitor Agent, right-click **GroupWise Monitor**, then click **Start**.

Testing the High Availability Service

- 1 Stop one of the Linux agents, as described in [“Starting and Stopping the Linux Agents as Services” on page 77](#).
- 2 Check the status of the agent you stopped to make sure it is stopped.
- 3 Wait for the next Monitor Agent polling cycle.
You can check and, if necessary, change the Monitor Agent polling cycle in the [Monitor Agent console](#). Click **Preferences**, then scroll down to the **HTTP Settings** section.
- 4 After the polling cycle has passed, check the status of the agent again.
The agent that you stopped should now be running again.

14.1.4 Using the Linux GroupWise Agent Log Files

Agent status messages and error messages are written to the agent log files (*mmdagent.nnn*) in agent-specific subfolders of the following folder:

```
/var/log/novell/groupwise
```

The log file name includes the month and day when it was created, the name of the agent, and an incrementing extension to accommodate multiple log files on the same day.

The agents also maintain a symbolic link to a file named *agent.currentlog*, where *agent* is the name of the agent object in the Admin console. This link points to the current agent log file, regardless of the date and incrementing extension of the actual agent log file name. This facilitates monitoring the current agent log file using the `tail` command.

NOTE: The *agent.currentlog* symbolic link is not available for the DVA log files.

14.1.5 Uninstalling the Linux GroupWise Agents and Applications

If you move the GroupWise agents to a different server, the GroupWise agent software can be uninstalled just like any other software on Linux. To determine what GroupWise software is currently installed on the Linux server, use the following command:

```
rpm -qa | grep groupwise
```

This lists all of the GroupWise RPM packages on the server. The POA, the MTA, the GWIA, and the DVA are together in the same RPM. WebAccess has its own RPM. Monitor has two RPMs, one for the agent software and one for the application software.

The following list shows all GroupWise RPMs that you might need to uninstall from a server:

POA, MTA, GWIA, and DVA:	<code>novell-groupwise-server-version-date</code>
WebAccess Application:	<code>novell-groupwise-webaccess-version-date</code>
Monitor Agent:	<code>novell-groupwise-gwmon-version-date</code>
Monitor Application:	<code>novell-groupwise-monitor-version-date</code>
Calendar Publishing Host Application:	<code>novell-groupwise-calhost-version-date</code>
GroupWise High Availability Service:	<code>novell-groupwise-gwha-version-date</code>
GroupWise Check:	<code>novell-groupwise-gwcheck-version-date</code>
GroupWise Database Copy:	<code>novell-groupwise-dbcopy-version-date</code>

Use the following command to uninstall a GroupWise RPM package:

```
rpm -e novell-groupwise-package
```

Uninstalling the RPMs does not uninstall files created after installation by the GroupWise programs. To completely uninstall GroupWise, delete GroupWise files from the following locations:

```
/etc/init.d  
/usr/sbin  
/etc/xinetd.d  
/etc/opt/novell/groupwise  
/var/opt/novell/groupwise  
/var/log/novell/groupwise
```

14.2 Windows: Managing the GroupWise Agents

Basic agent monitoring and management is most easily performed on the System Overview page in the Admin console. For instructions, see [Section 13.2, “Making the Most of the System Overview,” on page 73](#). Refer to the following additional tasks as you maintain all the GroupWise agents on Windows:

14.2.1 Manually Starting and Stopping the Windows GroupWise Agents

Manually Starting and Stopping the GroupWise Agents as Services

- ♦ [“By Using the Windows Services Tool” on page 90](#)
- ♦ [“By Using the gwsc Command” on page 90](#)

By Using the Windows Services Tool

You can manage the GroupWise agents just as you would any other Windows services.

For example, on Windows Server 2012 R2:

- 1 From the Windows desktop, click **Start > Administrative Tools > Services**.
 - 2 Select the agent service, then click **Start**.
- or
- Select the agent service, then click **Stop**.

When the agents run without a user interface, you can monitor them by using their agent consoles. See [Section 14.3, “Monitoring the Agents from Your Web Browser,” on page 92](#).

By Using the gwsc Command

You can also manage the GroupWise agents by using the `gwsc` command, which is short for the `gadminutil services` command.

For the `gwsc` command, each agent is designated in terms of its object name or of the name of the domain and post office associated with it:

```
POA:    poa_object_name or post_office_name  
MTA:    mta_object_name or domain_name  
GWIA:   gwia_object_name  
DVA:    dva_object_name
```

Use the following set of `gwsc` commands to start and stop the agents as services and verify their status:

<code>gwsc -query</code>	Displays the status of the GroupWise agents that are configured to run on the server.
<code>gwsc -query name</code>	Displays the status of the specified agent.
<code>gwsc -start</code>	Starts the GroupWise agents that are configured to run on the server.
<code>gwsc -start name</code>	Starts the specified agent.
<code>gwsc -stop</code>	Stops the GroupWise agents that are configured to run on the server.
<code>gwsc -stop name</code>	Stops the specified agent.
<code>gwsc -list</code>	Lists the agent services that are configured on the server.

Manually Starting the Windows Agents As Applications for Troubleshooting

In general, you should run the Windows agents as services without a user interface, so that they can be managed in the Admin console.

Occasionally, when troubleshooting a problem that occurs at agent startup, the problem can occur before the agent console can be displayed and before error messages can be written to the agent log file. Under such circumstances, you can start an agent with a user interface in order to view any errors that the agent displays on the server console before the agent stops again.

IMPORTANT: When an agent is running with a user interface, it cannot be managed in the Admin console.

To run the agents as applications, you can create desktop shortcuts for them. The desktop shortcuts need to contain the following commands:

Syntax:

```
c:\Program Files\Novell\GroupWise Server\agents\gwpoa.exe
                               /home \post_office_folder
c:\Program Files\Novell\GroupWise Server\agents\gwmmta.exe
                               /home \domain_folder
c:\Program Files\Novell\GroupWise Server\agents\gwia.exe
                               /home /gwia_folder
c:\Program Files\Novell\GroupWise Server\agents\Monitor\gwmon.exe
                               /home \domain_folder
```

Example:

```
c:\Program Files\Novell\GroupWise Server\agents\gwpoa.exe
                               /home \mail\powin
c:\Program Files\Novell\GroupWise Server\agents\gwmta.exe
                               /home \mail\domwin
c:\Program Files\Novell\GroupWise Server\agents\gwia.exe
                               /home \mail\domwin\gwia
c:\Program Files\Novell\GroupWise Server\agents\Monitor\gwmon.exe
                               /home \mail\domwin
```

14.2.2 Using the Windows GroupWise Agent Log Files

Agent status messages and error messages are written to the agent log files (*mmdagent.nnn*) in the following directories:

POA:	<i>post_office_folder\wpcs\ofs</i>
MTA:	<i>domain_folder\mslocal</i>
GWIA:	<i>domain_folder\wpgate\gwia\000.prc</i>
DVA:	<i>c:\ProgramData\Novell\GroupWise\gwdva</i>
Monitor:	<i>c:\ProgramData\Novell\GroupWise Monitor</i>

NOTE: On some versions of Windows Server, the *ProgramData* folder is not visible by default. To display it in File Explorer, click **View**, then select **Hidden items**.

14.2.3 Uninstalling the Windows GroupWise Agents and Applications

If you move the GroupWise agents to a different server, you can uninstall the agent software from the old location to reclaim disk space.

Agents:	In the Control Panel, click Programs and Features . Right-click Novell GroupWise Server , then click Uninstall .
Monitor:	Stop the Monitor Agent, then delete the <i>c:\Program Files\Novell\GroupWise Server\Monitor</i> folder.
Applications:	Stop Tomcat, then delete the following folder: <i>c:\Novell</i>

14.3 Monitoring the Agents from Your Web Browser

To monitor any GroupWise agent from your web browser, view the agent console by supplying the IP address or DNS hostname and the port number of the agent. The following table lists the default port numbers:

POA:	<i>http://server_network_address:7181</i>
MTA:	<i>http://server_network_address:7180</i>
GWIA:	<i>http://server_network_address:9850</i>
DVA:	<i>http://server_network_address:8301</i>
Monitor:	<i>http://server_network_address:8200</i>

For more information about the agent consoles, including instructions on protecting the agent consoles with passwords, see the following sections in the [GroupWise 2014 R2 Administration Guide](#):

- ◆ [“Using the POA Console”](#)
- ◆ [“Using the MTA Console”](#)
- ◆ [“Using the GWIA Console”](#)
- ◆ [“Using the DVA Console”](#)
- ◆ [“Using the Monitor Web Console”](#)

15 What's Next

After you have created your GroupWise system, you can expand the system in the following ways:

Task	Section in This Guide
Setting up GroupWise WebAccess so that users can access their mailboxes through a web browser on a computer or mobile device	See Chapter 16, "Setting Up GroupWise WebAccess," on page 99.
Setting up a GroupWise Calendar Publishing Host so that GroupWise users can share their personal calendars and free/busy information with Internet users	See Chapter 17, "Setting Up the GroupWise Calendar Publishing Host," on page 113.
Setting up GroupWise Monitor to monitor your GroupWise agents	See Chapter 18, "Setting Up GroupWise Monitor," on page 131.
Setting up users to run the GroupWise client on their workstations	See Chapter 20, "Installing the GroupWise Client," on page 153.
Setting up synchronization between users' GroupWise mailboxes and their mobile devices	See Section 21.1, "Using the GroupWise Mobility Service to Synchronize GroupWise Data to Mobile Devices," on page 157.
Setting up instant messaging capabilities for users	See Section 21.2, "Using Novell Messenger to Provide Secure Instant Messaging for GroupWise Users," on page 157.
Setting up team collaboration capabilities	See Section 21.3, "Using Novell Vibe to Provide Team Workspaces for GroupWise Users," on page 158.

After your GroupWise system is fully installed, you can maintain your GroupWise system in the following ways:

Task	Section in the GroupWise 2014 R2 Administration Guide
Adding multiple domains to your GroupWise system	See "Domains."
Adding post offices to new domains	See "Post Offices."
Adding more users to post offices	See "Users."
Defining resources that users can schedule	See "Resources."
Defining groups of users that GroupWise users can select when addressing messages	See "Groups."
Changing the GroupWise client from Online mode to Caching mode so that users' messages are stored on a local drive as well as in the post office	See "Client."

Task	Section in the <i>GroupWise 2014 R2 Administration Guide</i>
Setting up GroupWise Remote so that GroupWise client users can access their mailboxes from a computer that is not directly connected to your network	See “ Client .”
Controlling the functionality of users’ GroupWise client software	See “ Client .”
Setting up a library	See “ Libraries and Documents .”
Configuring the agents to support secure connections (SSL)	See “ Post Office Agent ,” “ Message Transfer Agent ,” “ Internet Agent ,” and “ Document Viewer Agent .”
Configuring GroupWise to run in a clustering environment	See the “ Clustering ” in the <i>GroupWise 2014 R2 Interoperability Guide</i> .

IV GroupWise Component Installation and Setup

- ♦ [Chapter 16, “Setting Up GroupWise WebAccess,” on page 99](#)
- ♦ [Chapter 17, “Setting Up the GroupWise Calendar Publishing Host,” on page 113](#)
- ♦ [Chapter 18, “Setting Up GroupWise Monitor,” on page 131](#)
- ♦ [Chapter 19, “Setting Up GroupWise Calendar Server,” on page 147](#)
- ♦ [Chapter 20, “Installing the GroupWise Client,” on page 153](#)
- ♦ [Chapter 21, “Using Other Novell Products with GroupWise,” on page 157](#)

16 Setting Up GroupWise WebAccess

GroupWise WebAccess enables users to access GroupWise mailboxes through [desktop web browsers](#), through [tablet devices](#) such as Apple iPads, and through [mobile devices](#). The following sections provide information to help you successfully install the GroupWise WebAccess Application in your existing GroupWise system.

16.1 GroupWise WebAccess Overview

16.1.1 GroupWise WebAccess Functionality

When used in a desktop web browser, GroupWise WebAccess provides much of the functionality available in the GroupWise client. On a tablet device, the most commonly used functionality is available. WebAccess functionality on mobile devices is limited compared to WebAccess in a desktop browser or on a tablet device.


See the following guides for WebAccess user functionality details:

- ♦ [GroupWise 2014 R2 WebAccess User Guide](#)
- ♦ [GroupWise 2014 R2 WebAccess Mobile User Guide](#)
- ♦ [WebAccess Basic Interface Quick Start](#)

After you set up GroupWise WebAccess, see [Section 16.6, “What’s Next,” on page 110](#) for additional information that you might want to be aware of as you configure, maintain, and expand GroupWise WebAccess.

16.1.2 GroupWise WebAccess Components

GroupWise WebAccess consists of four components: the browser-based WebAccess user interface (desktop computer, tablet device, or mobile device), the WebAccess Application, the Post Office Agent (POA), and the Document Viewer Agent (DVA).



- ♦ **WebAccess User Interface:** The WebAccess user interface in web browsers gives users access to their GroupWise mailboxes anywhere an Internet connection is available.
- ♦ **WebAccess Application:** The WebAccess Application, which resides on the web server, provides the GroupWise WebAccess user interface. As users perform actions in WebAccess, the WebAccess Application passes information between the web browser and the Post Office Agent.

- ♦ **Post Office Agent:** The POA receives user requests from the WebAccess Application, accesses post offices and libraries to process the requests, and then passes information back to the WebAccess Application.
- ♦ **Document Viewer Agent:** The DVA isolates the conversion process for attached document files. The DVA can simultaneously convert multiple document files into HTML format. If it encounters a problem converting a document file, the problem does not affect conversion of other document files, nor does it affect the functioning of the WebAccess Application. Therefore, GroupWise WebAccess users do not experience interruptions because of document files that fail to convert into HTML. Document files that fail in the conversion process simply cannot be viewed in WebAccess. The DVA is typically installed along with the POA.

16.1.3 WebAccess Security Requirements

The WebAccess Application can be configured to support the level of security you have established for your Internet/intranet communication.

If you are not concerned about security issues (for example, you only plan to use the WebAccess Application on a secured intranet), you can install the WebAccess Application to any web server that provides access for your users and meets the requirements listed in [Section 16.2, “GroupWise WebAccess System Requirements,” on page 102](#).


If you plan to use the WebAccess Application to provide users with access to their mailboxes from anywhere on the Internet (rather than only within a secured intranet), and you already have a firewall in place to provide security, you have the following options for configuring the WebAccess Application:

- ♦ Install the WebAccess Application inside your firewall and use a proxy service. See [“WebAccess with a Proxy Service” on page 101](#). This is the recommended configuration.
- ♦ Install the WebAccess Application on a web server outside your firewall, and install the POA and the DVA on a server inside your firewall. See [“WebAccess without a Proxy Service” on page 101](#).

WebAccess with a Proxy Service

If your firewall includes a proxy service, you can install the WebAccess Application to a web server inside your firewall. The POA and the DVA are located on a post office server, which is also inside the firewall.


In this configuration, only the firewall server with the proxy service is located outside the firewall, as shown in the following illustration.



WebAccess without a Proxy Service

If your firewall does not provide a proxy service, you need to install the WebAccess Application to a web server that is outside the firewall. The POA and the DVA are located on a post office server, which is inside the firewall.

In this configuration, both the web server and the firewall server are located outside the firewall, as shown in the following illustration.



The firewall must allow inbound IP packets to be sent from the web server to the IP address and port of the POA (for example, 172.16.5.18:1677).

In addition, the firewall must allow outbound IP packets to be sent from the POA to the web server. This requires all high ports (above 1023) to be open to outbound IP packets.

16.2 GroupWise WebAccess System Requirements

16.2.1 Hardware and Operating System Requirements

- ☐ x86-64 or x86-32 processor
- ☐ Any of the following server operating systems for the WebAccess Application:
 - ♦ Novell Open Enterprise Server (OES) 11 or Novell Open Enterprise Server (OES) 2015, plus the latest Support Pack
 - ♦ SUSE Linux Enterprise Server (SLES) 11 or SUSE Linux Enterprise Server (SLES) 12 plus the latest Service Pack

NOTE: On Linux, the X Window System and Open Motif are required by the GUI GroupWise agent server consoles for the Post Office Agent, the Message Transfer Agent, and the Internet Agent.

By default, the GroupWise Linux agents run as services without user interfaces. Starting and stopping the agents when they are running with a user interface is not supported in the GroupWise Administration console.

- ♦ Windows Server 2012 R2, plus the latest Service Pack
- ☐ Adequate server memory as required by the operating system

- ☐ Adequate server disk space:
 - ♦ Approximately 525 MB (shared with the Calendar Publishing Host Application and the Monitor Application when they are installed on the same web server; varies by platform)

16.2.2 Web Server Requirements

The web server that is supported for your operating system:

- ☐ x86-64 or x86-32 processor
- ☐ OES 11 / OES 2015 / SLES 11

Apache 2.2 plus:

- ♦ Tomcat 6
- ♦ ModProxy Module
- ♦ **OES11 / OES 2015 / SLES 11:** IBM Java 8 Runtime Environment (JRE)
- ♦ **SLES 12:** OpenJDK 7

A Linux repository should be available when you run the GroupWise Installation Wizard. Apache, Tomcat, the JRE or JDK, and the ModProxy Module are automatically installed from the Linux repository if they are not already present on the Linux server.

If no Linux repository is available during the GroupWise installation, you are prompted to manually install these required components from the Linux media, and then restart the GroupWise installation.

- ☐ Windows Server 2012 R2

Microsoft Internet Information Server (IIS) 7 or later plus:

- ♦ Tomcat 6
- ♦ Oracle Java 8 Runtime Environment (JRE)
- ♦ Jakarta Connector 1.2

Tomcat 6.0.24, Oracle JRE 8, and Jakarta Connector 1.2 are automatically installed along with the GroupWise software if they are not already present on the Windows server.

- ♦ ISAPI support

ISAPI support is no longer installed by default when you install Windows Server 2008 R2 or later and Internet Information Services (IIS). If ISAPI support was not manually selected when IIS was installed, you can add it after the fact. See

16.2.3 GroupWise Requirements

- ☐ One or more Post Office Agents (POAs) configured for SOAP and secure SSL connections
- ☐ One or more Document Viewer Agents (DVAs) configured to communicate with the POAs

16.2.4 User Requirements

WebAccess User Requirements

- ☐ Any of the following web browsers:
 - ♦ Linux: Mozilla Firefox; Google Chrome

- ♦ Windows: Microsoft Internet Explorer 9 or later; Mozilla Firefox; Google Chrome; Windows Edge
 - ♦ Macintosh: The latest version of Safari for your version of Mac OS; Mozilla Firefox; Google Chrome
- ☐ Any mobile device that supports Wireless Access Protocol (WAP) and has a microbrowser that supports Hypertext Markup Language (HTML) 4.0 or later

WebAccess Mobile User Requirements

Any of the following tablet operating systems and tablets:

- ☐ Android 4.1, 5.0, or later, with Google Chrome, on any Android device
- ☐ Apple iOS 7.x, 8.x, or later, with Apple Safari
- ☐ Kindle Fire, with Amazon Silk
- ☐ Windows Mobile 8.0 or later Pro, with Microsoft Internet Explorer, on any Windows device (full WebAccess, no template)

16.3 Planning GroupWise WebAccess

Use the “[GroupWise WebAccess Installation Worksheet](#)” on [page 110](#) to record the information required to install the WebAccess Application.

The topics in this section present the required information in a convenient planning sequence. The Installation Worksheet organizes the information in the order in which you need it during installation.

16.3.1 Selecting the WebAccess Application Platform

The WebAccess Application can be installed to a web server on Linux or Windows. See [Section 16.2](#), “[GroupWise WebAccess System Requirements](#),” on [page 102](#) for supported web servers.

GROUPWISE WEBACCESS APPLICATION INSTALLATION WORKSHEET

Under **Web Server Platform**, mark whether you plan to install the WebAccess Application to a Linux or Windows web server.

16.3.2 Gathering Web Server Information

The WebAccess Application integrates with your web server to pass mailbox information gathered by the POA to your web browser for display in WebAccess. The location of the WebAccess Application files that are installed depends on the web server that it is being integrated with.

The default web server paths vary by platform:

Apache Web Server on OES 11:	/etc/opt/novell/httpd/conf.d
Tomcat on OES 11:	/var/opt/novell/tomcat/webapps
Apache Web Server on SLES 11:	/etc/apache2/conf.d
Tomcat on SLES 11:	/usr/share/tomcat/webapps
Microsoft Internet Information Server (IIS) on Windows:	c:\inetpub\wwwroot
Tomcat on Windows:	c:\novell\tomcat\webapps

GROUPWISE WEBACCESS APPLICATION INSTALLATION WORKSHEET

Under **Web Server Information**, select the type of web server where you plan to install the WebAccess Application. Also specify the web server's root directory.

On Windows, if the Internet Information Server services more than one website, specify the website where you want to install the WebAccess Application.

16.3.3 Determining the WebAccess Application's Configuration

WebAccess Application configuration information is stored in a configuration file (`webacc.cfg`). The `webacc.cfg` file is located in the following folders:

Linux: /var/opt/novell/groupwise/webaccess
Windows: c:\novell\groupwise\webaccess

To change the WebAccess Application's configuration, you must manually modify the `webacc.cfg` file.

GROUPWISE WEBACCESS APPLICATION INSTALLATION WORKSHEET

Under **Configuration File Location**, note the location of the `webacc.cfg` file for the platform where you are installing WebAccess.

16.3.4 Connecting the WebAccess Application with Supporting Agents

The WebAccess Agent needs to communicate with a POA and a DVA.

GROUPWISE WEBACCESS APPLICATION INSTALLATION WORKSHEET

Under **POA Network Address**, specify the IP address or DNS hostname of a POA that the WebAccess Application can communicate with, along with that POA's SOAP port. The default SOAP port for the POA is 7191.

Under **DVA Network Address**, specify the IP address or DNS hostname of a DVA that the WebAccess Application can communicate with, along with that DVA's TCP port. The default DVA port is 8301.

IMPORTANT: The POA that the WebAccess Application communicates with must be configured for SOAP. A secure SSL connection between the POA and the WebAccess Application is highly recommended.

For instructions on preparing the POA to work successfully with the WebAccess Application, see the following sections in the [GroupWise 2014 R2 Administration Guide](#):

- ♦ [“Supporting SOAP Clients”](#)
- ♦ [“Securing the Post Office with SSL Connections to the POA”](#)

For instructions on preparing the DVA to work successfully with the WebAccess Application, see the following sections in the [GroupWise 2014 R2 Administration Guide](#):

- ♦ [“Multiple DVAs for WebAccess”](#)
- ♦ [“Installing the DVA”](#)

16.4 Installing the GroupWise WebAccess Software

As you install the WebAccess software, use the [GroupWise WebAccess Installation Worksheet](#) that you filled out in [Section 16.3, “Planning GroupWise WebAccess,”](#) on page 104 to provide the required information.

16.4.1 Linux: Installing the GroupWise WebAccess Software

- ♦ [“Preparing the Linux Server for GroupWise WebAccess”](#) on page 106
- ♦ [“Installing the Linux WebAccess Software”](#) on page 106

Preparing the Linux Server for GroupWise WebAccess

- 1 Ensure that the web server where you are installing the WebAccess Application meets the system requirements listed in [Section 16.2, “GroupWise WebAccess System Requirements,”](#) on page 102.
- 2 Ensure that the Linux operating system media is available, either physically or in a repository, in case the Installation Wizard needs to install supporting packages on the Linux server.
- 3 Ensure that the server has a static IP address.
- 4 Ensure that the POA that the WebAccess Application will communicate with has SOAP enabled on a secure SSL connection, as described in [Section 16.3.4, “Connecting the WebAccess Application with Supporting Agents,”](#) on page 105.
- 5 Continue with [Installing the Linux WebAccess Software](#).

Installing the Linux WebAccess Software

- 1 Download and extract the GroupWise 2014 R2 software to a temporary location on your server.
- 2 In a terminal window, become `root` by entering `su -` and the `root` password.
- 3 Browse to the location of the extracted software, and run the following command to start the install:

```
./install.sh
```

- 4 Type the number for the language in which you want to run the GroupWise Installation Wizard, then press Enter to select **OK**.
- 5 (Optional) Type 1 for **Documentation**, then press Enter to review the Readme, Quick Start, and Installation Guide to better prepare yourself for the installation.
- 6 Type 2 for **Installation**, then press Enter.
- 7 Type a to accept the License Agreement and display the Software list.
- 8 Type 2 for **GroupWise WebAccess**, then press Enter to display the Actions list.
- 9 Type 1 for **Install**, then press Enter to install GroupWise WebAccess.
The WebAccess package is installed on the server. If any supporting packages are not available on the server, the Installation Wizard automatically installs them from the operating system media.
- 10 When the installation is finished, press any key to return to the Installation Options list.
- 11 Type 2 for **Configure**, then press Enter to configure the WebAccess Application.
- 12 Follow the prompts to configure the WebAccess Application, using the following information from the [GroupWise WebAccess Installation Worksheet](#):

[POA Network Address](#)
[DVA Network Address](#)
[Web Server Information](#)
- 13 Press any key to exit WebAccess Configuration.
- 14 Exit the GroupWise Installation Wizard.
- 15 Verify the status of the DVA that you configured the WebAccess Application to communicate with.
For instructions, see [Chapter 14, "Working with the GroupWise Agents,"](#) on page 77. For more information about the DVA, see "Document Viewer Agent" in the [GroupWise 2014 R2 Administration Guide](#).
- 16 Continue with [Section 16.5, "Testing GroupWise WebAccess,"](#) on page 108.

16.4.2 Windows: Installing the GroupWise WebAccess Software

- ♦ ["Preparing the Windows Server for GroupWise WebAccess"](#) on page 107
- ♦ ["Installing the Windows WebAccess Software"](#) on page 107

Preparing the Windows Server for GroupWise WebAccess

- 1 Ensure that the web server where you are installing the WebAccess Application meets the system requirements listed in [Section 16.2, "GroupWise WebAccess System Requirements,"](#) on page 102.
- 2 Ensure that the server has a static IP address.

- 3 Ensure that the POA that the WebAccess Application will communicate with has SOAP enabled on a secure SSL connection, as described in [Section 16.3.4, “Connecting the WebAccess Application with Supporting Agents,”](#) on page 105.
- 4 Continue with [Installing the Windows WebAccess Software](#).

Installing the Windows WebAccess Software

- 1 Run `setup.exe` at the root of the extracted GroupWise software to start the GroupWise Installation Wizard.
- 2 (Optional) Review the Readme, Quick Start, and Installation Guide to better prepare yourself for the installation.
- 3 Click **GroupWise WebAccess**.
- 4 Click **Next** to display the Web Server Information page.

The Installation Wizard provides diagrams that help you understand how the various components interact with each other. Review the diagrams as you provide the requested information.
- 5 Follow the prompts to configure the WebAccess Application, using the following information from the [GroupWise WebAccess Installation Worksheet](#):

[Web Server Information](#)
[POA Network Address](#)
[DVA Network Address](#)
- 6 Click **Next** to display the Installation Summary.
- 7 Review the Installation Summary page, then click **Install** to install the WebAccess Application.
- 8 (Conditional) If prompts appear because your web server is running, decide whether you want the Installation Wizard to stop your web server.
- 9 When the installation is complete, click **Finish** to exit the WebAccess Installation Wizard.

You can choose to have the Installation Wizard restart the web server for you.

Along with the WebAccess Application, the WebAccess Installation Wizard also installs Tomcat 7 to `c:\novell\tomcat`, integrates it with your web server, and automatically starts it to support the WebAccess Application.
- 10 Exit the GroupWise Installation Wizard.
- 11 Verify the status of the DVA that you configured the WebAccess Application to communicate with.

For instructions, see [Chapter 14, “Working with the GroupWise Agents,”](#) on page 77. For more information about the DVA, see “[Document Viewer Agent](#)” in the [GroupWise 2014 Administration Guide](#).
- 12 Continue with [Testing GroupWise WebAccess](#).

16.5 Testing GroupWise WebAccess

After you have installed WebAccess, you should test it in the environments where you think that your GroupWise users will typically use it.

16.5.1 Testing WebAccess on a Workstation

- 1 To access GroupWise WebAccess, use the following URL:

`http://web_server_address/gw/webacc`

Replace `web_server_address` with the IP address or DNS hostname of your web server. If the web server uses SSL, use `https` rather than `http`.

- 2 Type your GroupWise user name in the **User Name** field and your GroupWise mailbox password in the **Password** field.
- 3 (Optional) Click **Settings**, then select the interface language you want from the **Language** drop-down list.
- 4 Click **Login** to display the GroupWise WebAccess main window.
- 5 Click **Options > Help** for more information about using GroupWise WebAccess.

16.5.2 Testing WebAccess on a Tablet Device

- 1 To access GroupWise WebAccess on a tablet device such as an iPad, use the following URL:

`http://web_server_address/gw/webacc`

Replace `web_server_address` with the IP address or DNS hostname of your web server. If the web server uses SSL, use `https` rather than `http`.

or

(Conditional) If you have a tablet device that is not yet [supported](#), but you want to see how well the mobile interface works on your device, use the following URL:

`http://web_server_address/gw/webacc?User.interface=mobile`

Replace `web_server_address` with the IP address or DNS hostname of your web server. If the web server uses SSL, use `https` rather than `http`.

- 2 Type your GroupWise user name in the **User Name** field and your GroupWise mailbox password in the **Password** field.
- 3 (Optional) Tap **Settings**, then select the interface language you want from the **Language** drop-down list.
- 4 Tap **Login** to display the GroupWise WebAccess main window.
- 5 Tap **Options > Help** for more information about using GroupWise WebAccess on your iPad.

16.5.3 Testing the WebAccess Basic Interface on a Mobile Device

- 1 To access GroupWise WebAccess in the web browser on your mobile device, use the following URL:

`http://web_server_address/gw/webacc`

Replace `web_server_address` with the IP address or DNS hostname of your web server. If the web server uses SSL, use `https` rather than `http`.

- 2 Follow the instructions in your mobile device's documentation to add this URL to your Favorites or Bookmarks so you do not need to type the URL every time you log in on your mobile device.
- 3 Type your GroupWise user name in the **User Name** field and your GroupWise mailbox password in the **Password** field.

- 4 Tap **Login** to display the GroupWise WebAccess main window.

The appearance of the WebAccess basic interface varies depending on the size of the screen where it is displayed.

For more information about using WebAccess on your mobile device, see the [WebAccess Basic Interface Quick Start](https://www.novell.com/documentation/groupwise2014/gw2014_qs_webaccbasic/data/gw2014_qs_webaccbasic.html) (https://www.novell.com/documentation/groupwise2014/gw2014_qs_webaccbasic/data/gw2014_qs_webaccbasic.html).

As an alternative to this limited interface, you can synchronize GroupWise data to your mobile device using the GroupWise Mobility Service. For more information, see the [GroupWise Mobility Service website](http://www.novell.com/documentation/groupwisemobility2) (<http://www.novell.com/documentation/groupwisemobility2>).

16.5.4 Assisting Users with Login Problems

The WebAccess Login page includes a **Can't log in** link, which provides the following information to WebAccess users by default:

If you have forgotten your GroupWise password, contact your local GroupWise administrator.

For your convenience and for the convenience of your WebAccess users, you can customize the information that is provided by the **Can't log in** link. For setup instructions, see “[Helping Users Who Forget Their GroupWise Passwords](#)” in the *GroupWise 2014 R2 Administration Guide*.

16.5.5 Monitoring the WebAccess Application

You can monitor the WebAccess Application from your web browser. For more information, see “[Using the WebAccess Application Console](#)” in the *GroupWise 2014 R2 Administration Guide*.

16.6 What's Next

You can further configure and maintain GroupWise WebAccess in the following ways:

Task	Section in the GroupWise 2014 R2 Administration Guide
Scale GroupWise WebAccess to meet the needs of your users and environment	See “ Scaling Your GroupWise WebAccess Installation .”
Control users' access to GroupWise WebAccess	See “ Managing User Access ” and “ Helping Users Who Forget Their GroupWise Passwords .”
Configure the WebAccess Application	See “ Configuring the WebAccess Application .”
Monitor the WebAccess Application	See “ Monitoring the WebAccess Application .”
Control logging for the WebAccess Application	See “ Using WebAccess Application Log Files .”

16.7 GroupWise WebAccess Installation Worksheet

Installation Wizard Field	Value for Your GroupWise System	Explanation
Web Server Platform <ul style="list-style-type: none">♦ Linux♦ Windows		Section 16.3.1, “Selecting the WebAccess Application Platform,” on page 104
POA Network Address <ul style="list-style-type: none">♦ IP address♦ SOAP port (default 7191)		
DVA Network Address <ul style="list-style-type: none">♦ IP address♦ TCP port (default 8301)		Section 16.3.4, “Connecting the WebAccess Application with Supporting Agents,” on page 105
Web Server Information OES 11 <ul style="list-style-type: none">♦ Apache path /etc/opt/novell/httpd/conf.d♦ Tomcat path /var/opt/novell/tomcat/webapps		Section 16.3.2, “Gathering Web Server Information,” on page 104
Web Server Information SLES 11 <ul style="list-style-type: none">♦ Apache path /etc/apache2/conf.d♦ Tomcat path /usr/share/tomcat/webapps		
Web Server Information Windows <ul style="list-style-type: none">♦ Microsoft Internet Information Server (IIS) for Windows♦ Path to the web server’s root directory♦ Website		Section 16.3.2, “Gathering Web Server Information,” on page 104

Installation Wizard Field	Value for Your GroupWise System	Explanation
Configuration File Location		Section 16.3.2, "Gathering Web Server Information," on page 104
Linux		
	<code>/var/opt/novell/ groupwise/webaccess</code>	
Windows		
	<code>c:\novell\groupwise\ webaccess</code>	

17 Setting Up the GroupWise Calendar Publishing Host

The GroupWise Calendar Publishing (CalPub) Host publishes GroupWise users' calendars to the Internet, so that the calendars are readily available to colleagues who are not part of the GroupWise system. The CalPub Host also returns free/busy schedule status to Internet colleagues who want to set up appointments with GroupWise users. The free/busy search checks the main GroupWise Calendar and personal calendars.

17.1 GroupWise Calendar Publishing Host Overview


17.1.1 GroupWise Calendar Publishing Host Functionality

The CalPub Host enables Internet users to view GroupWise users' published calendars and to retrieve free/busy information from their calendars to assist with scheduling available appointment times. Internet users do not need login access to the GroupWise system in order to view published calendars and obtain free/busy status. Information provided by the CalPub Host is publicly available to Internet users everywhere.

For calendar publishing user functionality details, see the [Calendar Publishing User Quick Start](https://www.novell.com/documentation/groupwise2014/gw2014_qs_calpubuser/data/gw2014_qs_calpubuser.html) (https://www.novell.com/documentation/groupwise2014/gw2014_qs_calpubuser/data/gw2014_qs_calpubuser.html).

17.1.2 GroupWise Calendar Publishing Host Components

The CalPub Host includes three components: the CalPub Host Application, which connects to the Internet through a web server, the Post Office Agent (POA), which connects to your GroupWise system, and the GroupWise Administration Service, which provides authentication to the CalPub Host Administration console.



- ♦ **Calendar Publishing Host Application:** The CalPub Host Application, which resides on the web server, provides the browser interface for users across the Internet. As users request calendar and free/busy information from GroupWise users, the CalPub Host Application passes the information between the web browser and the POA.
- ♦ **Post Office Agent:** The POA receives user requests from the CalPub Host Application, accesses post offices and mailboxes to process the requests, and then passes information back to the CalPub Host Application in the form of ICS (Internet Calendaring and Scheduling) files and IFB (Internet Free Busy) files. These files can be imported into GroupWise, Outlook, and Macintosh iCal calendaring applications.

- ♦ **GroupWise Admin Service:** The CalPub Host has an Administration console for configuration and management tasks. You can authenticate to the CalPub Host Admin console by using the user name and password of any GroupWise administrator user.

17.1.3 GroupWise Calendar Publishing Host Security Requirements

The CalPub Host Application can be configured to support the level of security you have established for your Internet/intranet communication.

If you are not concerned about security issues (for example, you only plan to use the CalPub Host Application on a secured intranet), you can install the CalPub Host Application to any web server that provides access for your users and meets the requirements listed in [Section 17.2, “GroupWise Calendar Publishing Host System Requirements,”](#) on page 115.


If you plan to use the CalPub Host Application to provide calendar and free/busy information to users anywhere on the Internet (rather than simply within a secured intranet), and you already have a firewall in place to provide security, you have the following options for configuring the CalPub Host Application:

- ♦ Install the CalPub Host Application inside your firewall and use a proxy service, as described in [“Calendar Publishing Host with a Proxy Service”](#) on page 114. This is the recommended configuration.
- ♦ Install the CalPub Host Application on a web server outside your firewall and have it communicate with a POA through your firewall, as described in [“Calendar Publishing Host without a Proxy Service”](#) on page 115.

Calendar Publishing Host with a Proxy Service

If your firewall includes a proxy service, you can install the CalPub Host Application to a web server inside your firewall. The POA is located on a post office server, which is also located inside the firewall.


In this configuration, only the firewall server with the proxy service is located outside the firewall, as shown in the following illustration.



Calendar Publishing Host without a Proxy Service

If your firewall does not provide a proxy service, you need to install the CalPub Host Application to a web server that is outside the firewall. The POA is located on a post office server, which is located the firewall.

In this configuration, both the web server and the firewall server are located outside the firewall, as shown in the following illustration.



The firewall must allow inbound IP packets to be sent from the web server to the POA's internal or external IP address and the calendar publishing port for the POA (for example, 172.16.5.18:7171). If you are using an external IP address, all POAs that support calendar publishing must be configured to use the same external IP address. For more information about external POA IP addresses, see [“Securing Client Access through an External Proxy Server”](#) in the *GroupWise 2014 R2 Administration Guide*.

In addition, the firewall must allow outbound IP packets to be sent from the POA to the web server. This requires all high ports (above 1023) to be open to outbound IP packets.

17.2 GroupWise Calendar Publishing Host System Requirements

17.2.1 Hardware and Operating System Requirements

- ☐ x86-64 or x86-32 processor
- ☐ Any of the following server operating systems for the Calendar Publishing Host Application:
 - ♦ Novell Open Enterprise Server (OES) 11 or Novell Open Enterprise Server (OES) 2015, plus the latest Support Pack
 - ♦ SUSE Linux Enterprise Server (SLES) 11 or SUSE Linux Enterprise Server (SLES) 12 plus the latest Service Pack

NOTE: On Linux, the X Window System and Open Motif are required by the GUI GroupWise agent server consoles for the Post Office Agent, the Message Transfer Agent, and the Internet Agent.

By default, the GroupWise Linux agents run as services without user interfaces. Starting and stopping the agents when they are running with a user interface is not supported in the GroupWise Administration console.

- ♦ Windows Server 2012 R2, plus the latest Service Pack
- ☐ Adequate server memory as required by the operating system
- ☐ Adequate server disk space:
 - ♦ Approximately 525 MB (shared with the WebAccess Application and the Monitor Application when they are installed on the same web server; varies by platform)
 - ♦ 50 KB per published calendar
 - ♦ 50 KB per user for free/busy searching

17.2.2 Web Server Requirements

The web server that is supported for your operating system:

- ☐ x86-64 or x86-32 processor
- ☐ OES 11 / OES 2015 / SLES 11

Apache 2.2 plus:

- ♦ Tomcat 7
- ♦ ModProxy Module
- ♦ **OES11 / OES 2015 / SLES 11:** IBM Java 8 Runtime Environment (JRE)
- ♦ **SLES 12:** OpenJDK 7

A Linux repository should be available when you run the GroupWise Installation Wizard. Apache, Tomcat, the JRE or JDK, and the ModProxy Module are automatically installed from the Linux repository if they are not already present on the Linux server.

If no Linux repository is available during the GroupWise installation, you are prompted to manually install these required components from the Linux media, and then restart the GroupWise installation.

- ☐ Windows Server 2012 R2

Microsoft Internet Information Server (IIS) 7 or later plus:

- ♦ Tomcat 6
- ♦ Oracle Java 8 Runtime Environment (JRE)
- ♦ Jakarta Connector 1.2

Tomcat 6.0.24, Oracle JRE 8, and Jakarta Connector 1.2 are automatically installed along with the GroupWise software if they are not already present on the Windows server.

- ♦ ISAPI support

ISAPI support is no longer installed by default when you install Windows Server 2008 R2 or later and Internet Information Services (IIS). If ISAPI support was not manually selected when IIS was installed, you can add it after the fact. See

17.2.3 Web Browser Requirements

Any of the following web browsers for the GroupWise Calendar Publishing Host user web pages and the Calendar Publishing Host Administration console:

- ☐ Linux: Mozilla Firefox; Google Chrome
- ☐ Windows: Microsoft Internet Explorer 9 or later; Mozilla Firefox; Google Chrome; Windows Edge
- ☐ Macintosh: The latest version of Safari for your version of Mac OS; Mozilla Firefox; Google Chrome

17.3 Planning a GroupWise Calendar Publishing Host

Use the “[GroupWise Calendar Publishing Host Worksheets](#)” on [page 128](#) to record the information required to install and configure the CalPub Host Application.

The topics in this section present the required information in a convenient planning sequence. The Installation Worksheet organizes the information in the order in which you need it during installation.

17.3.1 Selecting the Calendar Publishing Host Application Platform

The CalPub Host can be installed to a web server on Linux or Windows. See [Section 17.2](#), “[GroupWise Calendar Publishing Host System Requirements](#),” on [page 115](#) for supported web servers.

GROUPWISE CALENDAR PUBLISHING HOST INSTALLATION WORKSHEET

Under **Web Server Platform**, mark whether you plan to install the CalPub Host Application to a Linux or Windows web server.

17.3.2 Gathering Web Server Information

The CalPub Host Application integrates with your web server to pass calendar information gathered by the Post Office Agent to your web browser for display. The location of the CalPub Application files that are installed depends on the web server that it is being integrated with.

The default web server paths vary by platform:

Apache Web Server on OES 11:	<code>/etc/opt/novell/httpd/conf.d</code>
Tomcat on OES 11:	<code>/var/opt/novell/tomcat/webapps</code>
Apache Web Server on SLES 11:	<code>/etc/apache2/conf.d</code>
Tomcat on SLES 11:	<code>/usr/share/tomcat/webapps</code>
Microsoft Internet Information Server (IIS) on Windows:	<code>c:\inetpub\wwwroot</code>
Tomcat on Windows:	<code>c:\novell\tomcat\webapps</code>

GROUPWISE CALENDAR PUBLISHING HOST INSTALLATION WORKSHEET

Under **Web Server Information**, select the type of web server where you plan to install the CalPub Host Application. Also specify the web server's root directory.

On Windows, if the Internet Information Server services more than one website, specify the website where you want to install the CalPub Host Application.

The CalPub Host needs the IP address and TCP port number of the web server so that they can communicate.

GROUPWISE CALENDAR PUBLISHING HOST CONFIGURATION WORKSHEET

Under **Calendar Publishing Host Configuration**, list the IP address of the web server and the web server port number (by default, 80).

17.3.3 Choosing the Calendar Publishing Host Name

You must provide a unique and descriptive name for the CalPub Host. The name might include the platform or location of the CalPub Host, or perhaps the users it serves. You specify this name when you install the CalPub Host Application and again when you configure it in the GroupWise Admin console. The name must be specified identically in both places, including spacing and capitalization.

The CalPub Host name is stored in the `calhost.cfg` file, located in the following folders:

Linux: `/var/opt/novell/groupwise/calhost`

Windows: `c:\novell\groupwise\calhost`

GROUPWISE CALENDAR PUBLISHING HOST INSTALLATION WORKSHEET

Under **Calendar Publishing Host Name**, specify a unique name for this CalPub Host.

GROUPWISE CALENDAR PUBLISHING HOST CONFIGURATION WORKSHEET

Under **Calendar Publishing Host Configuration**, list the name for the CalPub Host name again. Ensure that the names are specified identically on both worksheets.

If desired, provide a helpful description of the CalPub Host.

17.3.4 Determining the URL of the Calendar Publishing Host

The CalPub Host uses the DNS hostname of the web server as part of its base URL.

`http://web_server_address:port/gwcal`

Replace `web_server_address` with the DNS hostname of the web server. Replace `port` with the port number on which the CalPub Host communicates with the web server. The default port number is 80; it does not need to be specified if your web server uses that default.

IMPORTANT: Select the URL carefully. This URL is disseminated by GroupWise users to their Internet colleagues when they publish their personal calendars and free/busy information. If you change the URL later, GroupWise users need to send updated information to Internet colleagues.

You might want to create a generic URL, such as `http://gwcal.example.com/gwcal`, and then configure your network to redirect incoming traffic to the CalPub Host server.

GROUPWISE CALENDAR PUBLISHING HOST CONFIGURATION WORKSHEET

Under **Calendar Publishing Host Configuration**, list the CalPub Host base URL (`http://web_server_address/gwcal`).

You typically need only one CalPub Host in your GroupWise system. However, depending on the size of your GroupWise system and the locations of your GroupWise users, you might need multiple CalPub Hosts in various locations if some users experience slowness when accessing the initial location.

17.3.5 Selecting a Calendar Publishing Host Administrator

The web-based CalPub Admin console is provided for additional configuration of the CalPub Host. You must select at least one GroupWise user to access the Calpub Admin console. You might want to select a GroupWise user who is already a GroupWise system administrator, domain administrator, or post office administrator, but this is not required. Any GroupWise user can be a CalPub Host administrator.

The CalPub administrator logs into the CalPub Admin console using the same user name and password that is used for mailbox access.

GROUPWISE CALENDAR PUBLISHING HOST CONFIGURATION WORKSHEET

Under **Authentication Information**, list at least one GroupWise user to serve as a CalPub Host administrator.

17.3.6 Connecting the Calendar Publishing Host to a POA

The CalPub Host connects to your GroupWise system through the POA of a post office. For initial installation, you enable one POA for calendar publishing. As you roll out calendar publishing to your GroupWise users, you must enable calendar publishing for the POA of every post office where users publish calendars and free/busy information.

The initially selected POA must be configured to communicate with the CalPub Host. The POA server's IP address or DNS hostname is required, along with a calendar publishing port. The default calendar publishing port is 7171.

Use the default port number unless it is already in use on the server.

GROUPWISE CALENDAR PUBLISHING HOST INSTALLATION WORKSHEET

Under **Post Office Agent Information**, specify the IP address or DNS hostname of the POA that will communicate with the CalPub Host, along with the calendar publishing port number. The default calendar publishing port is 7171.

GROUPWISE CALENDAR PUBLISHING HOST CONFIGURATION WORKSHEET

Under **Calendar Publishing Post Office**, transfer the IP address or DNS hostname of the POA, along with the calendar publishing port from the *Installation Worksheet* to the **Configuration Worksheet**. You need this information during installation and during configuration.

For a complete list of default port numbers used by the GroupWise agents, see “[GroupWise Port Numbers](#)” in the *GroupWise 2014 Administration Guide*.

17.3.7 Designing Your Calendar Browse List

The CalPub Host collects a list of published calendars for Internet users to browse and select from at the following URL:

`http://web_server_address/gwcal/calendar`

However, by default, no calendars are displayed in this calendar browse list. You can handle the calendar browse list in three different ways:

- ♦ Do not provide a calendar browse list.

Users need to notify Internet colleagues by email of the URL to access their published calendars.

- ♦ Use the calendar browse list only for calendars of general corporate interest.

If you want to have such a corporate browse list, you restrict which users can list calendars on the browse list, by allowing only a few specific users who manage the corporate calendars to publish to the calendar browse list.

- ♦ Allow most, if not all, users to publish their personal calendars on the calendar browse list.

This open approach to the calendar browse list makes users’ published calendars easily accessible to anyone who knows the URL of the calendar browse list for your GroupWise system.

GROUPWISE CALENDAR PUBLISHING HOST CONFIGURATION WORKSHEET

Under **Calendar Browse List**, mark whether you want to enable the calendar browse list, and if so, what kind (corporate or open).

17.3.8 Selecting Calendar Publishing Settings

After you have set up the CalPub Host, you can configure how you want it to work for your GroupWise users. The following settings are available in the CalPub Admin console:

- ♦ **Enable Calendar Publishing:** Lets users publish personal GroupWise calendars on the Internet. When calendar publishing is enabled, users of the GroupWise client and GroupWise WebAccess can right-click a personal calendar, and then click **Publish** to select options for publishing a personal calendar.
- ♦ **Enable Rules To Move Items to a Published Calendar:** Allows users to create rules that move specific items to a published GroupWise calendar. Rules are disabled by default.

- ♦ **Enable Publish Free/Busy Search:** Allows users to make their appointment information available to external users, so that external users can perform Free/Busy Searches on users' GroupWise calendars. Free/Busy searching is disabled by default. Free/busy publishing can be enabled even if no Calendar Publishing Host has been selected.
- ♦ **Enable Subscribe to Calendar:** Allows users to subscribe to Internet calendars that are updated on a regular basis, such as calendars for sporting events. Calendar subscription is disabled by default. Calendar subscription can be enabled even if no Calendar Publishing Host has been selected.

GROUPWISE CALENDAR PUBLISHING HOST CONFIGURATION WORKSHEET

Under **Calendar Publishing Options**, mark the options you want to enable for the CalPub Host.

17.4 Installing the GroupWise Calendar Publishing Host

As you set up the CalPub Host, use the [GroupWise Calendar Publishing Host Worksheets](#) that you filled out in [Section 17.3, “Planning a GroupWise Calendar Publishing Host,”](#) on page 117 to provide the required information.

17.4.1 Linux: Installing the Calendar Publishing Host Software

- ♦ [“Preparing the Linux Server for the Calendar Publishing Host”](#) on page 121
- ♦ [“Installing the Linux Calendar Publishing Host Software”](#) on page 121

Preparing the Linux Server for the Calendar Publishing Host

- 1 Ensure that the web server where you are installing the CalPub Host Application meets the system requirements listed in [Section 17.2, “GroupWise Calendar Publishing Host System Requirements,”](#) on page 115.
- 2 Ensure that the Linux operating system media is available, either physically or in a repository, in case the Installation Wizard needs to install supporting packages on the Linux server.
- 3 Ensure that the server has a static IP address.
- 4 Continue with [Installing the Linux Calendar Publishing Host Software](#).

Installing the Linux Calendar Publishing Host Software

- 1 In a terminal window, become `root` by entering `su -` and the `root` password.
- 2 Browse to the location of the extracted software, and run the following command to start the install:


```
./install.sh
```
- 3 Type the number for the language in which you want to run the GroupWise Installation Wizard, then press Enter to select **OK**.
- 4 (Optional) Type `1` for **Documentation**, then press Enter to review the Readme, Quick Start, and Installation Guide to better prepare yourself for the installation.
- 5 Type `2` for **Installation**, then press Enter.

- 6 Type **a** to accept the License Agreement and display the Software list.
- 7 Type **3** for **Calendar Publishing Host**, then press Enter to display the Actions list.
- 8 Type **1** for **Install**, then press Enter to install the GroupWise Calendar Publishing Host.

The CalPub Host package is installed on the server. If any supporting packages are not available on the server, the Installation Wizard automatically installs them from the operating system media.
- 9 When the installation is finished, press any key to return to the Installation Options list.
- 10 Type **2** for **Configure**, then press Enter to configure the CalPub Host Application
- 11 Follow the prompts to configure the CalPub Host Application, using the following information from the [Calendar Publishing Host Installation Worksheet](#):

[Calendar Publishing Host Name](#)
[Post Office Agent Information](#)
[Web Server Information](#)
- 12 When the installation is finished, review the instructions for configuring the Calendar Publishing Host.
- 13 Press any key to exit CalPub Host Configuration.
- 14 Exit the GroupWise Installation Wizard.
- 15 Continue with [“Configuring the Calendar Publishing Host in the GroupWise Admin Console” on page 123](#).

17.4.2 Windows: Installing the Calendar Publishing Host Software

- ♦ [“Preparing the Windows Server for the Calendar Publishing Host” on page 122](#)
- ♦ [“Installing the Windows Calendar Publishing Host Software” on page 122](#)

Preparing the Windows Server for the Calendar Publishing Host

- 1 Ensure that the web server where you are installing the CalPub Host Application meets the system requirements listed in [Section 17.2, “GroupWise Calendar Publishing Host System Requirements,” on page 115](#).
- 2 Ensure that the server has a static IP address.
- 3 Continue with [Installing the Windows Calendar Publishing Host Software](#).

Installing the Windows Calendar Publishing Host Software

- 1 Run `setup.exe` at the root of the extracted GroupWise software to start the GroupWise Installation Wizard.
- 2 (Optional) Review the Readme, Quick Start, and Installation Guide to better prepare yourself for the installation.
- 3 Click **GroupWise Calendar Publishing Host**.
- 4 Click **Next** to display the Calendar Publishing Host Name page.

The Installation Wizard provides diagrams that help you understand how the various components interact with each other. Review the diagrams as you provide the requested information.

- 5 Follow the prompts to configure the CalPub Host Application, using the following information from the [Calendar Publishing Host Installation Worksheet](#):

[Calendar Publishing Host Name](#)

[Web Server Information](#)

[Post Office Agent Information](#)

- 6 Click **Next** to display the Installation Summary.
- 7 (Conditional) If prompts appear because your web server is running, decide whether you want the Installation Wizard to stop your web server.
- 8 When the installation is finished, review the instructions for configuring the Calendar Publishing Host.
- 9 Click **Next** to continue.
- 10 When the installation is complete, click **Finish** to exit the Calendar Publishing Host Installation Wizard.

You can choose to have the Installation Wizard restart the web server for you.

Along with the Calendar Publishing Host Application, the Calendar Publishing Host Installation Wizard also installs Tomcat 7 to c:\novell\tomcat, integrates it with your web server, and automatically starts it to support the Calendar Publishing Host Application.

- 11 Exit the GroupWise Installation Wizard.
- 12 Continue with [Configuring GroupWise to Support the Calendar Publishing Host](#).

17.5 Configuring GroupWise to Support the Calendar Publishing Host

After you install the Calendar Publishing Host Application, additional configuration is still required.

17.5.1 Configuring the Calendar Publishing Host in the GroupWise Admin Console

Use the information under [Calendar Publishing Host Configuration](#) and [Calendar Browse List](#) on your [Calendar Publishing Host Configuration Worksheet](#) as you configure the CalPub Host.

- 1 In the [GroupWise Admin console](#), click **System > Calendar Publishing**, then click **New**.
- 2 Fill in the fields to configure the CalPub Host, using the following information from the [Calendar Publishing Host Configuration Worksheet](#)

[Name:](#)

[URL:](#)

[Description:](#)

[Address:](#)

[Port:](#)

IMPORTANT: The name that you specify in the GroupWise Admin console must be the identical name that you specified during installation, including spacing and capitalization, as described in [Section 17.3.3, "Choosing the Calendar Publishing Host Name," on page 118](#).

If you decide that you want to use a different name after you have already installed the CalPub Host Application, you must reinstall the software, and then specify the identical name during the reinstallation that you specify in the GroupWise Admin console.

- 3 Click **OK** to save the CalPub Host configuration information.
- 4 If you want to allow users to add their published calendars to the calendar browse list as the default for your GroupWise system, select **Enable Publishing of Calendars to the Browse List**.
or
If you want to set up a corporate calendar browse list or provide no calendar browse list, leave **Enable Publishing of Calendars to the Browse List** deselected.
- 5 Click **OK** when you are finished.
- 6 Continue with [Enabling Calendar Publishing](#).

17.5.2 Enabling Calendar Publishing

Use the information under **Calendar Publishing Options** on your [GroupWise Calendar Publishing Host Worksheets](#) as you enable calendar publishing.

- 1 In the [GroupWise Admin console](#), click **Post Offices**, then click the name of the post office where you want to enable calendar publishing.
For convenience in testing your Calendar Publishing Host setup, you might want to start with your post office.
- 2 Click **Client Options > Calendar > Web Calendar**.
As you roll out calendar publishing, you can use Client Options to enable it at the domain, post office, and user level.
- 3 Select a Calendar Publishing Host from the drop-down list.
- 4 Set the Web Calendar options as you planned on your [Calendar Publishing Host Installation Worksheet](#).
- 5 Click **OK** to save the Web Calendar settings, then click **Close**.
- 6 Restart Tomcat:

```
OES 11:      rcnovell-tomcat6 restart
SLES 11:      rctomcat6 restart
```

- Windows
1. At the Windows server, click **Start > Administrative Tools > Services**.
 2. Right-click **Tomcat 6**, then click **Restart**.

- 7 Continue with [Configuring a POA for Calendar Publishing](#).

17.5.3 Configuring a POA for Calendar Publishing

After calendar publishing is enabled, the POA can look up calendar information and return it to the CalPub Host in the form of ICS (Internet Calendaring and Scheduling) or IFB (Internet Free Busy) files. Internet users can import these files into GroupWise, Outlook, and Macintosh iCal calendaring applications.

- 1 In the [GroupWise Admin console](#), click **Post Office Agents**, then click the name of the POA that you want to configure for calendar publishing.
- 2 Click **Agent Settings**, then scroll down to the **Calendar Publishing** section.
- 3 Select **Enabled**.
- 4 (Optional) Decrease the number in the **Max Calendar Publishing Threads** field as needed.
The default maximum number of calendar publishing threads is 4. By default, the POA creates 2 calendar publishing threads and adds more as needed. However, you cannot set the maximum higher than 4. The default setting is highly recommended.
- 5 Click **OK** to save the calendar publishing configuration settings.
- 6 As you roll out calendar publishing to your GroupWise users, enable calendar publishing on the POA for each post office where users will publish calendars and free/busy information.
To determine which POAs have been enabled for calendar publishing, see “[Viewing Calendar Publishing Status in the POA Console](#)” in the *GroupWise 2014 R2 Administration Guide*.
- 7 Continue with [Setting Up Calendar Publishing Administration](#).

17.5.4 Setting Up Calendar Publishing Administration

After calendar publishing has been enabled and the POA is communicating with the CalPub Host, you use the CalPub Admin console to monitor the CalPub Host and to make configuration changes as needed. Any GroupWise administrator user can access the CalPub Host Admin console. Use the information under **Authentication Information** on your [Calendar Publishing Host Configuration Worksheet](#) as you set up Calendar Publishing Host administration.

- 1 Edit the `calhost.cfg` file in the following folder:

```
Linux:      /var/opt/novell/groupwise/calhost
Windows:   c:\Novell\GroupWise\calhost
```

- 2 Search to find the following line:

```
#Admin.WebConsole.enable=false
```

- 3 Remove the pound sign (#) to activate the setting.
- 4 Change `false` to `true`.
- 5 Save the file, then exit the text editor.
- 6 Restart Tomcat:

```
OES 11:      rcnovell-tomcat6 restart
SLES 11:     rctomcat6 restart
```

- Windows
1. At the Windows server, click **Start > Administrative Tools > Services**.
 2. Right-click **Tomcat 6**, then click **Restart**.

- 7 Display the CalPub Host Admin console:

`http://server_network_address/gwcal/admin`

- 8 Log in to the CalPub Host Admin console using any GroupWise administrator user name and password.

For more information about the CalPub Host Admin console, see “[Using the CalPub Admin Console](#)” in the *GroupWise 2014 R2 Administration Guide*.

- 9 (Conditional) If additional GroupWise administrators need to access the CalPub Admin console, notify them of the URL to access.
- 10 Continue with [Using the Published Calendar Browse List](#).

17.5.5 Using the Published Calendar Browse List

If you selected **Enable Publishing of Calendars to the Browse List** as your GroupWise system default, continue with [Section 17.6, “Testing GroupWise Calendar Publishing,” on page 126](#).

If you are planning to implement a corporate calendar browse list in the future, you can enable publishing of calendars to the browse list for yourself for testing purposes.

- 1 Browse to and right-click your User object, then click **Properties**.
- 2 Click **GroupWise > Calendar Publishing**.
- 3 Select **Override**, then select **Enable Publishing of Calendars to the Browse List**.
This gives you the right to add your calendars to the calendar browse list so that you can test the setup of the Calendar Publishing Host.
- 4 Continue with [Testing GroupWise Calendar Publishing](#).

17.6 Testing GroupWise Calendar Publishing

17.6.1 Publishing a Personal Calendar

- 1 In the GroupWise client, create and populate a personal calendar, as described in “[Creating a Personal Calendar](#)” in the *GroupWise 2014 R2 Client User Guide*.
- 2 Right-click the personal calendar, then click **Publish**.
- 3 Select **Publish This Calendar**.

For more information, see “[Publishing Personal Calendars on the Internet](#)” in the *GroupWise 2014 R2 Client User Guide*.

This feature is also available in GroupWise WebAccess, as described in “[Publishing Personal Calendars on the Internet](#)” in the *GroupWise 2014 R2 WebAccess User Guide*.

For more information, see the *GroupWise 2014 Calendar Publishing Host User Quick Start*.

- 4 Click **Send Publish Location**, then address and send the resulting message, which provides the URL from which Internet colleagues can obtain your calendar information.

The URL has the following format:

`http://calpubhost_server/gwcal/freebusy/user_name@internet_domain`

- 5 Click **OK** to publish the selected personal calendar.

- 6 Check your mailbox for the notification sent by the Calendar Publishing Host.
- 7 Continue with [Displaying the Browse List of Calendars](#).

17.6.2 Displaying the Browse List of Calendars

- 1 Display the following URL:

`http://web_server_address/gwcal/calendar`

Your newly published personal calendar should appear on the list.
- 2 Click your calendar to view it in its published format.

This assures you that your calendar is available for access by users across the Internet.

17.6.3 Publishing Free/Busy Information

- 1 In the GroupWise client, click **Tools > Options**.
- 2 Click **Calendar > Free/Busy**.
- 3 Click **Send Free/Busy Publish Location**, then address and send the resulting message, which provides the URL from which Internet colleagues can obtain your free/busy information.
- 4 Click **OK**, then click **Close**.
- 5 Check your mailbox for the notification sent by the Calendar Publishing Host.
- 6 Continue with [What's Next](#).

17.7 What's Next

You can further configure and maintain the Calendar Publishing Host in the following ways:

Task	Section in the <i>GroupWise 2014 R2 Administration Guide</i>
Using the CalPub Host Admin console to change the configuration of the CalPub Host	See " Configuring the Calendar Publishing Host ."
Changing the appearance of the calendar browse list to represent your company	See " Customizing the Calendar Publishing Host Logo ."
Restricting the posted list of calendars to those of corporate importance	See " Creating a Corporate Calendar Browse List ."
Monitoring the CalPub Host at the POA console and through CalPub Host log files	See " Monitoring Calendar Publishing ."

17.8 GroupWise Calendar Publishing Host Worksheets

17.8.1 Calendar Publishing Host Installation Worksheet

Installation Wizard Field	Value for Your GroupWise System	Explanation
Web Server Platform <ul style="list-style-type: none">♦ Linux♦ Windows		Section 17.3.1, "Selecting the Calendar Publishing Host Application Platform," on page 117
Calendar Publishing Host Name		Section 17.3.4, "Determining the URL of the Calendar Publishing Host," on page 118
Post Office Agent Information <ul style="list-style-type: none">♦ POA network address<ul style="list-style-type: none">♦ IP address♦ DNS hostname♦ Calendar publishing port (default 7171)		Section 17.3.6, "Connecting the Calendar Publishing Host to a POA," on page 119
Web Server Information OES 11 <ul style="list-style-type: none">♦ Apache path <code>/etc/opt/novell/httpd/conf.d</code>♦ Tomcat path <code>/var/opt/novell/tomcat/webapps</code>		Section 17.3.2, "Gathering Web Server Information," on page 117
Web Server Information SLES 11 <ul style="list-style-type: none">♦ Apache path <code>/etc/apache2/conf.d</code>♦ Tomcat path <code>/usr/share/tomcat/webapps</code>		Section 17.3.2, "Gathering Web Server Information," on page 117
Web Server Information Windows <ul style="list-style-type: none">♦ Microsoft Internet Information Server (IIS) for Windows♦ Path to the web server's root directory♦ Website		Section 17.3.2, "Gathering Web Server Information," on page 117

17.8.2 Calendar Publishing Host Configuration Worksheet

Configuration Field	Value for Your GroupWise System	Explanation
Calendar Publishing Host Configuration		Section 17.3.3, "Choosing the Calendar Publishing Host Name," on page 118
♦ Name		
♦ URL		Section 17.3.4, "Determining the URL of the Calendar Publishing Host," on page 118
♦ Description		
♦ IP address		Section 17.3.2, "Gathering Web Server Information," on page 117
♦ TCP port		
Calendar Browse List		Section 17.3.7, "Designing Your Calendar Browse List," on page 120
♦ Yes		
♦ Corporate (restricted)		
♦ Open		
♦ No		
Calendar Publishing Options		Section 17.3.8, "Selecting Calendar Publishing Settings," on page 120
♦ Enable calendar publishing		
♦ Enable rules to move items to a published calendar		
♦ Enable subscribe to calendar		
♦ Enable publish free/busy searches		
Calendar Publishing Post Office		Section 17.3.6, "Connecting the Calendar Publishing Host to a POA," on page 119
♦ Name		
♦ POA network address		
♦ IP address		
♦ DNS hostname		
♦ Calendar publishing port (default 7171)		
Authentication Information		Section 17.3.5, "Selecting a Calendar Publishing Host Administrator," on page 119
♦ GroupWise user name		

18 Setting Up GroupWise Monitor

GroupWise Monitor is a monitoring and management tool that allows you to monitor GroupWise agents from any location where you are connected to the Internet and have access to a web browser. Some agent administration can also be performed from your web browser if the agent console is password protected.

IMPORTANT: If you are installing GroupWise Monitor in a clustered server environment, see the “[Clustering](#)” in the *GroupWise 2014 R2 Interoperability Guide* before you install Monitor.

18.1 GroupWise Monitor Overview

18.1.1 GroupWise Monitor Functionality

GroupWise Monitor is a monitoring and management tool that allows you to monitor GroupWise agents from any location where you are connected to the Internet and have access to a web browser. Some agent administration can also be performed from your web browser. Monitor provides more detail than is provided on the System page in the GroupWise Admin console.

You can install Monitor on either Linux or Windows. Either version can monitor agents on both Linux and Windows. Depending on the installation platform, two or three different monitoring environments are available:

- ♦ **Monitor Web Console:** The Monitor Web console, provided by the Monitor Application, takes advantage of your web server’s capabilities to make agent status information available to you when you are outside your firewall.
- ♦ **Monitor Agent Console:** The Monitor Agent console, provided by the Monitor Agent itself, can be used only behind your firewall, but it provides capabilities that are not available in the main Monitor Web console. This section focuses on using the full-featured Monitor Agent console.


NOTE: The Monitor Web console and the Monitor Agent console are available on both Linux and Windows because they are browser based.

- ♦ **Windows Monitor Agent Server Console:** The Windows Monitor Agent server console is available only on the Windows server where the Windows Monitor Agent runs and only if you run the Monitor Agent as an application, rather than as a Windows service. All agent configuration tasks can be performed at the Windows Monitor Agent server console, but some reports are not available.

Specific differences in functionality between the three Monitor consoles are summarized in “[Comparing the Monitor Consoles](#)” in the *GroupWise 2014 R2 Administration Guide*.

18.1.2 GroupWise Monitor Components

GroupWise Monitor consists of two components: the Monitor Agent and the Monitor Application.



- ♦ **Monitor Agent:** The Monitor Agent continuously polls the POA, MTA, and GWIA; gathers status information from them; and displays the status information in the Monitor Agent console. The Monitor Agent also services requests for agent status information from the Monitor Application, which displays the Monitor Web console.
- ♦ **Monitor Application:** The Monitor Application extends the capability of your web server so that agent status information can be displayed in your web browser in the Monitor Web console.

18.1.3 One Monitor Server versus Two

The Monitor Agent and the Monitor Application can run together on a Linux server or a Windows server. The server where they run together must be a web server because the Monitor Application is installed into the web server.

The Monitor Agent and the Monitor Application can also run on different servers. The security issues discussed in [Monitor Security Requirements](#) might determine whether you run the Monitor Agent on the same server with the web server and the Monitor Application.

18.1.4 Monitor Security Requirements

GroupWise Monitor can be configured to support the level of security you have established for your Internet/intranet communication.

If you are not concerned about security issues (for example, you plan to use Monitor only on a secured intranet), you can install the Monitor components to any servers that provide access for your GroupWise administrators and that meet the requirements listed in [Section 18.2, “GroupWise Monitor System Requirements,”](#) on page 134.


If you plan to use Monitor to provide GroupWise administrators with access to your GroupWise system from anywhere on the Internet (rather than simply within a secured intranet), and you already have a firewall in place to provide security, you have the following options for configuring Monitor:

- ♦ Install both Monitor components inside your firewall and use a proxy service. See [“Configuring Monitor with a Proxy Service”](#) on page 133. This is the recommended configuration.
- ♦ Install the Monitor Application to a web server outside your firewall and the Monitor Agent on a server inside your firewall. See [“Configuring Monitor without a Proxy Service”](#) on page 133.

Configuring Monitor with a Proxy Service

If your firewall includes a proxy service, you can install the Monitor Application to a web server inside your firewall, and the Monitor Agent to another server inside the firewall, as shown in the following illustration.

In this configuration, only the firewall server with the proxy service is located outside the firewall, as shown in the following illustration.




If desired, the Monitor Agent can also be installed to the web server rather than to a separate server, as described in [Section 18.1.3, "One Monitor Server versus Two,"](#) on page 132.

Configuring Monitor without a Proxy Service

If your firewall does not provide a proxy service, you need to install the Monitor Application to a web server that is outside the firewall. However, the Monitor Agent requires direct access to a GroupWise domain folder, so it needs to be installed to a server that is located within the firewall. It should be installed to the same server where a domain folder is located.

In this configuration, both the web server and the firewall server are located outside the firewall, as shown in the following illustration.



The firewall must allow inbound IP packets to be sent from the web server to the IP address and port number of the Monitor Agent (for example, 172.16.5.18:8200).

In addition, the firewall must allow outbound IP packets to be sent from the Monitor Agent to the web server. This requires all high ports (above 1023) to be open to outbound IP packets.

18.1.5 Monitor and the GroupWise High Availability Service on Linux

The Monitor Agent can be used with the GroupWise High Availability service (*gwha*), which runs on Linux, to automatically restart GroupWise agents when they stop unexpectedly. For setup instructions, see [“Automatically Restarting the Linux GroupWise Agents with the GroupWise High Availability Service” on page 83](#).

There is no GroupWise High Availability service on Windows. Windows includes a mechanism for restarting services automatically when they stop unexpectedly. For more information, see [“Clustering”](#) in the *GroupWise 2014 R2 Interoperability Guide*.

18.2 GroupWise Monitor System Requirements

18.2.1 Hardware and Operating System Requirements

- ☐ x86-64 processor for the Monitor Agent
- ☐ x86-64 or x86-32 processor for the Monitor Application
- ☐ Any of the following server operating systems for the Monitor Agent and the Monitor Application:
 - ♦ Novell Open Enterprise Server (OES) 11 or Novell Open Enterprise Server (OES) 2015, plus the latest Support Pack
 - ♦ SUSE Linux Enterprise Server (SLES) 11 or SUSE Linux Enterprise Server (SLES) 12 plus the latest Service Pack

NOTE: On Linux, the X Window System and Open Motif are required by the GUI GroupWise agent server consoles for the Post Office Agent, the Message Transfer Agent, and the Internet Agent.

By default, the GroupWise Linux agents run as services without user interfaces. Starting and stopping the agents when they are running with a user interface is not supported in the GroupWise Administration console.

- ♦ Windows Server 2012 R2, plus the latest Service Pack
- ☐ Adequate server memory as required by the operating system
- ☐ Adequate server disk space:
 - ♦ Approximately 40 MB for the Monitor Agent (varies by platform)
 - ♦ Approximately 525 MB for the Monitor Application (shared with the WebAccess Application and the Calendar Publishing Host Application when they are installed on the same web server; varies by platform)

18.2.2 Web Server Requirements

The web server that is supported for your operating system:

- ☐ x86-64 or x86-32 processor
- ☐ OES 11 / OES 2015 / SLES 11

Apache 2.2 plus:

- ♦ Tomcat 7
- ♦ ModProxy Module
- ♦ **OES11 / OES 2015 / SLES 11:** IBM Java 8 Runtime Environment (JRE)
SLES 12: OpenJDK 7

A Linux repository should be available when you run the GroupWise Installation Wizard. Apache, Tomcat, the JRE or JDK, and the ModProxy Module are automatically installed from the Linux repository if they are not already present on the Linux server.

If no Linux repository is available during the GroupWise installation, you are prompted to manually install these required components from the Linux media, and then restart the GroupWise installation.

- ☐ Windows Server 2012 R2

Microsoft Internet Information Server (IIS) 7 or later plus:

- ♦ Tomcat 6
- ♦ Oracle Java 8 Runtime Environment (JRE)
- ♦ Jakarta Connector 1.2

Tomcat 6.0.24, Oracle JRE 8, and Jakarta Connector 1.2 are automatically installed along with the GroupWise software if they are not already present on the Windows server.

- ♦ ISAPI support

ISAPI support is no longer installed by default when you install Windows Server 2008 R2 or later and Internet Information Services (IIS). If ISAPI support was not manually selected when IIS was installed, you can add it after the fact. See

18.2.3 Web Browser Requirements

Any of the following web browsers for the Monitor console:

- ☐ Linux: Mozilla Firefox; Google Chrome
- ☐ Windows: Microsoft Internet Explorer 10 or later; Mozilla Firefox; Windows Edge
- ☐ Macintosh: Mozilla Firefox; Google Chrome; Safari

18.3 Planning GroupWise Monitor

Use the “[GroupWise Monitor Installation Worksheets](#)” on page 144 to record your decisions about how to install GroupWise Monitor.

The topics in this section present the required information in a convenient planning sequence. The Installation Worksheet organizes the information in the order in which you need it during installation.

IMPORTANT: If you are installing GroupWise Monitor in a clustered server environment, see the “[Clustering](#)” in the [GroupWise 2014 Interoperability Guide](#) before you install Monitor.

18.3.1 Deciding Where to Install the GroupWise Monitor Components

After reviewing [Section 18.1, “GroupWise Monitor Overview,”](#) on page 131 and the system requirements listed in [Section 18.2, “GroupWise Monitor System Requirements,”](#) on page 134, plan where you want to install the Monitor components in your system.

- ♦ “[Monitor Agent Server](#)” on page 136
- ♦ “[Web Server](#)” on page 137

Monitor Agent Server

The Monitor Agent runs on Linux and Windows. On Linux, the Monitor Agent runs as a daemon. On Windows, the Monitor Agent runs as a Windows service or as an application. When the Monitor Agent runs as an application, it has a user interface on the Windows server. When it runs as a Windows service, it does not.

If you want to install the Monitor Agent and the Monitor Application to the same server, you can install them at the same time. If you want to install them to different servers, you must run the Monitor Installation program twice, once for each server. For example, you might want to install the Monitor Application on Linux for use with a Linux web server, but you might want to install the Monitor Agent on Windows so that you can use its server console, which is not available on Linux.

The Monitor Agent needs to communicate with an MTA. If possible, install the Monitor Agent on the same server where a domain and MTA are already located. If you want to install the Monitor Agent on its own server, consider creating a domain on that server specifically for helping the Monitor Agent communicate with the rest of your GroupWise system.

The installation folder for the Monitor Agent depends on the platform:

Linux: The Linux Monitor Agent is automatically installed to `/opt/novell/groupwise/agents`.
Windows: The default installation directory is `c:\Program Files\Novell\GroupWise Monitor`.

On Windows, you can specify a different directory during installation. On Linux, you cannot.

GROUPWISE MONITOR AGENT INSTALLATION WORKSHEET

Under **Agent Software Platform**, mark the platform (Linux or Windows) where you plan to install the Monitor Agent.

Under **Server Information**, specify the directory on the Linux or Windows server where you plan to install the Monitor Agent software.

Web Server

The Monitor Application can be installed to a web server on Linux or Windows.

GROUPWISE MONITOR APPLICATION INSTALLATION WORKSHEET

Under **Web Server Platform**, mark whether you plan to install the Monitor Application to a Linux or Windows web server.

The Monitor Application integrates with your web server to pass agent status information gathered by the Monitor Agent to your web browser for display in the Monitor web console. The location of the Monitor Application files that are installed depends on the web server that it is being integrated with. The default web server paths vary by platform:

Apache Web Server on OES 11:	/etc/opt/novell/httpd/conf.d
Tomcat on OES 11:	/var/opt/novell/tomcat6/webapps
Apache Web Server on SLES 11:	/etc/apache2/conf.d
Tomcat on SLES 11:	/usr/share/tomcat6/webapps
Microsoft Internet Information Server (IIS) on Windows:	c:\inetpub\wwwroot
Tomcat on Windows:	c:\novell\tomcat6\webapps

GROUPWISE MONITOR APPLICATION INSTALLATION WORKSHEET

Under **Web Server Information**, select the type of web server you want to use with Monitor, and specify the directory path to the web server root directory.

On Windows, if the Internet Information Server services more than one website, specify the website where you want to install the Monitor Application.

18.3.2 Determining the Monitor Agent's Configuration

As you install the Monitor Agent, you are prompted to supply the configuration information:

- ♦ [Monitor Agent Network Address](#)
- ♦ [Domain Folder](#)

Monitor Agent Network Address

The Monitor Agent communicates with the Monitor Application and with monitored agents by way of TCP/IP.

GROUPWISE MONITOR AGENT INSTALLATION WORKSHEET

Under **Server Information**, record the IP address or DNS hostname of the Linux or Windows server where you plan to install the Monitor Agent software. Use the default port number of 8200 unless that number is already in use on that server.

If you are installing the Monitor Application on a different server from where you are installing the Monitor Agent, record the same information under **Monitor Agent Information** on the [GroupWise Monitor Agent Installation Worksheet](#).

For a complete list of default port numbers used by the GroupWise agents, see “[GroupWise Port Numbers](#)” in the *GroupWise 2014 Administration Guide*.

Domain Folder

The Monitor Agent can gather information about the locations of GroupWise agents to monitor by reading from a domain database. Using the gathered information, the Monitor Agent can display a list of monitored agents when you start it for the first time.

GROUPWISE MONITOR AGENT INSTALLATION WORKSHEET

Under **Domain Location**, specify the path to a domain folder where an MTA is running.

If the domain is located on a different server from where you are installing the Monitor Agent, specify the IP address or DNS hostname of the domain server.

Service vs. Application (Windows Only)

On Windows, you can choose to install the Monitor Agent as a Windows service or an application.

When you install the Monitor Agent as an application, it displays a Monitor Agent console on the server where it runs. You can start the Windows Monitor Agent on the Windows **Start** menu, or you can create a desktop icon for it.

When you install the Monitor Agent as a service, it does not display a server console. You manage it by using the Windows Services administrative tool.

GROUPWISE MONITOR AGENT INSTALLATION WORKSHEET

Under **Windows Installation Option**, mark **Service** or **Application**.

18.3.3 Determining the Monitor Application's Configuration

Monitor Application configuration information is stored in a configuration file (`gwmonitor.cfg`), located in the following directories:

Linux: `/var/opt/novell/groupwise/monitor`

Windows: `c:\novell\groupwise\gwmonitor`

The default configuration information is sufficient for an initial Monitor Application installation. For more information about configuring the Monitor Application, see “[Configuring the Monitor Application](#)” in the *GroupWise 2014 R2 Administration Guide* after you have installed the Monitor Application.

18.4 Installing the GroupWise Monitor Software

As you install the Monitor software, use the [GroupWise Monitor Installation Worksheets](#) that you filled out in [Section 18.3, “Planning GroupWise Monitor,”](#) on page 136 to provide the required information.

IMPORTANT: If you are installing GroupWise Monitor in a clustered server environment, see the “[Clustering](#)” in the *GroupWise 2014 Interoperability Guide* before you install Monitor.

18.4.1 Linux: Installing the GroupWise Monitor Software

- ♦ “Preparing the Linux Server for GroupWise Monitor” on page 139
- ♦ “Installing and Configuring the Linux Monitor Agent” on page 139
- ♦ “Installing and Configuring the Linux Monitor Application” on page 140
- ♦ “Starting the Linux Monitor Agent” on page 141

Preparing the Linux Server for GroupWise Monitor

- 1 Ensure that the server where you are installing the Monitor Agent meets the system requirements listed in [Section 18.6, “GroupWise Monitor Installation Worksheets,”](#) on page 144.
- 2 Ensure that the web server where you are installing the Monitor Application meets the system requirements listed in [Section 18.2.2, “Web Server Requirements,”](#) on page 135.
- 3 Ensure that the server has a static IP address.
- 4 Ensure that the firewall on the server has the ports open that are used by the Monitor Agent and/or the Monitor Application and the web server.
For assistance, see “[GroupWise Port Numbers](#)” in the *GroupWise 2014 R2 Administration Guide*.
- 5 Continue with [Installing and Configuring the Linux Monitor Agent](#).

Installing and Configuring the Linux Monitor Agent

- 1 In a terminal window, become `root` by entering `su -` and the `root` password.
- 2 Browse to the location of the extracted software, and run the following command to start the install:


```
./install.sh
```
- 3 Type the number for the language in which you want to run the GroupWise Installation Wizard, then press Enter to select **OK**.
- 4 (Optional) Type **1** for **Documentation**, then press Enter to review the Readme, Quick Start, and Installation Guide to better prepare yourself for the installation.
- 5 Type **2** for **Installation**, then press Enter.
- 6 Type **a** to accept the License Agreement and display the Software list.
- 7 Type **4** for **GroupWise Monitor Agent**, then press Enter to display the Actions list.
- 8 Type **1** for **Install**, then press Enter to install the Monitor Agent.

The Monitor Agent package is installed on the server. If any supporting packages are not available on the server, the Installation Wizard automatically installs them from the operating system media.

During the installation, any other GroupWise agents on the server are stopped and then started again after the Monitor software has been installed.

- 9 Type **2** for **Configure**, then press Enter to configure the Monitor Agent.
- 10 Follow the prompts to configure the Monitor Agent, using the following information from the [GroupWise Monitor Agent Installation Worksheet](#):

[Domain Directory Path](#)
- 11 Type **1** for **Yes**, then press Enter, to configure the Monitor Agent to automatically start when the server restarts.

IMPORTANT: The Monitor Agent must be running in order for the GroupWise High Availability Service (gwha) to automatically restart the GroupWise agents if they stop unexpectedly. For more information, see [“Automatically Restarting the Linux GroupWise Agents with the GroupWise High Availability Service”](#) on page 83.

12 Press any key to exit the Monitor Agent Configuration.

13 Type b for Back to return to the Software list.

14 In a terminal window, start the Monitor Agent:

```
rcgrpwise-ma start
```

NOTE: Unlike the other GroupWise agents, you do not need to be logged in as `root` in order to start the Monitor Agent.

15 Continue with [Installing and Configuring the Linux Monitor Application](#).

Installing and Configuring the Linux Monitor Application

1 If you are installing the Monitor Application on the same server where you just installed the Monitor Agent, continue with [Step 2](#).

or

If you are installing the Monitor Application on a different server from where you installed the Monitor Agent:

1a Access the web server where you want to install the Monitor Application.

1b In a terminal window, become `root` by entering `su -` and the `root` password.

1c Browse to the location of the extracted software, and run the following command to start the install:

```
./install.sh
```

1d Type the number for the language in which you want to run the GroupWise Installation Wizard, then press Enter to select **OK**.

1e Type 2 for **Installation**, then press Enter.

1f Type a to accept the License Agreement and display the Software list.

2 Type 5 for **GroupWise Monitor Application**, then press Enter to display the Actions list.

3 Type 1 for **Install**, then press Enter to install the Monitor Application.

The Monitor Application is installed on the server. If any supporting packages are not available on the server, the Installation Wizard automatically installs them from the operating system media.

4 When the installation is finished, press any key to return to the Installation Options list.

5 Type 2 for **Configure**, then press Enter to configure the Monitor Application.

6 Follow the prompts to configure the Monitor Application, using the following information from the [GroupWise Monitor Application Installation Worksheet](#):

[Server Information](#)

[Web Server Information](#)

7 Press any key to exit Monitor Application Configuration.

8 Exit the GroupWise Installation Wizard.

- 9 (Conditional) If you use a proxy service, follow the instructions in [“Configuring Proxy Service Support for the Monitor Console”](#) in the *GroupWise 2014 R2 Administration Guide*.
- 10 Continue with [Starting the Linux Monitor Agent](#).

Starting the Linux Monitor Agent

- 1 Use the following commands to manage the Monitor Agent:

```
rcgrpwise-ma start
rcgrpwise-ma restart
rcgrpwise-ma stop
rcgrpwise-ma status
```

- 2 (Optional) If desired, you can run the Monitor Agent executable directly:

- 2a Change to the GroupWise agent bin folder.

```
cd /opt/novell/groupwise/agents/bin
```

- 2b Use one of the following commands to start the Monitor Agent:

```
./gwmon --home /domain_folder &
./gwmon --ipa domain_server_ip_address --ipp mta_port_number &
```

- 3 For instructions on using the Monitor consoles, continue with [Section 18.5, “Testing GroupWise Monitor,”](#) on page 143.

18.4.2 Windows: Installing the GroupWise Monitor Software

- ♦ [“Preparing the Windows Server for GroupWise Monitor”](#) on page 141
- ♦ [“Installing the Windows GroupWise Monitor Software”](#) on page 142
- ♦ [“Starting the Windows Monitor Agent”](#) on page 142

Preparing the Windows Server for GroupWise Monitor

- 1 Ensure that the server where you are installing the Monitor Agent meets the system requirements listed in [Section 18.6, “GroupWise Monitor Installation Worksheets,”](#) on page 144.
- 2 Ensure that the web server where you are installing the Monitor Application meets the system requirements listed in [Section 18.2.2, “Web Server Requirements,”](#) on page 135.
- 3 Ensure that the server has a static IP address.
- 4 Ensure that no GroupWise agents are currently running on the Windows server where you plan to install the Monitor Agent.
- 5 Ensure that the firewall on the server has the ports open that are used by the Monitor Agent and/or the Monitor Application and the web server.
For assistance, see [“GroupWise Port Numbers”](#) in the *GroupWise 2014 Administration Guide*.
- 6 Continue with [Installing the Windows GroupWise Monitor Software](#).

Installing the Windows GroupWise Monitor Software

- 1 Run `setup.exe` at the root of the extracted GroupWise software to start the GroupWise Installation Wizard.
- 2 Click **GroupWise Monitor**, accept the License Agreement, then click **Next**.
- 3 Click **Next** to display the GroupWise Monitor Components page.

The Installation Wizard provides diagrams that help you understand how the various components interact with each other. Review the diagrams as you provide the requested information.
- 4 (Conditional) If you are installing the Monitor Agent, follow the prompts to provide the information from your [GroupWise Monitor Agent Installation Worksheet](#):

[Server Information](#)

[Domain Directory](#)

[Service vs. Application](#)

- 5 (Conditional) If you are installing the Monitor Application, follow the prompts to provide the information from your [GroupWise Monitor Application Installation Worksheet](#):

[Monitor Agent Information](#) (This page does not appear when you install the Monitor Agent and the Monitor Application together on the same server.)

[Web Server Information](#)

- 6 Review the Installation Summary, then click **Install**.
- 7 (Conditional) If prompts appear because your web server is running, decide whether you want the Installation Wizard to stop your web server.
- 8 When the installation is complete, click **Finish** to exit the Monitor Installation program.

You can choose to have the Monitor Installation program start the Monitor Agent and restart the web server for you.
- 9 Click **Finish** to exit the GroupWise Installation program.

If you chose to start the Monitor Agent immediately, the Monitor Agent server console displays on the Windows server.

If the Monitor Agent does not start successfully, see [“Manually Starting the Windows Agents As Applications for Troubleshooting”](#) on page 91.
- 10 (Conditional) If you use a proxy service, follow the instructions in [“Configuring Proxy Service Support for the Monitor Console”](#) in the *GroupWise 2014 Administration Guide*.
- 11 Continue with [Testing GroupWise Monitor](#).

Starting the Windows Monitor Agent

- 1 If you installed the Monitor Agent as a Windows service, use the Services administrative tool to start and stop it.

or

If you installed the Monitor Agent as an application, start it on the Windows Start menu, or create a desktop icon to start it.
- 2 Continue with [Testing GroupWise Monitor](#).

18.5 Testing GroupWise Monitor

Monitor has two different web-based consoles. The main Monitor web console uses the capabilities of your web server to provide access from outside your firewall. The web-based Monitor Agent console is provided by the Monitor Agent itself and provides additional functionality beyond that which is available from outside your firewall.

On Windows, the Monitor Agent also has a server console that displays only on the Windows server where the Monitor Agent runs.

18.5.1 Using the Monitor Web Console

To display agent status information in your web browser from outside your firewall, enter the Monitor Web console URL in your web browser:

```
http://network_address/gwmon/gwmonitor
```

Replace *network_address* with the IP address or DNS hostname of the server where your web server runs. The Monitor console appears.

You can use this same URL to view the same agent status information in various browsers and on mobile devices.

You can perform many of the same monitoring activities at the Monitor Web console as you can at the Windows Monitor Agent server console. Refer to the online help in the Monitor Web console for additional information about each Monitor Web console page.

For more information about using the Monitor consoles, see “[Monitor](#)” in the *GroupWise 2014 R2 Administration Guide*.

18.5.2 Using the Monitor Agent Console

To display agent status information in your web browser from inside your firewall, enter the Monitor Agent console URL in your web browser:

```
http://network_address:8200
```

For instructions on protecting the Monitor Agent console with a password, see “[Securing the Monitor Web Console](#)” in the *GroupWise 2014 R2 Administration Guide*.

18.5.3 Using the Windows Monitor Agent Server Console

To start the Monitor Agent on a Windows server and display the Windows Monitor Agent server console click **Search > GroupWise Monitor**. You might find it convenient to pin GroupWise Monitor to the Windows **Start** menu for future use.

The Windows Monitor Agent server console appears.

In the Monitor Agent server console, you can perform many activities, for example:

- ♦ Use items on the **Configuration** menu to configure the Windows Monitor Agent as needed.
- ♦ Use items on the **View** menu to choose how much and what kind of agent status information to display.
- ♦ Create agent groups in order to monitor related agents together.

- ♦ Use items on the **Reports** menu to check the status of links throughout your GroupWise system and to organize status information into a format that can be emailed or printed.
- ♦ Use items on the **Actions** menu to control agent polling.

For more information about using the Windows Monitor Agent server console, see “[Monitor](#)” in the *GroupWise 2014 R2 Administration Guide*.

18.6 GroupWise Monitor Installation Worksheets

18.6.1 GroupWise Monitor Agent Installation Worksheet

Installation Program Field	Value for Your GroupWise System	Explanation
Monitor Component		Section 18.1, “GroupWise Monitor Overview,” on page 131
♦ GroupWise Monitor Agent		
Agent Software Platform		Section 18.3.1, “Deciding Where to Install the GroupWise Monitor Components,” on page 136
♦ Linux		
♦ Windows		
Server Information		Section 18.3.1, “Deciding Where to Install the GroupWise Monitor Components,” on page 136
♦ Installation path		
Linux:		“Monitor Agent Network Address” on page 137
/opt/novell/groupwise/ agents/bin		
Windows:		
c:\Program Files\Novell\GroupWise Monitor		
♦ Network address		
♦ IP address		
♦ DNS hostname		
♦ TCP port (default 8200)		
Domain Location		“Domain Folder” on page 138
♦ Server		
♦ Path		
Windows Installation Option		“Service vs. Application (Windows Only)” on page 138
♦ Service		
♦ Application		

18.6.2 GroupWise Monitor Application Installation Worksheet

Installation Program Field	Value for Your GroupWise System	Explanation
Monitor Component <ul style="list-style-type: none">♦ GroupWise Monitor Application		Section 18.1, “GroupWise Monitor Overview,” on page 131
Web Server Platform <ul style="list-style-type: none">♦ Linux♦ Windows		Section 18.1, “GroupWise Monitor Overview,” on page 131
Monitor Agent Information <ul style="list-style-type: none">♦ IP address♦ DNS hostname♦ TCP port (default 8200)		“Monitor Agent Network Address” on page 137
Web Server Information: OES 11 <ul style="list-style-type: none">♦ Apache path /etc/opt/novell/httpd/ conf.d♦ Tomcat path /var/opt/novell/tomcat6/ webapps		Section 18.3.1, “Deciding Where to Install the GroupWise Monitor Components,” on page 136
Web Server Information: SLES 11 <ul style="list-style-type: none">♦ Apache path /etc/apache2/conf.d♦ Tomcat path /usr/share/tomcat6/ webapps		Section 18.3.1, “Deciding Where to Install the GroupWise Monitor Components,” on page 136
Web Server Information: Windows <ul style="list-style-type: none">♦ Microsoft Internet Information Server (IIS) for Windows♦ Path to the web server’s root directory♦ Website c:\inetpub\wwwroot		Section 18.3.1, “Deciding Where to Install the GroupWise Monitor Components,” on page 136

19 Setting Up GroupWise Calendar Server

The GroupWise Calendar Server allows users to use CalDAV and CardDAV to sync their GroupWise Calendar and GroupWise Frequent Contacts book to their Mac devices. CalDAV also lets user run free/busy searches against other users in the GroupWise system.

19.1 GroupWise Calendar Server Overview

GroupWise Calendar Server allows you to use CalDAV and CardDAV to sync your GroupWise Calendar and your GroupWise Contacts book to your Mac. For full GroupWise functionality on Mac you need to also have the following configured:

- ♦ **IMAP:** Provides incoming mail server for the Mac Mail app.
- ♦ **SMTP:** Provides outgoing mail server for the Mac Mail app.

19.2 GroupWise Calendar Server System Requirements

19.2.1 Server Requirements

- ☐ The Calendar Server install is only supported on a Linux server.

19.2.2 Configuration Requirements

The majority of the configuration is done in a web browser. The following files are required on the machine where you are running the configuration:

- ☐ Valid certificate for the Calendar Server.
- ☐ Novell Push Notification Service certificate to push notifications to Mac devices. The NPNS certificate can be created at novell.com/npns.

19.3 Planning GroupWise Calendar Server

Use the [GroupWise Calendar Server Worksheet](#) to record the information required to install the Calendar Server application.

19.3.1 Gathering the Primary Domain Information

The Calendar Server needs the server information for the GroupWise Primary Domain server to be able to connect to the GroupWise system. The Primary Domain server host name or IP address, the admin service port, and the admin service username and password are required.

GroupWise Calendar Server Worksheet

Under *GroupWise Domain Information*, enter the host name or IP address and admin service port, username, and password.

19.3.2 Gathering the Server Information

The Calendar Server requires an SSL port for secure communication to your Mac devices. Specify the SSL port you want to use if you don't want to use the default port 443.

GroupWise Calendar Server Worksheet

Under *Server Information*, enter an SSL port for the server.

If you are installing the Calendar Server in a cluster, you can bind to a specific IP address from the server or use all available IP addresses. If you are not installing in a cluster, leave **Listen on all interfaces** selected.

GroupWise Calendar Server Worksheet

Under *Server Information*, specify the IP address to listen on or specify **Listen on all interfaces**.

An SSL/TLS certificate is required for the Calendar Server service. Using a public or private CA, create a certificate and key (if applicable to the format you are using) for the GroupWise Calendar Server. The following formats are supported for the certificate:

- ♦ PEM
- ♦ DER
- ♦ PKCS #12
- ♦ Java keystore
- ♦ PEM encoded with multiple objects

GroupWise Calendar Server Worksheet

Under *Server Information*, specify the SSL/TLS certificate and key to use for the server.

19.3.3 Specifying the Application Admin

An read-only admin user is created at initial configuration of the Calendar Server that the service uses to connect to the GroupWise Admin Service. The user is called an application admin and does not consume a mailbox in your system. You do not need to create a user before configuring the Calendar Server, but should note the username and password you plan on using.

GroupWise Calendar Server Worksheet

Under *Admin Connection*, specify the application admin username and password.

19.3.4 Gathering SOAP Information

The Calendar Server receives SOAP connections from the POA servers. The Calendar Server needs a port to use to receive these SOAP connections.

GroupWise Calendar Server Worksheet

Under *SOAP Event Listener*, specify a port and an IP address if running in a cluster. Otherwise, specify **Listen on all interfaces**.

19.3.5 Gathering the Novell Push Notification Certificate

The Novell Push Notification Server is used to notify your Mac devices if they have updates to CalDAV or CardDAV. It uses push technology through an open IP connection to push notifications from the server to Mac devices even when the device is asleep or the app is no longer running. A certificate is required to be able to use this service. The NPNS certificate can be downloaded from novell.com/npns.

GroupWise Calendar Server Worksheet

Under *NPNS*, specify the name of the NPNS certificate and key.

19.4 Installing the Calendar Server Software

Before you can start installing Calendar Server, you need to have the GroupWise installation software available and extracted in a temporary directory on your server.

- 1 In a terminal windows, become root by entering **su -** and the root password
- 2 Start the GroupWise Installation Wizard at the root of the extracted GroupWise installation software:

```
./install.sh
```
- 3 Type the number for the language in which you want to run the GroupWise Installation Wizard.
- 4 (Optional) Type 1 for **Documentation** to view the Readme, Quick Start, and Installation Guide.
- 5 Type 2 for **Installation**.
- 6 Type a to accept the License Agreement.
- 7 Type 6 for **GroupWise Calendar Server**.
The packages for the GroupWise Calendar Server component are installed on the server.
- 8 When the installation is finished, press any key to return to the Installation Options list.
- 9 Type 2 for **Configure**.
- 10 When prompted, enter the host name or IP address of the GroupWise Primary Domain server.
- 11 Enter the port used by the GroupWise admin service on the Primary Domain server.

You are prompted to accept the admin service certificate if it is issued from an untrusted root CA. Enter Yes to accept the certificate. If the certificate is incorrect, enter No and any additional certificates appear and the option is given to trust the additional certificate. If no more certificates are available, the utility will exit being unable to connect to the GroupWise admin service.

- 12 Browse to the URL displayed in the terminal on the machine where you will finish the configuration and login to the configuration page using the GroupWise admin service credentials.
- 13 Using the information from the [GroupWise Calendar Server Worksheet](#), fill in the fields to configure the Calendar Server.
- 14 In the **Connectivity Test** section, click **Run Scan** to verify the SOAP configuration of your POA servers. Use the information in [Troubleshooting Calendar Server Configuration Errors](#) to resolve any issues found during the scan.

If you want to only see POA's with problems, select **Only show POA's with problems**.
- 15 Click **Save**.

19.5 Configuring Auto-Discovery of GroupWise Calendar Server

Auto-discovery allows your users to setup the accounts using their Groupwise email address and password. If you do not setup auto-discovery, the GroupWise Calendar server DNS name must be specified when creating the account. Auto-discovery does not work for CardDAV. To configure auto-discovery, a DNS record must be added to your DNS server for CalDAV.

Use the format below for the DNS record:

```
_caldavs._tcp 86400 IN SRV 0 1 SSL_port DNS_name
```

Example:

```
_caldavs._tcp 86400 IN SRV 0 1 443 calsvr.acme.com
```

If you have multiple [iDomains](#), one DNS record for each domain is required.

19.6 Testing GroupWise Calendar Server

19.6.1 Calendar Server Service Name

The GroupWise Calendar Server is listed under the following service name:

```
gwcalsvr
```

19.6.2 Testing Calendar Server on a Workstation

To test Calendar Server, follow the steps found in the [GroupWise Mac User Quick Start](#) to configure your workstation.

19.6.3 Troubleshooting Calendar Server Configuration Errors

Use the table below to help you resolve errors in the SOAP connectivity test.

Error	Description	Resolution
SUCCESS	TLS connection was established and SOAP is responding properly.	No action required.

Error	Description	Resolution
TLS_DISABLED	SOAP is responding properly, but the connection was not over TLS.	Enable TLS for SOAP on the POA.
SOAP_DISABLED	SOAP is not enabled for the post office. No connection was attempted.	Enable SOAP on the POA.
UNREACHABLE	Failed to connect to the POA due to a connection failure or socket timeout.	Ensure the POA service is running on the server. Ensure that the POA network is accessible from the Calendar Server.
UNTRUSTED_CA	The certificate chain did not contain a trusted root certificate.	See Resolving an Untrusted CA .
UNTRUSTED_CERT	The endpoint certificate presented during the TLS handshake is invalid. This can be for multiple reason including expiration or invalid usage of the cert.	Issue a new TLS certificate to the POA. Trust the endpoint certificate. If the certificate is trusted, then the trust does not expire when the certificate expires. This also doesn't prevent the man-in-the-middle attach.
HOSTNAME_MISMATCH	A valid TLS certificate is presented by a server that does not match either the CN of the certificate or any of the subject alternative names.	Issue a new certificate that matches the hostname or IP address of the server. Correct the address of the POA so it matches the certificate. Trust the endpoint certificate. If the certificate is trusted, then the trust does not expire when the certificate expires. This also doesn't prevent the man-in-the-middle attach.
UNKNOWN	Most likely caused by network instability, but includes any error not shows above.	Manually check connectivity by running a curl command. See the format below: <code>curl -X options https:// POA_server:SOAP_port/soap</code>

19.6.4 Resolving an Untrusted CA

The following are possible resolutions for fixing an UNTRUSTED_CA error during the connectivity test:

- ◆ Configure the POA with a certificate that is issued from a publicly trusted root certificate authority.
- ◆ Configure the POA with a certificate that is issued by the GroupWise CA.

- ♦ Manually override the trust:
 - ♦ If the TLS handshake contained the CA certificate from the server, you can trust the CA in the pop up that appears when you click **Trust**.
 - ♦ If the TLS handshake did not contain the CA certificate from the server, you can manually upload the CA certificate into the **Trust** dialog.
 - ♦ You can choose to trust the endpoint certificate. While this is a hassle free way of overriding certificate validation issues during the TLS process, it does not prevent man-in-the-middle attacks. Also, the trust does not expire even if the certificate has expired.

19.7 GroupWise Calendar Server Worksheet

Configuration Information	Value for Your GroupWise System	Explanation
GroupWise Domain Information		Section 19.3.1, "Gathering the Primary Domain Information," on page 147
♦ Primary Domain Host name or IP address		
♦ Port (default 9710)		
♦ Admin service Username and password		
Server Settings		Section 19.3.2, "Gathering the Server Information," on page 148
♦ Port (default 443)		
♦ Bind Address OR Listen on all interfaces		
♦ TLS Certificate		
♦ TLS Key		
Admin Connection		Section 19.3.3, "Specifying the Application Admin," on page 148
♦ Application		
♦ Password		
Soap Event Listener		Section 19.3.4, "Gathering SOAP Information," on page 149
♦ Port		
♦ Bind Address OR Listen on all interfaces		
NPNS		Section 19.3.5, "Gathering the Novell Push Notification Certificate," on page 149
♦ Certificate		
♦ Key		

20 Installing the GroupWise Client

The following sections assist you with assigning GroupWise accounts to users and with installing the GroupWise 2014 client.

- ♦ [Section 20.1, “GroupWise Client Overview,” on page 153](#)
- ♦ [Section 20.2, “GroupWise Client Workstation Requirements,” on page 153](#)
- ♦ [Section 20.3, “Installing the GroupWise Client,” on page 154](#)
- ♦ [Section 20.4, “Starting the Groupwise Client,” on page 155](#)
- ♦ [Section 20.5, “What’s Next,” on page 156](#)

For information about client licensing requirements, see [“Auditing Mailbox License Usage in the Post Office”](#) in the *GroupWise 2014 R2 Administration Guide*.

20.1 GroupWise Client Overview

Each user with a GroupWise account has a mailbox in a post office. In a corporate workplace environment, GroupWise users with Windows workstations can run the GroupWise client to access their mailboxes and to send and receive mail.

When the users are not at their workstations, they can access their GroupWise mailboxes from a web browser by using GroupWise WebAccess or on a tablet device by using GroupWise WebAccess Mobile. See [Chapter 16, “Setting Up GroupWise WebAccess,” on page 99](#).

Users can also synchronize GroupWise data to their mobile devices. See [Section 21.1, “Using the GroupWise Mobility Service to Synchronize GroupWise Data to Mobile Devices,” on page 157](#).

20.2 GroupWise Client Workstation Requirements

- ♦ x86-32 processor or x86-64 processor

On a 64-bit processor, GroupWise still runs as a 32-bit application.

- ♦ Any of the following desktop operating systems for the GroupWise client:
 - ♦ Windows 7 on a 1 GHz or higher workstation with at least 1 GB of RAM
 - ♦ Windows 8 or Windows 8.1 on a 1 GHz or higher workstation with at least 1 GB of RAM
 - ♦ Windows 10 on a 1 GHz or higher workstation with at least 1 GB of RAM
- ♦ Microsoft Internet Explorer 9 or later
- ♦ Any of the following word processors for use as the GroupWise editor:
 - ♦ LibreOffice 3.6 or later
 - ♦ Microsoft Word 2007 or later
- ♦ Approximately 200 MB of free disk space on each user’s workstation to install the GroupWise client.

20.3 Installing the GroupWise Client

The GroupWise client software is available on the GroupWise download page. A simple installation of the GroupWise client helps you test your GroupWise system as you are setting it up.

- ♦ [Section 20.3.1, “Installing the GroupWise Client,” on page 154](#)
- ♦ [Section 20.3.2, “Implementing System-Wide GroupWise Client Rollouts,” on page 155](#)

20.3.1 Installing the GroupWise Client

- 1 Install the GroupWise client software on a Windows workstation that meets the system requirements listed in [Section 20.2, “GroupWise Client Workstation Requirements,” on page 153](#).
- 2 Run the GroupWise Installation Wizard (`gw14.x.x_client_win_multi.exe`).
- 3 Select the language in which you want to run the GroupWise Client Installation Wizard, then click **OK**.

All available languages are automatically installed on the workstation, but you select the specific language that you want to use for the Installation Wizard.

The GroupWise Client Installation Wizard appears.

- 4 Click **Next** to display the Setup Type dialog box.
- 5 Select one of the following options:
 - ♦ **Typical:** Installs the most commonly used components in the standard installation directory of `c:\Program Files\Novell\Groupwise` without prompting for further information. Review the Custom settings to see which ones are enabled by default.
 - ♦ **Custom:** Allows you to customize the following GroupWise client functionality:
 - ♦ Languages (select as needed)
 - ♦ Internet Browser Mail Integration (enabled by default)
 - ♦ Program Folder (Novell GroupWise by default)
 - ♦ Add GroupWise to the Desktop (selected by default)
 - ♦ Add GroupWise to Quick Launch (selected by default)
 - ♦ Add Icons to the Start Menu (selected by default)
 - ♦ Add Notify to the Startup folder (disabled by default)

If Notify is not added to the Startup folder, Notify does not automatically run when Windows starts. Users can control how Notify starts in the GroupWise client. For instructions, see “[Starting Notify](#)” in the *GroupWise 2014 R2 Client User Guide*.

See “[Using GroupWise Client Custom Installation Options](#)” in the *GroupWise 2014 R2 Administration Guide* for more information about installing the GroupWise client.

- 6 Click **Next**.
- 7 (Conditional) If you selected **Typical** or **Upgrade**:

- 7a Click **Install** to install the client files.

When the client Installation Wizard has completed, a shortcut to run GroupWise appears on your desktop and in the Quick Launch area.

- 7b Click **Finish** to exit the GroupWise Installation program.

- 7c Continue with [Section 20.4, “Starting the Groupwise Client,” on page 155](#).

8 (Conditional) If you selected **Custom**:

8a Ensure that each component you want to install is selected.

Languages: Select which languages to install.

Internet Browser Mail Integration: Sets GroupWise to be the default email program on the workstation, so that whenever the user clicks an email link on a web page or chooses the Mail command in the browser, GroupWise starts.

8b Click **Next**.

8c Select the Program folder where you want to add the GroupWise icons.

The default is **Novell GroupWise**.

8d Select whether you want the GroupWise icon added to your Desktop and Quick Launch.

8e Select whether you want GroupWise icons added to the Start menu.

8f Select whether you want Notify added to the Startup folder.

If Notify is not added to the Startup folder, Notify does not automatically run when Windows starts. Users can control how Notify starts in the GroupWise client. For instructions, see “Starting Notify” in the *GroupWise 2014 R2 Client User Guide*.

8g Click **Next**.

8h Click **Install** to install the client software files.

When the Installation Wizard has completed, a shortcut to run GroupWise appears on your desktop.

8i Click **Finish** to exit the GroupWise Client Installation Wizard.

8j Continue with [Section 20.4, “Starting the Groupwise Client,”](#) on page 155.

20.3.2 Implementing System-Wide GroupWise Client Rollouts

For a system-wide rollout of the GroupWise client software, see “[Distributing the GroupWise Client](#)” in the *GroupWise 2014 R2 Administration Guide*.

20.4 Starting the Groupwise Client

At startup, the GroupWise client needs to know the location (IP address/hostname and port number) for the user’s post office.

The GroupWise client can get the information for the initial login in two ways:

- ♦ The user can provide the post office location when prompted.
- ♦ The GroupWise client can access a GroupWise name server to get the user’s post office location.

A GroupWise name server is a DNS hostname entry that defines the IP address of a POA. During startup, the GroupWise client automatically looks for the GroupWise name server in DNS. The POA identified as the GroupWise name server then redirects the client login to the POA for the user’s post office. For information about creating a GroupWise name server, see “[Post Office Agent](#)” in the *GroupWise 2014 R2 Administration Guide*.

After the first successful login, the GroupWise client stores the post office location as the default for future logins. The user is subsequently presented with a simpler Startup dialog box.

To start the GroupWise client for the first time:

- 1 Double-click the GroupWise icon on the Windows desktop.
- 2 Enter the password and post office address information, then click **OK**.

For more information about logging in, see “[Getting Started](#)” in the *GroupWise 2014 R2 Client User Guide*.

For information about providing users’ GroupWise passwords automatically, see “[Security Options: Password](#)” in the *GroupWise 2014 R2 Administration Guide*.

20.5 What’s Next

For information about using the features in the GroupWise client, click **Help > Help Topics**, or **Help > User Guide**. The User Guide is also available on the [GroupWise 2014 R2 Documentation website](http://www.novell.com/documentation/groupwise2014r2/) (<http://www.novell.com/documentation/groupwise2014r2/>) in HTML and PDF formats.

21 Using Other Novell Products with GroupWise

- ♦ Section 21.1, “Using the GroupWise Mobility Service to Synchronize GroupWise Data to Mobile Devices,” on page 157
- ♦ Section 21.2, “Using Novell Messenger to Provide Secure Instant Messaging for GroupWise Users,” on page 157
- ♦ Section 21.3, “Using Novell Vibe to Provide Team Workspaces for GroupWise Users,” on page 158

21.1 Using the GroupWise Mobility Service to Synchronize GroupWise Data to Mobile Devices

The GroupWise Mobility Service provides data synchronization between GroupWise mailboxes and mobile devices for synchronizing email, appointments, contacts, tasks, notes, and phone messages. The GroupWise Mobility Service is fast, reliable and scalable, and supports the latest device operating systems. For more information, see the [GroupWise Mobility 2.0 Documentation website](#).

To support BlackBerry devices with an operating system earlier than BlackBerry 10.x, use [BlackBerry Enterprise Server for GroupWise](#).

21.2 Using Novell Messenger to Provide Secure Instant Messaging for GroupWise Users

Novell Messenger is a corporate-based, secure instant messaging solution that supports instant messaging, presence, and archiving of conversations. The Messenger client integrates with the GroupWise Groupwise client to provide access to instant messaging features from within the GroupWise client.

Novell Messenger is installed separately from GroupWise and does not rely on your GroupWise system. All Messenger information is stored in eDirectory, not in GroupWise databases. For more information, see:

- ♦ [Novell Messenger Documentation website \(https://www.novell.com/documentation/novell_messenger22/\)](https://www.novell.com/documentation/novell_messenger22/)
- ♦ [GroupWise and Messenger Quick Start \(https://www.novell.com/documentation/groupwise2014/gw2014_qs_messenger/data/gw2014_qs_messenger.html\)](https://www.novell.com/documentation/groupwise2014/gw2014_qs_messenger/data/gw2014_qs_messenger.html)

21.3 Using Novell Vibe to Provide Team Workspaces for GroupWise Users

Novell Vibe enhances GroupWise by providing easy document management and document sharing, team calendars and task lists, workflows, discussion threads, wikis, blogs, RSS feeds, and more.

For more information, see:

- ♦ [Novell Vibe 3 Documentation website \(http://www.novell.com/documentation/vibe34/\)](http://www.novell.com/documentation/vibe34/)
- ♦ “Novell Vibe” in the *GroupWise 2012 Interoperability Guide*

The integration procedure is the same in GroupWise 2014 R2 as it was in GroupWise 2012.

- ♦ [GroupWise 2014 R2 and Vibe Quick Start](#)

V GroupWise System Upgrade

- ♦ [Chapter 22, “What’s New in GroupWise 2014 R2,” on page 161](#)
- ♦ [Chapter 23, “Understanding the Upgrade Process,” on page 163](#)
- ♦ [Chapter 24, “Preparing Your Existing GroupWise System for the Upgrade,” on page 169](#)
- ♦ [Chapter 25, “Installing the GroupWise 2014 Software,” on page 171](#)
- ♦ [Chapter 26, “Upgrading the Primary Domain Server,” on page 175](#)
- ♦ [Chapter 27, “Upgrading a Secondary Domain Server,” on page 179](#)
- ♦ [Chapter 28, “Upgrading a Post Office Server,” on page 183](#)
- ♦ [Chapter 29, “Upgrading GroupWise Agents and Applications,” on page 185](#)
- ♦ [Chapter 30, “Upgrading Users’ GroupWise Client Software,” on page 191](#)
- ♦ [Chapter 31, “Transitioning from ConsoleOne,” on page 193](#)
- ♦ [Chapter 32, “Upgrading the GroupWise/Exchange Coexistence Solution,” on page 195](#)

22 What's New in GroupWise 2014 R2

To see a list of what's new in GroupWise 2014 R2, please see the [Novell GroupWise 2014 R2 Readme](#).

23 Understanding the Upgrade Process

You can upgrade a GroupWise 8, GroupWise 2012, or GroupWise 2014 system to GroupWise 2014 R2.

IMPORTANT: If you need to upgrade from an older GroupWise version, you must upgrade at least to GroupWise 8, and preferably to GroupWise 2012, in order to ensure that your GroupWise data is compatible with the upgrade process that is provided in GroupWise 2014.


If your GroupWise system is still on NetWare, see “[Migrating Away from NetWare](#)” in the [GroupWise 2012 Installation Guide](#).

IMPORTANT: After you understand the upgrade process in general, you are ready to upgrade specific components of your existing GroupWise system. Do not start upgrading your GroupWise system until you have a solid understanding of the entire process.

For a large GroupWise system, you might need to maintain a mixed-version environment as you roll out GroupWise 2014 R2. For a table showing which GroupWise 8 and GroupWise 2012 components can be used with GroupWise 2014 R2, see [Appendix A, “GroupWise Version Compatibility,”](#) on [page 199](#).

23.1 Domain and Post Office Upgrades

Functionality enhancements in GroupWise 2014 require the GroupWise domain and post office databases to be upgraded. The following diagram illustrates the required upgrade sequence for installing the GroupWise 2014 software.



1. Upgrade the primary domain server first, so that correct replication of GroupWise 2014 information can take place as you upgrade secondary domains and post offices.

If there are secondary domains or post offices on the primary domain server, you can upgrade them at the same time as the primary domain, but this is not required.

2. Upgrade secondary domain servers.

If there are multiple secondary domains or post offices on a secondary domain server, you can upgrade them at the same time, but this is not required.

3. Upgrade post office servers after upgrading the secondary domains that they belong to.

When you install the GroupWise 2014 software on a server where an earlier version of GroupWise is installed, the Installation Wizard stops the existing agents, installs the GroupWise 2014 software, and then starts the GroupWise 2014 agents.

IMPORTANT: Upgrading the domain and post office servers does not upgrade the domain and post office databases. Database upgrades are performed in a separate step.

When you upgrade multiple domains and post office on the same server at the same time, the Installation console orchestrates the process of upgrading the databases in the proper order.

23.2 Agent Upgrades

POA POAs are automatically upgraded along with the post offices that they belong to.

The upgrade process looks for POA startup files. If a POA startup file is found, the setting of the --home switch is verified. If the home folder is valid, the existing POA startup file is used with the upgraded POA. If the POA startup file cannot be found, or if the home folder is not valid, a new POA startup file is created in the post office folder. The GroupWise 2014 location for POA startup files is the post office folder.

If you have been running multiple POAs on multiple servers, the upgrade process cannot upgrade POAs on remote servers. In GroupWise 2014, the need for running multiple POAs for a post office does not occur. You can configure the POA that runs on the server where the post office is located to handle all the needs of the post office.

If your existing POAs have been using the internal Document Converter Agent (DCA) rather than the independent Document Viewer Agent (DVA), you must run at least one DVA in your GroupWise 2014 system.

MTA MTAs are automatically upgraded along with the domains that they belong to.

The upgrade process looks for MTA startup files. If an MTA startup file is found, the setting of the --home switch is verified. If the home folder is valid, the existing MTA startup file is used with the upgraded MTA. If the MTA startup file cannot be found, or if the home folder is not valid, a new MTA startup file is created in the domain folder. The GroupWise 2014 location for MTA startup files is the domain folder.

GWIA GWIAs are automatically upgraded along with the domains that they belong to.

IMPORTANT: If you are upgrading to GroupWise 2014 from GroupWise 8, you need to understand the important changes to where GWIA configuration information is stored. See “[Using Internet Agent Startup Switches](#)” in the *GroupWise 8 Administration Guide* before you upgrade to GroupWise 2014.

DVA Existing DVAs are automatically upgraded along with the POAs that they were installed with. However, their startup files (`gwdva.dva`) are not modified. On Linux, the `gwha.conf` file already has an entry for each DVA. On Windows, the DVA service is already set up.

If you were not running a DVA in your existing GroupWise system, you must install and configure at least one DVA in your GroupWise 2014 system.

23.3 Monitor Upgrades

GroupWise Monitor is not dependent on any other GroupWise agents, so you can upgrade the Monitor Agent and the Monitor Application to GroupWise 2014 at any time.

IMPORTANT: If you are upgrading from GroupWise 8 directly to GroupWise 2014, you need to understand that Monitor no longer relies on eDirectory objects for its configuration information. All configuration information is located in the `gwmonitor.cfg` file instead. See “[Understanding Monitor Updates](#)” and “[Updating GroupWise Monitor](#)” in the *GroupWise 2012 Installation Guide* before you upgrade Monitor from GroupWise 8 directly to GroupWise 2014.

On Linux, the GroupWise High Availability Service (gwha), that works in conjunction with the Monitor Agent to automatically restart the GroupWise agents, has been made more secure.

23.4 WebAccess Upgrades

If you are upgrading from GroupWise 2012 to GroupWise 2014, there are no WebAccess upgrade issues. You can upgrade your WebAccess software whenever it is convenient as you upgrade your GroupWise system. However, in order to use the WebAccess Application console, you must change the way it is configured. For instructions, see “[Using the WebAccess Application Console](#)” in the *GroupWise 2014 R2 Administration Guide*.

IMPORTANT: If you are upgrading from GroupWise 8 directly to GroupWise 2014, you need to understand that the WebAccess Agent is no longer part of GroupWise. See “[Understanding WebAccess Updates](#)” and “[Updating GroupWise WebAccess](#)” in the *GroupWise 2012 Installation Guide* before you upgrade WebAccess from GroupWise 8 directly to GroupWise 2014.

23.5 Calendar Publishing Host Upgrades

There are no Calendar Publishing Host upgrade issues. You can upgrade the Calendar Publishing Host to GroupWise 2014 at any time after the POA that it communicates with has been upgraded. However, in order to use the CalPub Host Admin console, you must change the way it is configured. For instructions, see [Section 17.5.4, “Setting Up Calendar Publishing Administration,” on page 125](#).

23.6 GroupWise Client Upgrades

After a post office is upgraded to version 2014, users can run the GroupWise 2014 client on workstations that meet the requirements listed in [Chapter 5, “GroupWise User Requirements,” on page 31](#). If necessary, they can also continue to run their older GroupWise clients. However, older clients do not have GroupWise 2014 functionality just because they are accessing mailboxes in a GroupWise 2014 post office.

IMPORTANT: A user who needs to proxy into another user’s mailbox should not upgrade to the GroupWise 2014 client until the mailbox owner’s post office has been upgraded to version 2014. The GroupWise 2014 client cannot proxy into a mailbox that has not been upgraded to GroupWise 2014.

23.7 Obsolete eDirectory Schema Extensions

GroupWise 2014 no longer extends the eDirectory schema to accommodate GroupWise-specific objects. After upgrading domains and post offices to GroupWise 2014, the associated GroupWise objects in eDirectory are *not* used by GroupWise 2014.

IMPORTANT: It is not necessary to remove obsolete GroupWise objects from eDirectory. If you want to remove them, use iManager (recommended) or ConsoleOne (not recommended). If you use ConsoleOne, remove (or move) the GroupWise snapins first. Otherwise, you run the risk of inadvertently deleting a GroupWise account. Always back up your domain database before taking any action.

23.8 Obsolete Software Distribution Directories

GroupWise 2014 no longer uses software distribution directories. After you have upgraded post offices, you can delete the associated software distribution directories in the Admin console.

- 1 In the [GroupWise Admin console](#), click **System > Legacy**.
- 2 Click **Software Areas**.
- 3 Select the obsolete software distribution directory, then click **Delete**.

GroupWise 2014 uses the Client Auto-Update feature instead of software distribution directories. For usage instructions, see “[Using Client Auto-Update to Distribute the GroupWise Client Software](#)” in the *GroupWise 2014 R2 Administration Guide*.

23.9 Obsolete GroupWise Gateways

There are no known issues with using GroupWise gateways with GroupWise 2014. However, GroupWise gateways are legacy products that are not supported with the current GroupWise version. You can delete obsolete gateways in the GroupWise Admin console.

- 1 In the [GroupWise Admin console](#), click **System > Legacy**.
- 2 On the **Gateways** tab, select the obsolete gateway, then click **Delete**.

23.10 NetWare Compatibility

As of GroupWise 2012, GroupWise does not include GroupWise agents that run on NetWare, because NetWare has entered the Extended Support phase of the Novell Support Life cycle. For more information, see TID 7003092, “NetWare Support,” in the [Novell Support Knowledgebase \(http://www.novell.com/support/\)](http://www.novell.com/support/).

If you currently have NetWare servers in your GroupWise system, you must decide how to handle them as you move forward with your GroupWise 2014 upgrade. You have several alternatives:

- ♦ Migrate NetWare servers to Open Enterprise Server (OES).
- ♦ Move domains and post offices from NetWare servers to [supported Linux servers](#).
- ♦ Move domains and post offices from NetWare servers to [supported Windows servers](#).

You might decide to use one or more of these alternatives as you upgrade your GroupWise system to GroupWise 2014. Detailed instructions for each alternative are provided in “[Migrating Away from NetWare](#)” in the [GroupWise 2012 Installation Guide](#), because GroupWise 2012 is the first version where NetWare is not supported.

24 Preparing Your Existing GroupWise System for the Upgrade

To prepare your GroupWise system to be upgraded to version 2014, complete the following tasks:

- ☐ Validate your domain and post office databases to ensure that there are no physical inconsistencies with the database. If problems exist, you should recover or rebuild the database. For information about validating, recovering, or rebuilding a database, see the documentation for your current GroupWise version at the [Novell Documentation website \(http://www.novell.com/documentation/#d\)](http://www.novell.com/documentation/#d).
- ☐ Back up each domain or post office immediately before upgrading it. For information about backing up your GroupWise databases, see the documentation for your current GroupWise version at the [Novell Documentation website \(http://www.novell.com/documentation/#d\)](http://www.novell.com/documentation/#d).
- ☐ Collect the information about your existing GroupWise system that the GroupWise Installation Wizard prompts you for as you upgrade to GroupWise 2014. You might find it helpful to review [Chapter 8, “Planning Your GroupWise System,” on page 41](#) and to record the information on the worksheets provided for an initial installation:
 - ♦ “[Simple GroupWise System Worksheet](#)” on [page 52](#) (for a small GroupWise system that is all on one server)
 - ♦ “[Primary Domain Worksheet](#)” on [page 54](#) (for a primary domain on its own server)
 - ♦ “[Secondary Domain Worksheet](#)” on [page 54](#) (for each secondary domain)
 - ♦ “[Post Office Worksheet](#)” on [page 55](#) (for each post office)
 - ♦ “[GroupWise WebAccess Installation Worksheet](#)” on [page 110](#) (for each WebAccess Application)
 - ♦ “[GroupWise Calendar Publishing Host Worksheets](#)” on [page 128](#) (for each Calendar Publishing Host Application)
 - ♦ “[GroupWise Monitor Installation Worksheets](#)” on [page 144](#) (for each Monitor Agent/ Application)

- ❑ Prepare the existing agents for upgrade. The Installation console uses the same agent configuration for GroupWise 2014 that is in use for your existing GroupWise system. Your current agent configuration might not be the best option for GroupWise 2014. The [GroupWise 2012 Installation Guide](#) provides information for reconfiguring your existing agents in preparation for the upgrade.

Linux: The Installation console can locate agents that are listed in the `gwha.conf` file used by the GroupWise High Availability Service (gwha). For background information, see “[Enabling the GroupWise High Availability Service for the Linux GroupWise Agents](#)” in the [GroupWise 2012 Installation Guide](#).

Also, the Admin console cannot manage agents that run with the user interface provided by the `--show` switch. For background information, see “[Starting the Linux Agents with a User Interface](#)” in the [GroupWise 2012 Installation Guide](#).

Windows: The Installation console can locate agents that have been running as Windows services. For background information, see “[Starting the Windows Agents Manually or Automatically as Services](#)” in the [GroupWise 2012 Installation Guide](#).

Also, the Admin console cannot manage agents that run as applications with a user interface. For background information, see “[Starting the Windows Agents Manually As Applications](#)” in the [GroupWise 2012 Installation Guide](#).

In preparation for GroupWise 2014, you can configure your existing agents to run without a user interface, so that the Installation console can automatically locate them, or you can specify the locations of domains and post offices during the upgrade process.

- ❑ Ensure that all GroupWise servers meet the system requirements listed in [Chapter 4, “GroupWise Administration Requirements,”](#) on page 27.
- ❑ When you upgrade the primary domain to GroupWise 2014, you establish the user name and password for the GroupWise Super Admin. For background information about this administrative user, see “[Primary Domain: Super Admin Creation](#)” on page 46. Decide on the Super Admin user name and password before you start the upgrade process.
- ❑ When you upgrade a domain or post office on a Linux server, ensure that the Linux operating system media is available, either physically or in a repository, in case the Installation Wizard needs to install supporting packages on the Linux server.
- ❑ Ensure that all GroupWise client user workstations meet the system requirements listed in [Chapter 5, “GroupWise User Requirements,”](#) on page 31.

25 Installing the GroupWise 2014 Software

Before installing the GroupWise 2014 software, review the background information and complete the tasks in the following sections:

- ❑ [Chapter 23, “Understanding the Upgrade Process,” on page 163](#)
- ❑ [Chapter 24, “Preparing Your Existing GroupWise System for the Upgrade,” on page 169](#)

Then follow the installation instructions for the platform where the domain or post office to upgrade is located.

25.1 Linux: Installing the GroupWise 2014 Software

- 1 Stop the existing GroupWise agents that are running on the server to upgrade.
- 2 Ensure that the Linux operating system media is available, either physically or in a repository, in case the Installation Wizard needs to install supporting packages on the Linux server.
- 3 In a terminal window, become `root` by entering `su -` and the `root` password.
- 4 Browse to the location of the extracted software, and run the following command to start the install:

```
./install.sh
```

- 5 Type the number for the language in which you want to run the GroupWise Installation Wizard, then press Enter to select **OK**.
- 6 Type 2 for **Installation**, then press Enter.
- 7 Type **a** to accept the License Agreement and display the Software list.
- 8 Type 1 for **GroupWise Server**, then press Enter to display the Actions list.
- 9 Type 1 for **Install**, then press Enter to install the GroupWise Server component.

The packages for the GroupWise Server component (Admin Service and agents) are installed on the server. If any supporting packages are not available on the server, the Installation Wizard automatically installs them from the operating system media.

- 10 When the installation is finished, press any key to return to the Installation Options list.

All of the GroupWise agents are installed on every GroupWise server. The MTA and, optionally, the GWIA are configured to run on a domain server. The POA and the DVA are configured to run on a post office server.

The Installation Wizard starts any agents that typically run on the server.

IMPORTANT: Running the GroupWise 2014 agents does not upgrade the GroupWise databases on the server to GroupWise 2014. Updating the databases is performed in a subsequent step.

- 11 Type 2 for **Configure**, then press Enter to start the GroupWise Admin Service and display instructions for accessing the Installation console to upgrade the GroupWise server to GroupWise 2014.

- 12 Right-click the URL under **To install or configure a new GroupWise server**, then click **Open Link** to open your web browser.
If your web browser does not offer this functionality, open your web browser, then copy the URL into it.
- 13 Accept the self-signed certificate that the Installation Wizard has automatically provided for accessing the Installation console.
The browser session will then authorize for the next hour to perform installation console tasks. If the browser does not automatically authorize the session, you must manually authorize it by running in a terminal the **gwadmin-ipc authorize** command specified in your web browser.
- 14 Continue with the instructions for the upgrade task that you are performing:
 - ♦ [Chapter 26, “Upgrading the Primary Domain Server,” on page 175](#)
 - ♦ [Chapter 27, “Upgrading a Secondary Domain Server,” on page 179](#)
 - ♦ [Chapter 28, “Upgrading a Post Office Server,” on page 183](#)

25.2 Windows: Installing the GroupWise 2014 Software

- 1 Stop the existing GroupWise agents that are running on the server to upgrade.
- 2 Run `setup.exe` at the root of the extracted GroupWise software to start the GroupWise Installation Wizard.
- 3 Click **GroupWise Server** to install the GroupWise Server component.
- 4 Select the language in which you want to perform the installation, then click **OK** to start the GroupWise Server Setup Wizard.
- 5 Click **Next** to continue.
- 6 Accept the **License Agreement**, then click **Next** to display the Custom Setup page.

The following components are available for installation:

- ♦ **GroupWise Server:** (Required) Consists of the Admin Service, the POA, the MTA, the GWIA, and the DVA.
All of the GroupWise agents are installed on every GroupWise server. The MTA and, optionally, the GWIA are configured to run on a domain server. The POA and the DVA are configured to run on a post office server.
- ♦ **Client Auto-Update Repository:** (Optional) Helps you distribute the GroupWise client software to users' Windows workstations.
For usage instructions, see [“Using Client Auto-Update to Distribute the GroupWise Client Software”](#) in the *GroupWise 2014 R2 Administration Guide*.

- 7 Click **Next** to continue, then click **Install** to install the GroupWise software.
- 8 When the GroupWise software has been installed, click **Finish** to return to the main page of the Installation Wizard, then close the Installation Wizard.
- 9 Reboot the Windows server to complete the installation and start the GroupWise Installation console.
The Installation Wizard has created two new icons on your Windows desktop.
- 10 On your Windows desktop, double-click **GroupWise Install** to open your web browser and access the Installation console.
This starts the GroupWise Admin Service and launches the GroupWise Installation console in your web browser.

After installation, use **GroupWise Admin Console** to access the Admin console for ongoing GroupWise system administration.

- 11 Accept the self-signed certificate that the Installation Wizard has automatically provided for accessing the Installation console.

The browser session will then authorize for the next hour to perform installation console tasks. If the browser does not automatically authorize the session, you must manually authorize it by running in a terminal the **gwsadmin-ipc authorize** command specified in your web browser.

- 12 Continue with the instructions for the upgrade task that you are performing:
 - ♦ [Chapter 26, “Upgrading the Primary Domain Server,” on page 175](#)
 - ♦ [Chapter 27, “Upgrading a Secondary Domain Server,” on page 179](#)
 - ♦ [Chapter 28, “Upgrading a Post Office Server,” on page 183](#)

26 Upgrading the Primary Domain Server

Before you upgrade the primary domain server, you should have reviewed the following sections and completed the accompanying tasks:

- ❑ [Chapter 3, “GroupWise System Architecture,” on page 21](#)
- ❑ [Chapter 4, “GroupWise Administration Requirements,” on page 27](#)
- ❑ [Chapter 23, “Understanding the Upgrade Process,” on page 163](#)
- ❑ [Chapter 24, “Preparing Your Existing GroupWise System for the Upgrade,” on page 169](#)
- ❑ [Chapter 25, “Installing the GroupWise 2014 Software,” on page 171](#)

After you install the GroupWise 2014 software on the primary domain server, the Installation Wizard displays the Installation console in your web browser.

IMPORTANT: As a security feature, the Installation console times out after one hour. For instructions to renew the session, see [Section 11.4, “Handling an Installation Timeout,” on page 68](#).

- 1 In the Installation console, click **Upgrade an Existing Domain or Post Office to GroupWise 2014**.
What displays next depends on whether the Installation console can detect the existing domains and post offices on the server. The conditions for automatic detection are described in [Chapter 24, “Preparing Your Existing GroupWise System for the Upgrade,” on page 169](#).
- 2 (Conditional) If the Installation console can locate existing domains and post offices:
 - 2a (Conditional) If there are any domains and post offices on the primary domain server that you do not want to upgrade along with the primary domain, select them, then click **Remove** to remove them from the list.
 - 2b (Conditional) If you want to change the IP address or Admin port for any domain or post office, click its name to display the Network Information dialog box.
Specify the desired IP address or Admin port, then click **OK**.
 - 2c Skip to [Step 4](#) to perform the upgrade.
- 3 (Conditional) If the Installation console cannot locate existing domains and post offices:
 - 3a Click **Add**.
 - 3b Browse to and select the primary domain folder.
 - 3c Click **OK**, then review the MTA IP address and domain Admin port that the Installation console has provided.
 - 3d (Optional) Change the information as needed.
 - 3e Click **OK** to return to the Installation console.
 - 3f Repeat [Step 3a](#) through [Step 3e](#) for each additional domain and post office that you want to upgrade on the primary domain server.
 - 3g Continue with [Step 4](#) to perform the upgrade.
- 4 In the list of domains and post offices to upgrade, click **Next** to display the Credentials page.
- 5 Specify the user name for the GroupWise Super Admin, type the password twice for confirmation, then click **Next** to display the Summary page.

- 6 Review the information to ensure that it is correct, then click **Finish** to perform the upgrade.
- 7 Click **Go to the GroupWise Administration console now**.
- 8 Accept the self-signed certificate that the Installation console has automatically provided for accessing the Admin console.

The Login fields are displayed.

- 9 Specify the GroupWise Super Admin user name and password that you established in [Step 5](#), then click **Login** to display the Overview page in the GroupWise Admin console.

To finish the upgrade process, you must restart the MTA for the primary domain. You must also restart the agents for any other upgraded domains and post offices on the primary domain server.

If the primary domain has a GWIA, it was also upgraded along with the primary domain and its MTA. However, you do not need to restart the upgraded GWIA.

IMPORTANT: If you are upgrading from GroupWise 8, see [Section 23.2, “Agent Upgrades,” on page 164](#) for release-specific information.

- 10 To restart the MTA in the upgraded primary domain:
 - 10a In the Domain box on the Overview page, click **MTA** or click **Running > MTA** to display the MTA properties page.
 - 10b Click **Stop Agent**, then click **Start Agent** to restart the upgraded MTA.
 - 10c (Optional) Click **Launch MTA Console** to open the MTA console in a new browser window.

TIP: You can conveniently open the MTA console on the Overview page by clicking **Running**, and then clicking the IP address of the MTA.

If the primary domain has a GWIA, it was also upgraded along with the primary domain and its MTA. However, you do not need to restart the upgraded GWIA.

IMPORTANT: If you are upgrading from GroupWise 8, see [Section 23.2, “Agent Upgrades,” on page 164](#) for release-specific information.

- 10d Click **Overview** to return to the Overview page.
- 11 (Conditional) If the primary domain server has additional upgraded domains, repeat [Step 10](#) for the MTA in each upgraded domain.
- 12 (Conditional) If the primary domain server has upgraded post offices:
 - 12a In the Domain box on the Overview page, click **Running** next to the Post Office icon , then click **POA** to display the POA properties page.
 - 12b Click **Stop Agent**, then click **Start Agent** to restart the upgraded POA.
 - 12c (Optional) Click **Launch POA Console** to open the POA console in a new browser window.

TIP: You can conveniently open the POA console on the Overview page by clicking **Running**, and then clicking the IP address of the POA.

- 12d Click **Overview** to return to the Overview page.

If the post office has a DVA, it was also upgraded along with the post office and its POA. However, you do not need to restart the upgraded DVA.
- 13 (Conditional) If the primary domain server has additional post offices, repeat [Step 12](#) for the POA in each upgraded post office.

14 Continue with the next upgrade task for your GroupWise system:

- ♦ [Chapter 27, “Upgrading a Secondary Domain Server,” on page 179](#)
- ♦ [Chapter 28, “Upgrading a Post Office Server,” on page 183](#)
- ♦ [Section 29.2, “Upgrading GroupWise WebAccess,” on page 185](#)
- ♦ [Section 29.3, “Upgrading the Calendar Publishing Host,” on page 187](#)
- ♦ [Section 29.4, “Upgrading GroupWise Monitor,” on page 188](#)

27 Upgrading a Secondary Domain Server

After you have upgraded the primary domain server in your GroupWise system, you can upgrade secondary domains in your GroupWise system in any order that is convenient for you.

Before you upgrade a secondary domain server, review the following sections and complete the accompanying tasks if you have not done so recently:

- ❑ [Chapter 3, “GroupWise System Architecture,” on page 21](#)
- ❑ [Chapter 4, “GroupWise Administration Requirements,” on page 27](#)
- ❑ [Chapter 23, “Understanding the Upgrade Process,” on page 163](#)
- ❑ [Chapter 24, “Preparing Your Existing GroupWise System for the Upgrade,” on page 169](#)

To upgrade a secondary domain server:

- 1 Stop the existing GroupWise agents that are running on the server to upgrade.
- 2 Install the GroupWise 2014 software on the secondary domain server.

See [Chapter 25, “Installing the GroupWise 2014 Software,” on page 171](#) for instructions.

When the software installation is complete, the Installation Wizard displays the Installation console in your web browser.

IMPORTANT: As a security feature, the Installation console times out after one hour. For instructions to renew the session, see [Section 11.4, “Handling an Installation Timeout,” on page 68](#).

- 3 In the Installation console, click **Upgrade an Existing Domain or Post Office to GroupWise 2014**.
What displays next depends on whether the Installation console can detect the existing domains and post offices on the server. The conditions for automatic detection are described in [Chapter 24, “Preparing Your Existing GroupWise System for the Upgrade,” on page 169](#).
- 4 (Conditional) If the Installation console can locate existing domains and post offices:
 - 4a (Conditional) If there are any domains and post offices on the secondary domain server that you do not want to upgrade, select them, then click **Remove**.
 - 4b (Conditional) If you want to change the IP address or Admin port for any domain or post office, click its name to display the Network Information dialog box.
Specify the desired IP address or Admin port, then click **OK**.
 - 4c Skip to [Step 6](#) to perform the upgrade.
- 5 (Conditional) If the Installation console cannot locate existing domains and post offices:
 - 5a Click **Add**.
 - 5b Browse to and select the secondary domain folder.
 - 5c Click **OK**, then review the MTA IP address and domain Admin port that the Installation console has provided.
 - 5d (Optional) Change the information as needed.
 - 5e Click **OK** to return to the Installation console.

- 5f** If you want to upgrade additional domains and post offices on the domain server, repeat [Step 5a](#) through [Step 5e](#).
- 5g** Continue with [Step 6](#) to perform the upgrade.
- 6** In the list of secondary domains, and optionally, post offices to upgrade, click **Next** to display the Credentials page.
- 7** Specify the IP address of the primary domain server and the password for the GroupWise Super Admin, then click **Next** to display the Summary page.
- 8** Review the information to ensure that it is correct, then click **Finish** to perform the upgrade.
- 9** (Optional) Click the Existing Configuration slide-out to list all upgraded domains and post offices.
- 10** Click **Go to the GroupWise Administration console now**.
- 11** Accept the self-signed certificate that the Installation console has automatically provided for accessing the Admin console.
- The Login fields are displayed.
- 12** Specify the GroupWise Super Admin user name and password that you established when you upgraded the primary domain, then click **Login** to display the Overview page in the Admin console.
- To finish the upgrade process, you must restart the agents for all upgraded secondary domains and post offices on the secondary domain server.
- If any secondary domains have GWIAs, they were also upgraded along with the secondary domains. However, you do not need to restart the upgraded GWIAs.

IMPORTANT: If you are upgrading from GroupWise 8, see [Section 23.2, "Agent Upgrades,"](#) on [page 164](#) for release-specific information.

- 13** To restart the MTA in the upgraded secondary domain:
- 13a** In the Domain box on the Overview page, click **MTA** or click **Running > MTA** to display the MTA properties page.
- 13b** Click **Stop Agent**, then click **Start Agent** to restart the upgraded MTA.
- 13c** (Optional) Click **Launch MTA Console** to open the MTA console in a new browser window.

TIP: You can conveniently open the MTA console on the Overview page by clicking **Running**, and then clicking the IP address of the MTA.

If any secondary domains have GWIAs, they were also upgraded along with the secondary domains. However, you do not need to restart the upgraded GWIAs.

IMPORTANT: If you are upgrading from GroupWise 8, see [Section 23.2, "Agent Upgrades,"](#) on [page 164](#) for release-specific information.

- 14** (Conditional) If the secondary domain server has additional upgraded domains, repeat [Step 13](#) for the MTA in each upgraded domain.
- 15** (Conditional) If the secondary domain server has upgraded post offices:
- 15a** In the Domain box on the Overview page, click **Running** next to the Post Office icon, then click **POA** to display the POA properties page.
- 15b** Click **Stop Agent**, then click **Start Agent** to restart the upgraded POA.
- 15c** (Optional) Click **Launch POA Console** to open the POA console in a new browser window.

NOTE: You can conveniently open the POA console on the Overview page by clicking **Running**, and then clicking the IP address of the POA.

If the post office has a DVA, it was also upgraded along with the post office and its POA. However, you do not need to restart the upgraded DVA.

- 16 (Conditional) If the secondary domain server has additional post offices, repeat [Step 15](#) for the POA in each upgraded post office.
- 17 Continue with the next upgrade task for your GroupWise system:
 - ♦ [Chapter 28, “Upgrading a Post Office Server,” on page 183](#)
 - ♦ [Section 29.2, “Upgrading GroupWise WebAccess,” on page 185](#)
 - ♦ [Section 29.3, “Upgrading the Calendar Publishing Host,” on page 187](#)
 - ♦ [Section 29.4, “Upgrading GroupWise Monitor,” on page 188](#)

28 Upgrading a Post Office Server

You can upgrade a post office after you have upgraded the domain that owns it.

When the post office is located on the same server with the owning domain, you can upgrade it along with its domain. See these associated tasks:

- ❑ [Chapter 26, “Upgrading the Primary Domain Server,” on page 175](#)
- ❑ [Chapter 27, “Upgrading a Secondary Domain Server,” on page 179](#)

When the post office is on a separate post office server, review the following sections and complete the accompanying tasks if you have not done so recently:

- ❑ [Chapter 3, “GroupWise System Architecture,” on page 21](#)
- ❑ [Chapter 4, “GroupWise Administration Requirements,” on page 27](#)
- ❑ [Chapter 23, “Understanding the Upgrade Process,” on page 163](#)
- ❑ [Chapter 24, “Preparing Your Existing GroupWise System for the Upgrade,” on page 169](#)

To upgrade a post office server:

- 1 Stop the existing GroupWise agents that are running on the server to upgrade.
- 2 Install the GroupWise 2014 software on the post office server.
See [Chapter 25, “Installing the GroupWise 2014 Software,” on page 171](#) for instructions.
When the software installation is complete, the Installation Wizard displays the Installation console in your web browser.
- 3 In the Installation console, click **Upgrade an Existing Domain or Post Office to GroupWise 2014**.
What displays next depends on whether the Installation console can detect the existing domains and post offices on the server. The conditions for automatic detection are described in [Chapter 24, “Preparing Your Existing GroupWise System for the Upgrade,” on page 169](#).
- 4 (Conditional) If the Installation console can locate existing post offices:
 - 4a (Conditional) If there are any post offices on the post office server that you do not want to upgrade, select them, then click **Remove**.
 - 4b (Conditional) If you want to change the IP address or Admin port for any post office, click its name to display the NetWork Information dialog box.
 - 4c Skip to [Step 6](#) to perform the upgrade.
- 5 (Conditional) If the Installation console cannot locate existing post offices:
 - 5a Click **Add**.
 - 5b Browse to and select the post office folder.
 - 5c Click **OK**, then review the POA IP address and post office Admin port that the Installation console has provided.
 - 5d (Optional) Change the information as needed.
 - 5e Click **OK** to return to the Installation console.

- 5f** (Conditional) If you want to upgrade additional post offices on the post office server, repeat [Step 5a](#) through [Step 5e](#).
- 5g** Continue with [Step 6](#) to perform the upgrade.
- 6** In the list of post offices to upgrade, click **Next** to display the Credentials page.
- 7** Specify the IP address of the primary domain server and the password for the GroupWise Super Admin, then click **Next** to display the Summary page.
- 8** Review the information to ensure that it is correct, then click **Finish** to perform the upgrade.
- 9** (Optional) Click the Existing Configuration slide-out to list all upgraded domains and post offices.
- 10** Click **Go to the GroupWise Administration console now**.
- 11** Accept the self-signed certificate that the Installation console has automatically provided for accessing the Admin console.
- The Login fields are displayed.
- 12** Specify the IP address of the primary domain server and the password for the GroupWise Super Admin, then click **Next** to display the Summary page.
- To finish the upgrade process, you must restart the POAs for all upgraded post offices on the post office server.
- 13** To restart the POA in the upgraded post office:
- 13a** In the Domain box on the Overview page, click **Running** next to the Post Office icon , then click **POA** to display the POA properties page.
- 13b** Click **Stop Agent**, then click **Start Agent** to restart the upgraded POA.
- 13c** (Optional) Click **Launch POA Console** to open the POA console in a new browser window.
-
- NOTE:** You can conveniently open the POA console on the Overview page by clicking **Running**, and then clicking the IP address of the POA.
-
- 14** (Conditional) If the post office server has additional upgraded post offices, repeat [Step 13](#) for the POA in each upgraded post office.
- 15** Continue with the next upgrade task for your GroupWise system:
- ♦ [Section 29.2, “Upgrading GroupWise WebAccess,” on page 185](#)
 - ♦ [Section 29.3, “Upgrading the Calendar Publishing Host,” on page 187](#)
 - ♦ [Section 29.4, “Upgrading GroupWise Monitor,” on page 188](#)

29 Upgrading GroupWise Agents and Applications

- [Section 29.1, “Upgrading the Document Viewer Agent,” on page 185](#)
- [Section 29.2, “Upgrading GroupWise WebAccess,” on page 185](#)
- [Section 29.3, “Upgrading the Calendar Publishing Host,” on page 187](#)
- [Section 29.4, “Upgrading GroupWise Monitor,” on page 188](#)
- [Section 29.5, “Implementing SSL Encryption,” on page 189](#)

29.1 Upgrading the Document Viewer Agent

DVAs on the same servers with POA are automatically upgraded along with the POAs. The following situations require additional upgrade actions:

- If you installed additional DVAs on other servers, you must manually upgrade them. Stop the existing DVA, then install and set up the GroupWise 2014 DVA. For instructions, see [“Scaling Your DVA Installation”](#) in the *GroupWise 2014 R2 Administration Guide*.
- If you were not using the DVA in your existing GroupWise system, you must run at least one DVA in your GroupWise 2014 system. For instructions, see [“Installing the DVA”](#) in the *GroupWise 2014 R2 Administration Guide*.

In all cases, in order to make the DVA appear in the Admin console, you must manually add a DVA object. For instructions, see [“Setting Up the DVA”](#) in the *GroupWise 2014 R2 Administration Guide*.

29.2 Upgrading GroupWise WebAccess

After you have upgraded a domain and a post office to GroupWise 2014 R2, you can upgrade WebAccess for that domain and post office. For information about upgrade issues that you should consider, see [Section 23.4, “WebAccess Upgrades,” on page 165](#).

The POA that the GroupWise WebAccess Application communicates with must be configured for SOAP. A secure SSL connection between the POA and the WebAccess Application is highly recommended.

IMPORTANT: Before you upgrade your WebAccess Application, you must upgrade all post offices that connect to your WebAccess Application or users can have issues logging in.

- [Section 29.2.1, “Preparing to Upgrade the WebAccess Application,” on page 186](#)
- [Section 29.2.2, “Installing the GroupWise 2014 WebAccess Application,” on page 186](#)
- [Section 29.2.3, “Clearing User Browser Caches to Display GroupWise 2014 WebAccess Correctly,” on page 187](#)

29.2.1 Preparing to Upgrade the WebAccess Application

If you are upgrading from GroupWise 2012 to GroupWise 2014 R2, there are no WebAccess upgrade issues. You can upgrade your WebAccess software whenever it is convenient as you upgrade your GroupWise system. However, in order to use the WebAccess Application console, you must change the way it is configured. For instructions, see [“Using the WebAccess Application Console”](#) in the *GroupWise 2014 Administration Guide*.

IMPORTANT: If you are upgrading from GroupWise 8 directly to GroupWise 2014 R2, you need to understand that the WebAccess Agent is no longer part of GroupWise. See [“Understanding WebAccess Updates”](#) and [“Updating GroupWise WebAccess”](#) in the *GroupWise 2012 Installation Guide* before you upgrade WebAccess from GroupWise 8 directly to GroupWise 2014 R2.

29.2.2 Installing the GroupWise 2014 WebAccess Application

- 1 (Conditional) If you are upgrading from GroupWise 8:
 - 1a Prepare the POA to work successfully with the WebAccess Application, as described in the following sections in [“Post Office Agent”](#) in the *GroupWise 2014 R2 Administration Guide*:
 - ♦ [“Supporting SOAP Clients”](#)
 - ♦ [“Securing the Post Office with SSL Connections to the POA”](#)
 - 1b Stop the existing WebAccess Agent.
- 2 (Conditional) On Linux, stop Tomcat.

```
OES 11:      rcnovell-tomcat6 stop
SLES 11:      rctomcat6 stop
```

On Windows, the Installation Wizard does this for you.

- 3 To upgrade WebAccess to GroupWise 2014, follow the standard installation instructions in [Chapter 16, “Setting Up GroupWise WebAccess,”](#) on page 99.

IMPORTANT: If more than one web-based GroupWise component (WebAccess, Calendar Publishing Host, and/or Monitor) is installed on the same server, you must upgrade all web-based GroupWise components at the same time. After one existing web-based component has been upgraded to GroupWise 2014, other web-based components on the server do not work until they also are upgraded to GroupWise 2014.

- 4 Reconfigure the WebAccess Application console.
For instructions, see [“Enabling the WebAccess Application Console”](#) in the *GroupWise 2014 R2 Administration Guide*.
- 5 (Conditional) If you are upgrading from GroupWise 8, complete the steps in [“Cleaning Up the WebAccess Server after Updating to GroupWise 2012”](#) and [“Updating Access Control for WebAccess Users”](#) in the *GroupWise 2012 Installation Guide*.
- 6 Continue with [Clearing User Browser Caches to Display GroupWise 2014 WebAccess Correctly](#).

29.2.3 Clearing User Browser Caches to Display GroupWise 2014 WebAccess Correctly

After you have upgraded the WebAccess Application to GroupWise 2014, notify your GroupWise WebAccess users that they should clear their browser caches before logging into their mailboxes with the upgraded version of GroupWise WebAccess. If old GroupWise WebAccess files are used from users' browser caches, they might not be compatible with the upgraded files from the web server. The results can be unpredictable and undesirable.

29.3 Upgrading the Calendar Publishing Host

There are no Calendar Publishing Host upgrade issues. You can upgrade the Calendar Publishing Host to GroupWise 2014 at any time after the POA that it communicates with has been upgraded. However, in order to use the CalPub Host Admin console, you must change the way it is configured. For instructions, see [Section 17.5.4, "Setting Up Calendar Publishing Administration," on page 125](#).

- ♦ [Section 29.3.1, "Installing the GroupWise 2014 Calendar Publishing Host Application," on page 187](#)
- ♦ [Section 29.3.2, "Clearing User Browser Caches to Display Published Calendars Correctly," on page 188](#)

29.3.1 Installing the GroupWise 2014 Calendar Publishing Host Application

- 1 (Conditional) On Linux, stop Tomcat.

```
OES 11:      rcnovell-tomcat6 stop
SLES 11:     rctomcat6 stop
```

On Windows, the Installation Wizard does this for you.

- 2 To upgrade the Calendar Publishing Host to GroupWise 2014, follow the standard installation instructions in [Chapter 17, "Setting Up the GroupWise Calendar Publishing Host," on page 113](#).

IMPORTANT: If more than one web-based GroupWise component (WebAccess, Calendar Publishing Host, and/or Monitor) is installed on the same server, you must upgrade all web-based GroupWise components at the same time. After one existing web-based component has been upgraded to GroupWise 2014, other web-based components on the server do not work until they also are upgraded to GroupWise 2014.

- 3 Reconfigure the CalPub Host Admin console.
For instructions, see [Section 17.5.4, "Setting Up Calendar Publishing Administration," on page 125](#).
- 4 (Conditional) If you are upgrading from GroupWise 8, complete the steps in "[Cleaning Up the Calendar Publishing Host Server after Updating to GroupWise 2012](#)" in the [GroupWise 2012 Installation Guide](#).
- 5 Continue with [Clearing User Browser Caches to Display Published Calendars Correctly](#).

29.3.2 Clearing User Browser Caches to Display Published Calendars Correctly

After you have upgraded the Calendar Publishing Host Application to GroupWise 2014, notify your GroupWise users that they should clear their browser caches before accessing published calendars. If old Calendar Publishing files are used from users' browser caches, they might not be compatible with the upgraded files from the web server. The results can be unpredictable and undesirable.

External users of published calendars might not see some aspects of the GroupWise 2014 Calendar Publishing interface until after they clear their browser caches.

29.4 Upgrading GroupWise Monitor

After you have upgraded at least one domain to GroupWise 2014, you can upgrade GroupWise Monitor. For information about upgrade issues that you should consider, see [Section 23.2, “Agent Upgrades,”](#) on page 164.

- [Section 29.4.1, “Preparing to Upgrade GroupWise Monitor,”](#) on page 188
- [Section 29.4.2, “Installing the Monitor Software,”](#) on page 188
- [Section 29.4.3, “Clearing Browser Caches to Display GroupWise 2014 Monitor Correctly,”](#) on page 189
- [Section 29.4.4, “Reconfiguring the GroupWise High Availability Service,”](#) on page 189

29.4.1 Preparing to Upgrade GroupWise Monitor

GroupWise Monitor is not dependent on any other GroupWise agents, so you can upgrade the Monitor Agent and the Monitor Application to GroupWise 2014 at any time.

IMPORTANT: If you are upgrading from GroupWise 8 directly to GroupWise 2014, you need to understand that Monitor no longer relies on eDirectory objects for its configuration information. All configuration information is located in the `gwmonitor.cfg` file instead. See [“Understanding Monitor Updates”](#) and [“Updating GroupWise Monitor”](#) in the *GroupWise 2012 Installation Guide* before you upgrade Monitor from GroupWise 8 directly to GroupWise 2014.

29.4.2 Installing the Monitor Software

- 1 Stop the existing Monitor Agent.
- 2 (Conditional) On Linux, stop Tomcat.

```
OES 11:      rcnovell-tomcat6 stop
SLES 11:      rctomcat6 stop
```

On Windows, the Installation Wizard does this for you.

- 3 To upgrade Monitor to GroupWise 2014, follow the standard installation instructions in [Chapter 18, “Setting Up GroupWise Monitor,”](#) on page 131.

IMPORTANT: If more than one web-based GroupWise component (WebAccess, Calendar Publishing Host, and/or Monitor) is installed on the same server, you must upgrade all web-based GroupWise components at the same time. After one existing web-based component has been upgraded to GroupWise 2014, other web-based components on the server do not work until they also are upgraded to GroupWise 2014.

- 4 Restart all GroupWise services on the server.
- 5 (Conditional) If you are upgrading from GroupWise 8, complete the steps in “[Cleaning Up the Monitor Server after Updating to GroupWise 2012](#)” in the *GroupWise 2012 Installation Guide*.
- 6 Continue with [Clearing Browser Caches to Display GroupWise 2014 Monitor Correctly](#).

29.4.3 Clearing Browser Caches to Display GroupWise 2014 Monitor Correctly

After you have upgraded the Monitor Application to GroupWise 2014, clear your browser cache before accessing the upgraded version of GroupWise Monitor. If old GroupWise Monitor files are used from users' browser caches, they might not be compatible with the upgraded files from the web server. The results can be unpredictable and undesirable.

29.4.4 Reconfiguring the GroupWise High Availability Service

On Linux, the GroupWise High Availability Service (gwha), that works in conjunction with GroupWise Monitor to automatically restart the Linux GroupWise agents, now requires an additional file. The `gwha.allow` file lists the user that the High Availability Service uses to log in to the Monitor Agent. This file increases the security of the interaction between the High Available Service and the Monitor Agent. For setup instructions, see [Step 3](#) in “[Creating a GroupWise High Availability Service User](#)” on [page 86](#).

29.5 Implementing SSL Encryption

If you have not yet implemented SSL in your GroupWise system, you can now easily generate self-signed certificates by using the native GroupWise certificate authority (CA). For instructions, see “[Using a Self-Signed Certificate from the GroupWise Certificate Authority](#)” in the *GroupWise 2014 R2 Administration Guide*.

30 Upgrading Users' GroupWise Client Software

After a post office is upgraded to GroupWise 2014, users who have accounts in that post office can start using the GroupWise 2014 clients. You can give users access to a *GroupWise 2014* software on the GroupWise download page, so that they can install the GroupWise client themselves, or you can use the other methods of client software distribution described in “[Distributing the GroupWise Client](#)” in the *GroupWise 2014 R2 Administration Guide*.

31 Transitioning from ConsoleOne

Use the table below to learn how to perform familiar ConsoleOne tasks in the GroupWise Admin console.

Task	ConsoleOne Functionality	Admin Console Functionality
Locate a domain or post office to edit its properties.	Use the eDirectory View to browse the eDirectory tree structure to find the Domain or Post Office object.	Click Domains or Post Offices in the Administration panel to list the Domain or Post Office objects in your GroupWise system.
	or	or
	Use the GroupWise View to list the Domain or Post Office objects in your GroupWise system.	Click the domain or post office on the System Overview page.
		or
Locate a user to edit its properties.		Type the name of the domain or post office in the Global Search field.
	Use the eDirectory View to browse the eDirectory tree structure to find the User object.	Click Users in the Administration panel to list the User objects in your GroupWise system.
	or	or
	Use the GroupWise View to list the User objects in your GroupWise system.	Type the user's first name, last name, GroupWise user name, email address, or file ID (FID) in the Global Search field.
Locate an agent to edit its properties.	Use the eDirectory View to browse the eDirectory tree structure to find the agent object.	Click the agent type in the Administration panel to list the agent objects of that type in your GroupWise system.
	or	or
	Use the GroupWise View to list the agent objects in your GroupWise system.	Click the agent on the System Overview page.
		or
Perform GroupWise system operations.		Type the agent's IP address in the Global Search field.
	Click Tools > GroupWise System Operations .	Click System in the Administration panel.
		or
		Type the name of the GroupWise system tool in the Global Search field.

Task	ConsoleOne Functionality	Admin Console Functionality
Run GroupWise utilities.	Click Tools > GroupWise Utilities .	Click System in the Administration panel. or Type the name of the GroupWise system tool in the Global Search field.
Perform database maintenance.	Browse to and select a Domain or Post Office object, then click Tools > GroupWise Utilities > System Maintenance .	Display the properties of a domain or post office, then click Maintenance > System Maintenance .
Perform Mailbox/Library Maintenance.	Browse to and select a Post Office or User object, then click Tools > GroupWise Utilities > System Maintenance .	Display the properties of a post office or user, then click Maintenance > Mailbox/Library Maintenance .
Set Client Options.	Browse to and select a Domain, Post Office, or User object, then click Tools > GroupWise Utilities > Client Options .	Display the properties of a domain, post office, or user, then click Client Options .

If parts of your GroupWise system are still running legacy GroupWise agents, you should continue to use the legacy ConsoleOne and its snap-ins to administer the legacy parts of your GroupWise system. For convenience, you can safely run the GroupWise 2012 ConsoleOne and snap-ins on most of the legacy parts of your GroupWise system. However, the GroupWise 2012 snap-ins do not support specific legacy GroupWise functionality, such as the WebAccess Agent and its eDirectory objects, which no longer exist in GroupWise 2012.

When you are in the GroupWise 2014 Admin console, you can easily see which agents have not yet been upgraded. Legacy agents that have not yet been upgraded to GroupWise 2014 are marked with their GroupWise version.

32 Upgrading the GroupWise/Exchange Coexistence Solution

If you installed the GroupWise/Exchange Coexistence solution in your GroupWise system, you must follow the instructions in “[Configuring the MTA for Address Book Synchronization](#)” in the [GroupWise/Exchange Coexistence Guide](#) after you upgrade the MTA that synchronizes users between GroupWise and Exchange. This enables you to see the external GroupWise objects in the GroupWise Admin console.

No other changes to GroupWise or Exchange are required to continue using the GroupWise/Exchange Coexistence solution with your GroupWise 2014 system.

VI Appendixes

- ♦ [Appendix A, “GroupWise Version Compatibility,” on page 199](#)
- ♦ [Appendix B, “Attributes, Operators, and Values for Object Filters,” on page 205](#)
- ♦ [Appendix C, “Invalid Characters in GroupWise Object Names and Email Addresses,” on page 209](#)
- ♦ [Appendix D, “Cross-Platform Connections,” on page 211](#)
- ♦ [Appendix E, “Third-Party Materials,” on page 217](#)
- ♦ [Appendix F, “ISAPI Configuration,” on page 229](#)
- ♦ [Appendix G, “Documentation Updates,” on page 231](#)

A GroupWise Version Compatibility

Use the tables in this section to determine compatibility among the following GroupWise versions:

- ♦ [Section A.1, “GroupWise 2014 with Earlier GroupWise Versions,” on page 199](#)
- ♦ [Section A.2, “GroupWise 2014 in a Cross-Platform Environment,” on page 202](#)

For each GroupWise version, the tables indicate compatibility for:

- ♦ **Administrative components:** Domain and post office database platforms and versions, eDirectory platforms, and GroupWise snap-ins to ConsoleOne platforms and versions.
- ♦ **Agents:** Domain and post office database platforms and versions, agent platforms and versions.
- ♦ **Clients:** Post office directory platforms and access, POA platforms and versions, client modes.

In the compatibility tables, cells with combinations that are not applicable are marked N/A. For example, the POA never communicates with the Internet Agent, so that table cell is N/A.

For information about what operating system versions are supported for GroupWise 2014 on Linux and Windows, refer to [“GroupWise System Requirements” on page 25](#). For information about earlier versions of GroupWise, refer to:

- ♦ [GroupWise 2012 Installation Guide](#)
- ♦ [GroupWise 8 Installation Guide](#)

A.1 GroupWise 2014 with Earlier GroupWise Versions

Select the GroupWise version that you want to determine GroupWise 2014 compatibility with:

- ♦ [Section A.1.1, “Compatibility with GroupWise 2012,” on page 199](#)
- ♦ [Section A.1.2, “Compatibility with GroupWise 8,” on page 201](#)

A.1.1 Compatibility with GroupWise 2012

- ♦ [“GroupWise 2014 Administrative Components with GroupWise 2012” on page 199](#)
- ♦ [“GroupWise 2014 Agents with GroupWise 2012” on page 200](#)
- ♦ [“GroupWise 2014 Clients and POAs with GroupWise 2012” on page 200](#)

GroupWise 2014 Administrative Components with GroupWise 2012

GroupWise 2014 Components	GroupWise 2012 Domain and Post Office Databases	GW 2012 Objects in eDirectory	ConsoleOne + GW 2012 Snap-Ins
GW 2014 Domain and Post Office Databases	N/A	N/A	Not Supported
GW 2014 Admin Console	Supported	Not Supported	Not Supported

Table Summary: The GroupWise Admin console can be used to access GroupWise 2012 databases for domains and post offices, but GroupWise 2012 ConsoleOne with the GroupWise snap-ins should not be used to access GroupWise 2014 databases. The Admin console does not access GroupWise eDirectory objects. You must continue to use ConsoleOne with the GroupWise snap-ins to access GroupWise objects in eDirectory.

GroupWise 2014 Agents with GroupWise 2012

GroupWise 2014 Agents	GroupWise 2012 Domain and Post Office Databases	GW 2012 POA	GW 2012 MTA	GW 2012 GWIA	GW 2012 DVA	GW 2012 Monitor Agent
GW 2014 Domain and Post Office Databases	N/A	Not Supported	Not Supported	Not Supported	N/A	N/A
GW 2014 POA	Supported	N/A	Supported	N/A	Supported	Supported
GW 2014 MTA	Supported	Supported	Supported	N/A	N/A	Supported
GW 2014 GWIA	Supported	N/A	Supported	N/A	N/A	Supported
GW 2014 DVA	N/A	Supported	N/A	N/A	N/A	N/A
GW 2014 Monitor Agent	N/A	Supported	Supported	Supported	N/A	N/A

Table Summary: GroupWise 2012 agents cannot access domain and post office databases that have been upgraded to GroupWise 2014. When a GroupWise 2014 MTA or POA accesses an earlier GroupWise database, it has no effect on the database. You must use the Installation console to upgrade domain and post office databases to GroupWise 2014.

GroupWise 2014 Clients and POAs with GroupWise 2012

	GroupWise 2012 Client	GroupWise 2012 POA
GroupWise 2014 Client	N/A	Not Supported
GroupWise 2014 POA	Supported	N/A

Table Summary: The GroupWise 2012 client can communicate with the GroupWise 2014 POA, but the GroupWise 2014 client cannot communicate with the GroupWise 2012 POA. The general rule is that earlier GroupWise clients can always communicate with later POAs, but later GroupWise clients cannot communicate with earlier POAs.

A.1.2 Compatibility with GroupWise 8

IMPORTANT: Support for GroupWise 8 has ended. The information below is provided for your convenience. Some of the options listed below may not work as expected. Use at your own risk.

- ♦ [“GroupWise 2014 Administrative Components with GroupWise 8” on page 201](#)
- ♦ [“GroupWise 2014 Agents with GroupWise 8” on page 201](#)
- ♦ [“GroupWise 2014 Client with GroupWise 8” on page 202](#)

GroupWise 2014 Administrative Components with GroupWise 8

GroupWise 2014 Components	GroupWise 8 Domain and Post Office Databases	GW 8 Objects in eDirectory	ConsoleOne + GW 8 Snap-Ins
GW 2014 Domain and Post Office Databases	N/A	N/A	Not Supported
GW 2014 Admin Console	Supported	Not Supported	Not Supported

Table Summary: The GroupWise Admin console can be used to access GroupWise 8 databases for domains and post offices, but GroupWise 8 ConsoleOne with the GroupWise snap-ins should not be used to access GroupWise 2014 databases. The Admin console does not access GroupWise eDirectory objects. You must continue to use ConsoleOne with the GroupWise snap-ins to access GroupWise objects in eDirectory.

GroupWise 2014 Agents with GroupWise 8

GroupWise 2014 Agents	GroupWise 8 Domain and Post Office Databases	GW 8 POA	GW 8 MTA	GW 8 GWIA	GW 8 WebAccess Agent	GW 8 Monitor Agent
GW 2014 Domain and Post Office Databases	N/A	Not Supported	Not Supported	Not Supported	N/A	N/A
GW 2014 POA	Supported	N/A	Supported	N/A	N/A	Supported
GW 2014 MTA	Supported	Supported	Supported	Supported	N/A	Supported
GW 2014 GWIA	Supported	N/A	Supported	N/A	N/A	Supported
GW 2014 DVA	N/A	N/A	N/A	N/A	N/A	N/A
GW 2014 Monitor Agent	N/A	Supported	Supported	Supported	N/A	N/A

Table Summary: GroupWise 8 agents cannot access domain and post office databases that have been upgraded to GroupWise 2014. When a GroupWise 2014 MTA or POA accesses an earlier GroupWise database, it has no effect on the database. You must use the Installation console to upgrade domain and post office databases to GroupWise 2014.

The Document Viewer Agent (DVA) was introduced in GroupWise 2012 and so does not interact with any GroupWise 8 agents. The WebAccess Agent that was part of GroupWise 8 was eliminated in GroupWise 2012.

GroupWise 2014 Client with GroupWise 8

	GroupWise 8 Client	GroupWise 8 POA
GroupWise 2014 Client	N/A	Not Supported
GroupWise 2014 POA	Supported	N/A

Table Summary: The GroupWise 8 Windows client can communicate with the GroupWise 2014 POA, but the GroupWise 2014 client cannot communicate with the GroupWise8 POA. The general rule is that earlier GroupWise clients can always communicate with later POAs, but later GroupWise clients cannot communicate with earlier POAs.

A.2 GroupWise 2014 in a Cross-Platform Environment

- [Section A.2.1, “GroupWise 2014 Administrative Components and Databases,” on page 202](#)
- [Section A.2.2, “GroupWise 2014 Agents on Linux and Windows,” on page 202](#)

A.2.1 GroupWise 2014 Administrative Components and Databases

Thanks to the web-based nature of the GroupWise Admin console, it does not matter what platform GroupWise databases and agents are on, or where your browser is running, they successfully communicate.

A.2.2 GroupWise 2014 Agents on Linux and Windows

GroupWise 2014 on Linux Agents	GroupWise 2014 Domain or Post Office Databases on Windows	GW 2014 POA on Windows	GW 2014 MTA on Windows	GW 2014 GWIA on Windows	GW 2014 DVA on Windows	GW 2014 Monitor Agent on Windows
GW 2014 Domain and Post Office Databases on Linux	N/A	Not Supported	Not Supported	N/A	N/A	N/A
GW 2014 POA on Linux	Not Supported	N/A	Supported	N/A	Supported	Supported
GW 2014 MTA on Linux	Not Supported	Supported	Supported	Supported	N/A	Supported
GW 2014 GWIA on Linux	N/A	N/A	Supported	N/A	N/A	Supported

GroupWise 2014 on Linux Agents	GroupWise 2014 Domain or Post Office Databases on Windows	GW 2014 POA on Windows	GW 2014 MTA on Windows	GW 2014 GWIA on Windows	GW 2014 DVA on Windows	GW 2014 Monitor Agent on Windows
GW 2014 DVA on Linux	N/A	Supported	N/A	N/A	N/A	N/A
GW 2014 Monitor Agent on Linux	N/A	Supported	Supported	Supported	N/A	N/A

Table Summary: Domains and post offices can be located on Linux or Windows. Run the version of the GroupWise agents that matches the platform where the domains and post offices are located. Agents on either platform can communicate with other agents regardless of platform.

B Attributes, Operators, and Values for Object Filters

In general terms, a filter selects data. In any list of objects, you can use a filter in the **Search** field to select and list GroupWise object data based on object attributes and operators.

- ♦ [Section B.1, “Attributes,” on page 205](#)
- ♦ [Section B.2, “Logical Operators,” on page 206](#)
- ♦ [Section B.3, “Grouping Operators,” on page 207](#)
- ♦ [Section B.4, “Wildcard Characters,” on page 207](#)
- ♦ [Section B.5, “Literal Values,” on page 207](#)
- ♦ [Section B.6, “Date Specifications,” on page 208](#)

B.1 Attributes

To list the attributes that you can filter on for any object type, press Ctrl-Spacebar in the **Search** field of the object list. Common attributes that you might want to filter on include the following:

Object	Common Attributes
Domain	domainversion lockoutoldadmin minimumadminreleasedate minimumadminreleaseversion
Post Office	clientlockout clientlockoutdate clientlockoutversion disabledlogins intruderdetection postofficeversion
User	allowedaddressformats lastclientlogintime logindisabled mailboxicensetype mailboxsizemb preferredemailid visibility
POA	clientserverthreads imapenabled maintenancehandlerthreads messagehandlerthreads soapenabled

Object	Common Attributes
MTA	defaultroutingdomain loglevel platform syncldapservername trackadminmessages

For an exhaustive list of attributes and their possible values, display the following URL on the Admin Service server:

`https://admin_service_address:9710/gwadmin-service/list/object_type/schema`

Replace `admin_service_address` with the IP address or DNS hostname of a server where the Admin Service is installed.

Replace `object_type` with any of the following object types, depending on what you want to list:

- ♦ domain
- ♦ post_office
- ♦ user
- ♦ group
- ♦ resource
- ♦ nickname
- ♦ poa
- ♦ mta
- ♦ gwia
- ♦ library
- ♦ ldap_server

B.2 Logical Operators

Spaces around the operators are optional.

Operator	Meaning	Example
=	Equal	lastname = smith
!=	Not equal	visibility != system
>	Greater than	mailboxsizemb > 500
<	Less than	mtpport < 2000
>=	Greater than or equal to	soapthreads >= 10
<=	Less than or equal to	physicalconnections <= 1000

B.3 Grouping Operators

Spaces around the operators are optional.

Operator	Meaning	Example
&, and	Conjunction	firstname = john & lastname = smith firstname = john and lastname = smith
, or	Disjunction	lastname = smith lastname = jones lastname = smith or lastname = jones
!, not	Inversion	! (lastname = smith lastname = jones) not (lastname = smith or lastname = jones)
()	Parentheses	lastname = smith & (firstname = john firstname = jill) lastname = smith and (firstname = john or firstname = jill)

B.4 Wildcard Characters

The match operator must be used with wildcard characters. The string to match must be surrounded by single quote marks.

Characters	Meaning	Example
*	Zero or more characters	lastname match 'sm*'
?	One character	lastname match 'sm?th'

B.5 Literal Values

Spaces around the operators are optional.

Value	Explanation	Example
null	Empty	internetdomainname != null minimumadminreleasedate != null preferredaddressformat != null
true, 1	Enabled or set	logindisabled = true logindisabled = 1
false, 0	Disabled or not set	soapenabled = false soapenabled = 0

B.6 Date Specifications

You can filter on one specific date or on a range of dates that are relative to today.

Format	Explanation	Example
<code>yyyy-mm-ddTmm:ss</code>	Literal date	2014-01-01T00:00
<code>timelastmod > now(<i>time_unit</i>)</code>	Modified now (current time stamp on server)	<code>timelastmod > now()</code>
	Modified in the last day	<code>timelastmod > now(-1)</code>
	Modified in the last 2 weeks	<code>timelastmod > now(-2, weeks)</code>
	Modified in the last three months	<code>timelastmod > now(-3, months)</code>
	Modified in the last year	<code>timelastmod > now(-1, year)</code>

C Invalid Characters in GroupWise Object Names and Email Addresses

Although most characters in the languages supported by GroupWise can be used in GroupWise object names and Internet email addresses, some cannot.

- ♦ [Section C.1, “Invalid Characters in GroupWise Object Names,” on page 209](#)
- ♦ [Section C.2, “Invalid Characters in Internet Email Addresses,” on page 209](#)

C.1 Invalid Characters in GroupWise Object Names

Do not use any of the following invalid characters in GroupWise object names:

- ♦ Space (use underscore instead)
- ♦ ASCII characters 0-31
- ♦ Extended ASCII characters that are graphical or typographical symbols
Accented characters in the extended range can be used in GroupWise object names.
- ♦ Asterisk *
- ♦ At sign @
- ♦ Backslash \
- ♦ Braces { }
- ♦ Colon :
- ♦ Comma ,
- ♦ Double quote "
- ♦ Parentheses ()
- ♦ Period .

In addition to the characters listed above, do not use any of the following invalid characters in Agent objects names:

- ♦ Exclamation mark !
- ♦ Semicolon ;
- ♦ Single quote '

C.2 Invalid Characters in Internet Email Addresses

Characters that are valid and even desirable in the name of a user, group, or resource might not be valid in an email address. Such invalid characters include spaces and certain accented and special characters. (Providing a definitive list of such invalid characters is beyond the scope of the GroupWise product documentation.)

In the names of users, groups, and resources, use underscores (`_`) rather than spaces as separators between words in order to facilitate addressing across the Internet.

When an object name includes any character that is not valid in an email address, that object cannot receive messages. For such an object, you must set up a preferred email ID in order to ensure that it has a valid email address.

D Cross-Platform Connections

If you want users to be able to install the GroupWise client software to Windows workstations from a location on a Linux server, you must make the Linux server look like a Windows server from the point of view of the workstations. There are a variety of ways to accomplish this. Samba is one of them.

This section provides examples of how to use Samba to install the GroupWise client software from a Linux server.

- ♦ [Section D.1, “Setting up Samba on OES,” on page 211](#)
- ♦ [Section D.2, “Mapping a Drive to a Samba Share on an OES Server,” on page 214](#)
- ♦ [Section D.3, “Setting Up Samba on SLES,” on page 214](#)
- ♦ [Section D.4, “Mapping a Drive to a Samba Share on a SLES Server,” on page 216](#)

D.1 Setting up Samba on OES

In order to access the GroupWise client software on a Linux server, you can set up a Samba share to the client folder, either in the downloaded *GroupWise 2014* software or in the software distribution folder, if you have created one on the Linux server.

- ♦ [Section D.1.1, “Configuring NetWare Core Protocol \(NCP\),” on page 211](#)
- ♦ [Section D.1.2, “Installing Samba,” on page 212](#)
- ♦ [Section D.1.3, “Logging In to iManager,” on page 212](#)
- ♦ [Section D.1.4, “Creating a User to Manage the Samba Share,” on page 212](#)
- ♦ [Section D.1.5, “Configuring the eDirectory Universal Password for Samba,” on page 213](#)
- ♦ [Section D.1.6, “Setting the eDirectory Universal Password for the Samba Administrator User,” on page 213](#)
- ♦ [Section D.1.7, “Creating a Samba Share,” on page 213](#)
- ♦ [Section D.1.8, “Setting the eDirectory Rights for the Samba Share,” on page 213](#)
- ♦ [Section D.1.9, “Testing Samba on the OES Server,” on page 214](#)

D.1.1 Configuring NetWare Core Protocol (NCP)

- 1 In a terminal window on the OES server, become `root` by entering `su -` and the `root` password.
- 2 Enter the following command to create the NCP volume:

```
ncpcon create volume volume_name /folder
```

2a Replace `volume_name` with a unique name for the location of the GroupWise client software.

2b Replace `folder` with the full path to the GroupWise client software, for example:

```
/opt/novell/groupwise/software/client
```

- 3 Verify that the volume has been created:

```
more /etc/opt/novell/ncpserv.conf
```

The new volume should be listed at the end of the NCP server configuration file.

- 4 Restart the Novell eDirectory daemon:

```
rcnstd restart
```

- 5 Continue with [Installing Samba](#).

D.1.2 Installing Samba

If you installed Samba when you installed OES, continue with “[Logging In to iManager](#)” on page 212.

If you did not install Samba when you installed OES, install it now:

- 1 Start YaST.
- 2 Under **Groups**, click **Open Enterprise Server**, then click **OES Install and Configuration**.
- 3 Under **OES Services**, select **Novell Samba**, then click **Accept**.
- 4 Follow the prompts to install Novell Samba.
- 5 Continue with [Logging In to iManager](#).

D.1.3 Logging In to iManager

- 1 Access the following URL:

```
https://ip_address/nps/servlet/webacc?taskid=fw Startup
```

Replace *ip_address* with the IP address of the OES server.

- 2 Specify the eDirectory administrator user name, such as `admin.users.novell`, the password for the user name, and the IP address of the eDirectory tree, then click **Login**.
- 3 Continue with [Creating a User to Manage the Samba Share](#).

D.1.4 Creating a User to Manage the Samba Share

- 1 In iManager, click **Users > Create User**.
- 2 In the **Username** field, specify a unique user name for accessing the Samba share from Windows, such as `gwclient`.
- 3 In the **Last name** field, provide a last name (this is a required field).
- 4 In the **Context** field, browse to and click the eDirectory context where you want to create the new User object.
- 5 Type and confirm the password for the new user.

IMPORTANT: Any users who map a drive to the Samba share need to know this user name and password in order to map the drive.

- 6 Click **OK** to create the Samba user for the GroupWise client Samba share.
- 7 Click **Users** to close the **Users** menu.
- 8 Continue with [Configuring the eDirectory Universal Password for Samba](#).

D.1.5 Configuring the eDirectory Universal Password for Samba

- 1 Click **Passwords > Password Policies**.
- 2 Click **Samba Default Password Policy**.
- 3 On the **Policy Assignment** tab, browse to and click the name of the Samba User object that you created in [“Creating a User to Manage the Samba Share” on page 212](#), then click **OK** to add the user to the list.
- 4 Click **OK** to complete the process.
- 5 Continue with [Setting the eDirectory Universal Password for the Samba Administrator User](#).

D.1.6 Setting the eDirectory Universal Password for the Samba Administrator User

- 1 Under **Passwords**, click **Set Universal Password**.
- 2 Browse to and click the name of the Samba User object, then click **OK**.
- 3 Specify the password for the Samba user, retype the password for confirmation, then click **OK**.
- 4 Click **Passwords** to close the **Passwords** menu.
- 5 Continue with [Creating a Samba Share](#).

D.1.7 Creating a Samba Share

- 1 Click **File Protocols**, then click **Samba**.
- 2 Browse to and click the name of the Server object where you are setting up the Samba share.
- 3 On the **Shares** tab, create a new Samba share for the `client` folder on the Linux server:
 - 3a Click **New**.
 - 3b Specify a unique name for the Samba share, such as `gwclient`.
 - 3c Specify the full path name to the `client` folder on the Linux server, for example:


```
/opt/novell/groupwise/software/client
```
 - 3d Select **Read-Only**.
Write access is not required in order to install the GroupWise client software from the Linux server.
 - 3e Click **OK** to add the location to the list of Samba shares, then click **Close**.
 - 3f Click **File Protocols** to close the **File Protocols** menu.
- 4 Continue with [Setting the eDirectory Universal Password for the Samba Administrator User](#).

D.1.8 Setting the eDirectory Rights for the Samba Share

- 1 Click **Files and Folders**, then click **Properties**.
- 2 Browse to and click the name of the Linux partition or folder where you created the new share, then click **OK**.
- 3 Click **Rights**.
- 4 In the **Add Trustee** field, browse to and click the name of the Samba User object, then click **OK**.

- 5 Under **Inherited Rights Filter**, select **Read**, then click **OK**.
- 6 Continue with [Testing Samba on the OES Server](#).

D.1.9 Testing Samba on the OES Server

- 1 Double-click the Home Directory icon on the Linux desktop.
- 2 Click .
- 3 In the Location field, type `smb://user_name@ip_address`
 - 3a Replace `user_name` with the user name of the Samba administrator user.
 - 3b Replace `ip_address` with the IP address of the Linux server.The File Browser should display all Samba shares, including the new one that you created for the GroupWise client software.
- 4 Return to [Step 3](#) in [Chapter 20, "Installing the GroupWise Client,"](#) on page 153.

D.2 Mapping a Drive to a Samba Share on an OES Server

- 1 On the Windows server, right-click **N** on the Windows taskbar, then click **Novell Map Network Drive**.
- 2 Select the drive letter to map to the NCP volume on the OES server.
- 3 Specify the network path to the NCP volume in the following format:
`\\linux_hostname\ncp_volume`
 - 3a Replace `linux_hostname` with the hostname of the OES server.
 - 3b Replace `ncp_volume` with the name of the NCP volume that you just created.
- 4 For the network user name, specify the fully qualified Samba user name for eDirectory, such as `gwclient.users.novell`.
- 5 Click **Map**.
- 6 Click **OK**.
The mapped drive to the OES server opens in Windows Explorer and can now be accessed from Windows.
- 7 Return to [Step 4](#) in [Chapter 20, "Installing the GroupWise Client,"](#) on page 153.

D.3 Setting Up Samba on SLES

In order to access the GroupWise client software on a Linux server, you can set up a Samba share on the Linux server to the `client` folder, either in the downloaded *GroupWise 2014* software or in the software distribution folder, if you have created one on the Linux server.

- ♦ [Section D.3.1, "Preparing Your Firewall to Allow Samba Connections,"](#) on page 215
- ♦ [Section D.3.2, "Configuring the Samba Server,"](#) on page 215
- ♦ [Section D.3.3, "Configuring the Samba Web Administration Tool \(SWAT\),"](#) on page 215
- ♦ [Section D.3.4, "Accessing SWAT,"](#) on page 215

- ♦ [Section D.3.5, “Setting the Samba User Name and Password,” on page 216](#)
- ♦ [Section D.3.6, “Creating a Samba Share,” on page 216](#)

D.3.1 Preparing Your Firewall to Allow Samba Connections

- 1 In YaST, click **Firewall**, then click **Interfaces**.
- 2 Click **Change**, select **Internal Zone**, then click **OK**.
- 3 Click **Next** to view the summary, then click **Finish**.
- 4 Continue with [Configuring the Samba Server](#).

D.3.2 Configuring the Samba Server

- 1 In YaST, click **Network Services > Samba Server**.
- 2 Specify a workgroup or domain name, then click **Next**.
For use in your GroupWise system, the Samba server does not need to be part of a workgroup or domain, so it does not matter what you put in this field. For example, you could use GWCLIENT.
- 3 Select **Not a Domain Controller**, then click **Next**.
For use in your GroupWise system, the Samba server does not need to be a domain controller.
- 4 Under **Service Start**, select **During Boot**.
Because you prepared the firewall in [“Preparing Your Firewall to Allow Samba Connections” on page 215](#), the **Firewall Settings** section shows that the firewall port for Samba is already open.
- 5 Click **OK** to finish the basic configuration of the Samba server.
- 6 Continue with [Configuring the Samba Web Administration Tool \(SWAT\)](#).

D.3.3 Configuring the Samba Web Administration Tool (SWAT)

- 1 In YaST, click **Network Services > Network Services (xinetd)**.
- 2 Select **Enable**.
- 3 In the **Currently Available Services** list, select `swat`, then click **Toggle Status (On or Off)**.
SWAT is off by default; this turns it on.
- 4 Click **Finish**.
- 5 Continue with [“Accessing SWAT” on page 215](#).

D.3.4 Accessing SWAT

- 1 Display SWAT in your web browser with the following URL:
`http://localhost:901`
- 2 Specify the `root` user name and password, then click **OK**.
- 3 On the SWAT toolbar, click **Status** to verify that `smbd` and `nmbd` are running.
It is not necessary for `winbindd` to be running.
- 4 Continue with [Setting the Samba User Name and Password](#).

D.3.5 Setting the Samba User Name and Password

- 1 On the SWAT toolbar, click **Password**.
- 2 In the **User Name** field, specify a unique user name for use when mapping a drive to the Samba share, such as `gwclient`.
- 3 Type and confirm the password for the new user, then click **Add User**.

IMPORTANT: Any users who map a drive to the Samba share need to know this user name and password in order to map the drive.

- 4 Continue with [Creating a Samba Share](#).

D.3.6 Creating a Samba Share

- 1 On the SWAT toolbar, click **Shares**.
- 2 In the **Create Share** field, type a unique name for the share, such as `gwclient`, then click **Create Share**.
- 3 In the **Path** field, specify the full path name to the `client` folder on the Linux server.
- 4 Leave the **Read Only** field set to the default of **Yes**.

Write access is not required in order to install the GroupWise client software from the Linux server.

- 5 In the **Available** field, select **Yes**.
- 6 Click **Commit Changes**.

The Samba share on the Linux server is now ready for access from a Windows workstation.

- 7 Return to [Step 3](#) in [Chapter 20, "Installing the GroupWise Client,"](#) on page 153.

D.4 Mapping a Drive to a Samba Share on a SLES Server

- 1 In Windows Explorer, right-click the Computer object, then click **Map network drive**.
- 2 In the **Drive** field, select the drive letter for the new Samba share.
- 3 In the **Folder** field, specify the location of the Samba share in the following format:

`\\ip_address\share_name`

- 3a Replace `ip_address` with the IP address of the Linux server.
- 3b Replace `share_name` with the name of the new Samba share where the GroupWise client software is available.
- 4 Deselect **Reconnect to logon**.
- 5 Select **Connect using different credentials**.
- 6 Specify the Samba share user name and password, then click **OK**.

The Samba share for the OES file system opens in Windows Explorer and can now be accessed from Windows.
- 7 Return to [Step 4](#) in [Chapter 20, "Installing the GroupWise Client,"](#) on page 153.

E Third-Party Materials

The following third-party software is included in Novell GroupWise 2014:

- ♦ Section E.1, “Apache,” on page 217
- ♦ Section E.2, “BLT,” on page 218
- ♦ Section E.3, “GD Graphics Library,” on page 218
- ♦ Section E.4, “getopt.h,” on page 219
- ♦ Section E.5, “iCal4j - License,” on page 220
- ♦ Section E.6, “ICU License - ICU 1.8.1 and Later,” on page 220
- ♦ Section E.7, “JRE,” on page 221
- ♦ Section E.8, “NET-SNMP Open Source Package,” on page 221
- ♦ Section E.9, “ODMA 2.0,” on page 223
- ♦ Section E.10, “OpenLDAP,” on page 224
- ♦ Section E.11, “OpenSSL,” on page 225
- ♦ Section E.12, “Oracle Outside In Technology,” on page 226
- ♦ Section E.13, “Python 2.2,” on page 227
- ♦ Section E.14, “Yahoo! UI Library,” on page 227

E.1 Apache

The Apache Software License, Version 1.1 Copyright (c) 2000 The Apache Software Foundation. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. The end-user documentation included with the redistribution, if any, must include the following acknowledgment:
“This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>).”
Alternately, this acknowledgment may appear in the software itself, if and wherever such third-party acknowledgments normally appear.
4. The names “Apache” and “Apache Software Foundation” must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact apache@apache.org.
5. Products derived from this software may not be called “Apache”, nor may “Apache” appear in their name, without prior written permission of the Apache Software Foundation.

THIS SOFTWARE IS PROVIDED ``AS IS'' AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE APACHE SOFTWARE FOUNDATION OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

This software consists of voluntary contributions made by many individuals on behalf of the Apache Software Foundation. For more information on the Apache Software Foundation, please see <<http://www.apache.org/>>.

Portions of this software are based upon public domain software originally written at the National Center for Supercomputing Applications, University of Illinois, Urbana-Champaign.

E.2 BLT

Copyright 1993-1998 Lucent Technologies, Inc.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that the copyright notice and warranty disclaimer appear in supporting documentation, and that the names of Lucent Technologies any of their entities not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

Lucent Technologies disclaims all warranties with regard to this software, including all implied warranties of merchantability and fitness. In no event shall Lucent Technologies be liable for any special, indirect or consequential damages or any damages whatsoever resulting from loss of use, data or profits, whether in an action of contract, negligence or other tortious action, arising out of or in connection with the use or performance of this software.

E.3 GD Graphics Library

Portions copyright 1994, 1995, 1996, 1997, 1998, 1999, 2000, 2001, 2002, 2003, 2004 by Cold Spring Harbor Laboratory. Funded under Grant P41-RR02188 by the National Institutes of Health.

Portions copyright 1996, 1997, 1998, 1999, 2000, 2001, 2002, 2003, 2004 by Boutell.Com, Inc.

Portions relating to GD2 format copyright 1999, 2000, 2001, 2002, 2003, 2004 Philip Warner.

Portions relating to PNG copyright 1999, 2000, 2001, 2002, 2003, 2004 Greg Roelofs.

Portions relating to gdtf.c copyright 1999, 2000, 2001, 2002, 2003, 2004 John Ellson (ellson@graphviz.org).

Portions relating to gdft.c copyright 2001, 2002, 2003, 2004 John Ellson (ellson@graphviz.org).

Portions relating to JPEG and to color quantization copyright 2000, 2001, 2002, 2003, 2004, Doug Becker and copyright (C) 1994, 1995, 1996, 1997, 1998, 1999, 2000, 2001, 2002, 2003, 2004 Thomas G. Lane. This software is based in part on the work of the Independent JPEG Group. See the file README-JPEG.TXT for more information.

Portions relating to GIF compression copyright 1989 by Jef Poskanzer and David Rowley, with modifications for thread safety by Thomas Boutell.

Portions relating to GIF decompression copyright 1990, 1991, 1993 by David Koblas, with modifications for thread safety by Thomas Boutell.

Portions relating to WBMP copyright 2000, 2001, 2002, 2003, 2004 Maurice Szumlo and Johan Van den Brande.

Permission has been granted to copy, distribute and modify gd in any context without fee, including a commercial application, provided that this notice is present in user-accessible supporting documentation.

This does not affect your ownership of the derived work itself, and the intent is to assure proper credit for the authors of gd, not to interfere with your productive use of gd. If you have questions, ask. "Derived works" includes all programs that utilize the library. Credit must be given in user-accessible documentation.

This software is provided "AS IS." The copyright holders disclaim all warranties, either express or implied, including but not limited to implied warranties of merchantability and fitness for a particular purpose, with respect to this code and accompanying documentation.

Although their code does not appear in the current release, the authors also wish to thank Hutchison Avenue Software Corporation for their prior contributions.

E.4 getopt.h

Copyright (c) 2000 The NetBSD Foundation, Inc. All rights reserved.

This code is derived from software contributed to The NetBSD Foundation by Dieter Baron and Thomas Klausner.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. All advertising materials mentioning features or use of this software must display the following acknowledgement:
This product includes software developed by the NetBSD Foundation, Inc. and its contributors.
4. Neither the name of The NetBSD Foundation nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE NETBSD FOUNDATION, INC. AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE FOUNDATION OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN

CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

E.5 iCal4j - License

Copyright (c) 2012, Ben Fortuna

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- ♦ Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- ♦ Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- ♦ Neither the name of Ben Fortuna nor the names of any other contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

E.6 ICU License - ICU 1.8.1 and Later

COPYRIGHT AND PERMISSION NOTICE

Copyright (c) 1995-2006 International Business Machines Corporation and others

All rights reserved.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, provided that the above copyright notice(s) and this permission notice appear in all copies of the Software and that both the above copyright notice(s) and this permission notice appear in supporting documentation.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR HOLDERS INCLUDED IN THIS NOTICE BE LIABLE FOR ANY CLAIM, OR ANY SPECIAL INDIRECT OR CONSEQUENTIAL DAMAGES, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS,

WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Except as contained in this notice, the name of a copyright holder shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization of the copyright holder.

E.7 JRE

JRE Note

This product includes code licensed from RSA Security, Inc. Some portions licensed from IBM are available at <http://oss.software.ibm.com/icu4j/>.

E.8 NET-SNMP Open Source Package

- [Section E.8.1, “---- Part 1: CMU/UCD copyright notice: \(BSD like\) ----,” on page 221](#)
- [Section E.8.2, “---- Part 2: Networks Associates Technology, Inc copyright notice \(BSD\) ----,” on page 222](#)
- [Section E.8.3, “---- Part 3: Cambridge Broadband Ltd. copyright notice \(BSD\) ----,” on page 222](#)
- [Section E.8.4, “---- Part 4: Sun Microsystems, Inc. copyright notice \(BSD\) ----,” on page 223](#)

E.8.1 ---- Part 1: CMU/UCD copyright notice: (BSD like) ----

Copyright 1989, 1991, 1992 by Carnegie Mellon University Derivative Work - 1996, 1998-2000
Copyright 1996, 1998-2000 The Regents of the University of California All Rights Reserved

Permission to use, copy, modify and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appears in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of CMU and The Regents of the University of California not be used in advertising or publicity pertaining to distribution of the software without specific written permission.

CMU AND THE REGENTS OF THE UNIVERSITY OF CALIFORNIA DISCLAIM ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL CMU OR THE REGENTS OF THE UNIVERSITY OF CALIFORNIA BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM THE LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

E.8.2 ---- Part 2: Networks Associates Technology, Inc copyright notice (BSD) -----

Copyright (c) 2001-2003, Networks Associates Technology, Inc All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- ♦ Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- ♦ Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- ♦ Neither the name of the Networks Associates Technology, Inc nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDERS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

E.8.3 ---- Part 3: Cambridge Broadband Ltd. copyright notice (BSD) -----

Portions of this code are copyright (c) 2001-2003, Cambridge Broadband Ltd. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- ♦ Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- ♦ Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- ♦ The name of Cambridge Broadband Ltd. may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDER "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF

LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

E.8.4 ---- Part 4: Sun Microsystems, Inc. copyright notice (BSD) ---

--

Copyright © 2003 Sun Microsystems, Inc., 4150 Network Circle, Santa Clara, California 95054, U.S.A. All rights reserved.

Use is subject to license terms below.

This distribution may include materials developed by third parties.

Sun, Sun Microsystems, the Sun logo and Solaris are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- ♦ Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- ♦ Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- ♦ Neither the name of the Sun Microsystems, Inc. nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDERS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

E.9 ODMA 2.0

OPEN DOCUMENT MANAGEMENT API LICENSE 1.0 ODMA 2.0 SPECIFICATIONS AND SOFTWARE Copyright © 1994-1998 AIIM International

LICENSE:

Redistribution and use in source and binary forms, with or without modifications, are permitted provided that the following conditions are met:

- ♦ Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

- ♦ Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- ♦ Neither the name of AllIM International nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

DISCLAIMER:

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

ADDITIONAL INFORMATION:

- ♦ ODMA reference materials, software, and status: <<http://ODMA.info>>
- ♦ Information about this ODMA License and its application: <<http://DMare.info/license/>>
- ♦ Open Source Definition 1.9 and the BSD License (the model for this ODMA license): <<http://opensource.org>>
- ♦ HTML (ISO 8859-1) version of this license: <<http://Dmware.info/license/P040801F.htm>>

E.10 OpenLDAP

The OpenLDAP Public License Version 2.8, 17 August 2003

Redistribution and use of this software and associated documentation ("Software"), with or without modification, are permitted provided that the following conditions are met:

- 1 Redistributions in source form must retain copyright statements and notices,
- 2 Redistributions in binary form must reproduce applicable copyright statements and notices, this list of conditions, and the following disclaimer in the documentation and/or other materials provided with the distribution, and
- 3 Redistributions must contain a verbatim copy of this document.

The OpenLDAP Foundation may revise this license from time to time. Each revision is distinguished by a version number. You may use this Software under terms of this license revision or under the terms of any subsequent revision of the license.

THIS SOFTWARE IS PROVIDED BY THE OPENLDAP FOUNDATION AND ITS CONTRIBUTORS "AS IS" AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE OPENLDAP FOUNDATION, ITS CONTRIBUTORS, OR THE AUTHOR(S) OR OWNER(S) OF THE SOFTWARE BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER

CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

The names of the authors and copyright holders must not be used in advertising or otherwise to promote the sale, use or other dealing in this Software without specific, written prior permission. Title to copyright in this Software shall at all times remain with copyright holders.

OpenLDAP is a registered trademark of the OpenLDAP Foundation.

E.11 OpenSSL

OpenSSL License Copyright (c) 1998-2002 The OpenSSL Project. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1 Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2 Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3 All advertising materials mentioning features or use of this software must display the following acknowledgment:
"This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit. (<http://www.openssl.org/>)"
- 4 The names "OpenSSL Toolkit" and "OpenSSL Project" must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact openssl-core@openssl.org.
- 5 Products derived from this software may not be called "OpenSSL" nor may "OpenSSL" appear in their names without prior written permission of the OpenSSL Project.
- 6 Redistributions of any form whatsoever must retain the following acknowledgment:
"This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org/>)"

THIS SOFTWARE IS PROVIDED BY THE OpenSSL PROJECT ``AS IS'' AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE OpenSSL PROJECT OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

This product includes cryptographic software written by Eric Young (ey@cryptsoft.com). This product includes software written by Tim Hudson (tjh@cryptsoft.com).

Original SSLeay License

Copyright (C) 1995-1998 Eric Young (ey@cryptsoft.com) All rights reserved.

This package is an SSL implementation written by Eric Young (eay@cryptsoft.com). The implementation was written so as to conform with Netscape's SSL.

This library is free for commercial and non-commercial use as long as the following conditions are adhered to. The following conditions apply to all code found in this distribution, be it the RC4, RSA, lhash, DES, etc., code; not just the SSL code. The SSL documentation included with this distribution is covered by the same copyright terms except that the holder is Tim Hudson (tjh@cryptsoft.com).

Copyright remains Eric Young's, and as such any Copyright notices in the code are not to be removed. If this package is used in a product, Eric Young should be given attribution as the author of the parts of the library used. This can be in the form of a textual message at program startup or in documentation (online or textual) provided with the package.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1 Redistributions of source code must retain the copyright notice, this list of conditions and the following disclaimer.
- 2 Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3 All advertising materials mentioning features or use of this software must display the following acknowledgement:

"This product includes cryptographic software written by Eric Young (eay@cryptsoft.com)"

The word "cryptographic" can be left out if the routines from the library being used are not cryptographic related :-).

- 4 If you include any Windows specific code (or a derivative thereof) from the apps directory (application code) you must include an acknowledgement:

"This product includes software written by Tim Hudson (tjh@cryptsoft.com)"

THIS SOFTWARE IS PROVIDED BY ERIC YOUNG ``AS IS'' AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

The licence and distribution terms for any publicly available version or derivative of this code cannot be changed; i.e. this code cannot simply be copied and put under another distribution licence [including the GNU Public Licence.]

E.12 Oracle Outside In Technology

Oracle shall inform you of any notices and other instructions that are related to third party components (including open source software) that are included in a program and/or hardware and that Oracle is required to distribute with such programs and/or hardware. These notices and other

instructions shall be provided to you in at least one of the following ways, at Oracle's sole discretion: (a) automatically installed with the programs or in the installation details; (b) in the program documentation; (c) in the readme files or notice files; or (d) via a supplemental list.

You shall comply with all instructions related to third party software components (including open source software). If you reproduce the programs, operating system and/or integrated software, you shall reproduce all third party notices in an appropriate location in the reproduction and/or in its related documentation and include any associated source code (to the extent such source code is provided by Oracle), as required by the applicable notices or as otherwise directed by Oracle.

E.13 Python 2.2

Copyright (c) 1991 - 1995, Stichting Mathematisch Centrum Amsterdam, The Netherlands. All rights reserved.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Stichting Mathematisch Centrum or CWI not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

STICHTING MATHEMATISCH CENTRUM DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL STICHTING MATHEMATISCH CENTRUM BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

E.14 Yahoo! UI Library

Yahoo! UI Library uses the BSD License which states:

Software License Agreement (BSD License)

Copyright (c) 2006, Yahoo! Inc.

All rights reserved.

Redistribution and use of this software in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- ♦ Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- ♦ Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- ♦ Neither the name of Yahoo! Inc. nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission of Yahoo! Inc.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE

ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

F ISAPI Configuration

As of Windows 2008 R2, ISAPI support is no longer installed by default when Internet Information Services (IIS) is installed. As ISAPI support is required on Windows for WebAccess, Calendar Publishing Host, and Monitor, it needs to be added to IIS before these GroupWise components are installed. If ISAPI is added after the GroupWise components are installed, the individual components will need to be reinstalled. To add ISAPI to IIS after IIS has already been installed, continue with the steps for your operating system below:

- ♦ [Section F.1, “Windows 2012 R2,” on page 229](#)

F.1 Windows 2012 R2

- 1 In Windows Server Manager, click **Add roles and features**.
- 2 (Optional) If **Before You Begin** is displayed, click **Next**.
- 3 On the **Installation Type** page, make sure **Role-based or feature-based installation** is selected and then click **Next**.
- 4 On the **Server Selection** page, select your server and click **Next**.
- 5 Expand **Web Server (IIS)**, **Web Server**, and then **Application Development**.
- 6 Select **ISAPI Extensions** and **ISAPI Filters**, then click **Next**.
- 7 Click **Next** on the **Features** page.
- 8 Click **Install**.

G Documentation Updates

This section lists updates to the *GroupWise 2014 Installation Guide* that have been made since the initial release of GroupWise 2014. The information helps you to keep current on documentation updates and, in some cases, software updates (such as a Support Pack release).

The information is grouped according to the date when the *GroupWise 2014 Installation Guide* was republished. Within each dated section, the updates are listed by the names of the main table of contents sections.

The *GroupWise 2014 Installation Guide* has been updated on the following dates:

