

## Installation Guide

# Kablink® Teaming

**2.0**

July 31, 2009

## Legal Notices

Novell, Inc. makes no representations or warranties with respect to the contents or use of this documentation, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. reserves the right to revise this publication and to make changes to its content, at any time, without obligation to notify any person or entity of such revisions or changes.

Further, Novell, Inc. makes no representations or warranties with respect to any software, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc. reserves the right to make changes to any and all parts of Novell software, at any time, without any obligation to notify any person or entity of such changes.

Any products or technical information provided under this Agreement may be subject to U.S. export controls and the trade laws of other countries. You agree to comply with all export control regulations and to obtain any required licenses or classification to export, re-export or import deliverables. You agree not to export or re-export to entities on the current U.S. export exclusion lists or to any embargoed or terrorist countries as specified in the U.S. export laws. You agree to not use deliverables for prohibited nuclear, missile, or chemical biological weaponry end uses. See the [Novell International Trade Services Web page \(http://www.novell.com/info/exports/\)](http://www.novell.com/info/exports/) for more information on exporting Novell software. Novell assumes no responsibility for your failure to obtain any necessary export approvals.

Copyright © 2008-2009 Novell, Inc. All rights reserved. Permission is granted to copy, distribute, and/or modify this document under the terms of the GNU Free Documentation License (GFDL), Version 1.2 or any later version, published by the Free Software Foundation with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the GFDL can be found at <http://www.fsf.org/licenses/fdl.html>.

THIS DOCUMENT AND MODIFIED VERSIONS OF THIS DOCUMENT ARE PROVIDED UNDER THE TERMS OF THE GNU FREE DOCUMENTATION LICENSE WITH THE FURTHER UNDERSTANDING THAT:

1. THE DOCUMENT IS PROVIDED ON AN "AS IS" BASIS, WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, WARRANTIES THAT THE DOCUMENT OR MODIFIED VERSION OF THE DOCUMENT IS FREE OF DEFECTS, MERCHANTABLE, FIT FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT. THE ENTIRE RISK AS TO THE QUALITY, ACCURACY, AND PERFORMANCE OF THE DOCUMENT OR MODIFIED VERSION OF THE DOCUMENT IS WITH YOU. SHOULD ANY DOCUMENT OR MODIFIED VERSION PROVE DEFECTIVE IN ANY RESPECT, YOU (NOT THE INITIAL WRITER, AUTHOR OR ANY CONTRIBUTOR) ASSUME THE COST OF ANY NECESSARY SERVICING, REPAIR OR CORRECTION. THIS DISCLAIMER OF WARRANTY CONSTITUTES AN ESSENTIAL PART OF THIS LICENSE. NO USE OF ANY DOCUMENT OR MODIFIED VERSION OF THE DOCUMENT IS AUTHORIZED HEREUNDER EXCEPT UNDER THIS DISCLAIMER; AND

2. UNDER NO CIRCUMSTANCES AND UNDER NO LEGAL THEORY, WHETHER IN TORT (INCLUDING NEGLIGENCE), CONTRACT, OR OTHERWISE, SHALL THE AUTHOR, INITIAL WRITER, ANY CONTRIBUTOR, OR ANY DISTRIBUTOR OF THE DOCUMENT OR MODIFIED VERSION OF THE DOCUMENT, OR ANY SUPPLIER OF ANY OF SUCH PARTIES, BE LIABLE TO ANY PERSON FOR ANY DIRECT, INDIRECT, SPECIAL, INCIDENTAL, OR CONSEQUENTIAL DAMAGES OF ANY CHARACTER INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF GOODWILL, WORK STOPPAGE, COMPUTER FAILURE OR MALFUNCTION, OR ANY AND ALL OTHER DAMAGES OR LOSSES ARISING OUT OF OR RELATING TO USE OF THE DOCUMENT AND MODIFIED VERSIONS OF THE DOCUMENT, EVEN IF SUCH PARTY SHALL HAVE BEEN INFORMED OF THE POSSIBILITY OF SUCH DAMAGES.

Novell, Inc. has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more of the U.S. patents listed on the [Novell Legal Patents Web page \(http://www.novell.com/company/legal/patents/\)](http://www.novell.com/company/legal/patents/) and one or more additional patents or pending patent applications in the U.S. and in other countries.

Novell, Inc.

404 Wyman Street, Suite 500  
Waltham, MA 02451  
U.S.A.  
[www.novell.com](http://www.novell.com)

*Online Documentation:* To access the latest online documentation for this and other Novell products, see  
[the Novell Documentation Web page \(http://www.novell.com/documentation\)](http://www.novell.com/documentation).

## **Novell Trademarks**

For Novell trademarks, see [the Novell Trademark and Service Mark list \(http://www.novell.com/company/legal/trademarks/tmlist.html\)](http://www.novell.com/company/legal/trademarks/tmlist.html).

## **Third-Party Materials**

All third-party trademarks are the property of their respective owners.

# Contents

<b>About This Guide</b>	<b>9</b>
<b>Part I Basic Installation</b>	<b>11</b>
<b>1 What Is Kablink Teaming?</b>	<b>13</b>
1.1 Teaming Capabilities	13
1.1.1 Content Consumers	13
1.1.2 Content Providers	13
1.1.3 Administrators	14
1.2 Teaming Components	14
1.2.1 Teaming Software	14
1.2.2 Teaming Database	15
1.2.3 Teaming File Repository	15
1.2.4 Lucene Index	15
1.3 Teaming Configurations	15
<b>2 Teaming System Requirements</b>	<b>17</b>
2.1 Teaming Server Requirements	17
2.2 Teaming User Requirements	18
2.3 Supported Environments	19
2.3.1 File Viewer Support	19
2.3.2 IPV6 Support	19
2.3.3 Clustering Support	20
2.3.4 Xen Virtualization Support	20
2.3.5 VMware Support	20
2.3.6 Linux File System Support	20
2.4 Recommended Hardware Configurations	20
<b>3 Planning a Basic Teaming Installation</b>	<b>23</b>
3.1 What Is a Basic Teaming Installation?	23
3.2 Selecting the Operating Environment for Your Teaming Server	24
3.2.1 Teaming Server Platform	24
3.2.2 Teaming Server Architecture	24
3.2.3 Teaming Server Memory	24
3.2.4 Teaming Installation Locations	26
3.3 Selecting a Java Development Kit	26
3.4 Gathering Network Information for Your Teaming Site	27
3.4.1 Hostname	27
3.4.2 Port Numbers	27
3.5 Planning the Teaming Database	29
3.5.1 Database Type	29
3.5.2 Database Setup Method	30
3.5.3 Database Location	30
3.5.4 Database Credentials	31
3.5.5 Database Encryption Algorithm	32
3.6 Gathering Outbound E-Mail Information	32
3.6.1 Outbound E-Mail Protocol	32

3.6.2	Outbound E-Mail Host . . . . .	33
3.6.3	Outbound E-Mail Authentication . . . . .	33
3.6.4	Outbound E-Mail Send Restriction . . . . .	34
3.7	Enabling Inbound E-Mail . . . . .	34
3.7.1	Internal Mail Host for Inbound E-Mail . . . . .	34
3.7.2	Inbound E-Mail Port Number . . . . .	34
3.7.3	Inbound E-Mail IP Address . . . . .	35
3.7.4	Inbound E-Mail Security . . . . .	35
3.8	Planning Site Security . . . . .	36
3.8.1	Teaming Site Administrator Password . . . . .	36
3.8.2	Linux User ID for Teaming . . . . .	36
3.9	Gathering Directory Services Information . . . . .	37
3.9.1	LDAP Directory Service . . . . .	37
3.9.2	LDAP Connections . . . . .	37
3.9.3	LDAP Synchronization Options . . . . .	40
3.10	Accommodating Multiple Languages . . . . .	42
<b>4</b>	<b>Setting Up a Basic Teaming Site . . . . .</b>	<b>45</b>
4.1	Linux: Setting Up a Basic Teaming Site . . . . .	45
4.1.1	Performing Pre-Installation Tasks on Linux . . . . .	45
4.1.2	Running the Linux Teaming Installation Program . . . . .	46
4.1.3	Configuring Teaming to Start Automatically on Reboot . . . . .	49
4.1.4	Setting Up Port Forwarding . . . . .	49
4.1.5	Configuring the Document Converter on Linux . . . . .	51
4.1.6	Starting Teaming on Linux . . . . .	52
4.1.7	Checking the Status of the Teaming Server . . . . .	52
4.1.8	Restarting Teaming . . . . .	52
4.1.9	Stopping Teaming . . . . .	53
4.1.10	Uninstalling Teaming . . . . .	53
4.2	Windows: Setting Up a Basic Teaming Site . . . . .	53
4.2.1	Performing Pre-Installation Tasks on Windows . . . . .	53
4.2.2	Running the Windows Teaming Installation Program . . . . .	54
4.2.3	Configuring the Document Converter on Windows . . . . .	55
4.2.4	Running Teaming as a Windows Service . . . . .	57
4.2.5	Running Teaming as a Windows Application . . . . .	58
4.2.6	Uninstalling Teaming . . . . .	58
<b>5</b>	<b>Adding Users to Your Teaming Site . . . . .</b>	<b>59</b>
5.1	Accessing Your Basic Teaming Site as the Site Administrator . . . . .	59
5.2	Creating a User . . . . .	60
5.3	Adding Teaming Users from Your LDAP Directory . . . . .	61
5.4	Preventing Users from Creating User Accounts . . . . .	63
<b>6</b>	<b>What's Next . . . . .</b>	<b>65</b>
<b>7</b>	<b>Basic Teaming Installation Summary Sheet . . . . .</b>	<b>67</b>
<b>Part II</b>	<b>Advanced Installation and Reconfiguration . . . . .</b>	<b>73</b>
<b>8</b>	<b>Planning an Advanced Teaming Installation . . . . .</b>	<b>75</b>
8.1	What Is an Advanced Installation? . . . . .	75

8.2	Distributing Different Data Types to Different Locations . . . . .	75
8.3	Using Advanced Network Information Settings . . . . .	77
8.3.1	Changing the Teaming Session Timeout. . . . .	77
8.3.2	Providing a Secure Keystore File . . . . .	77
8.4	Configuring Web Services . . . . .	78
8.5	Changing Your Lucene Index Server Configuration. . . . .	78
8.5.1	Understanding Indexing. . . . .	78
8.5.2	Changing Lucene Configuration Settings . . . . .	79
8.6	Managing RSS Feeds . . . . .	79
8.6.1	Configuring RSS Feeds. . . . .	79
8.6.2	Disabling RSS Feeds. . . . .	80
8.7	Configuring Presence. . . . .	80
<b>9</b>	<b>Performing an Advanced Teaming Installation</b>	<b>83</b>
<b>10</b>	<b>Setting Configuration Options after Installation</b>	<b>85</b>
<b>11</b>	<b>Advanced Teaming Installation Summary Sheet</b>	<b>87</b>
<b>Part III</b>	<b>Multi-Server Configurations and Clustering</b>	<b>89</b>
<b>12</b>	<b>Creating the Teaming Database on a Remote Server</b>	<b>91</b>
12.1	Preparing to Manually Create a Database . . . . .	91
12.2	Creating a MySQL Database . . . . .	92
12.3	Creating a Microsoft SQL Database . . . . .	93
12.4	Creating an Oracle Database. . . . .	93
12.5	Installing Teaming with a Remote Database . . . . .	95
<b>13</b>	<b>Running Multiple Database Servers</b>	<b>97</b>
<b>Part IV</b>	<b>Update</b>	<b>99</b>
<b>14</b>	<b>What's New in Kablink Teaming 2.0</b>	<b>101</b>
14.1	Teaming 2.0 User Enhancements . . . . .	101
14.2	Teaming 2.0 Installation Enhancements . . . . .	101
14.3	Teaming 2.0 Administration Enhancements . . . . .	101
<b>15</b>	<b>Updating from Kablink Teaming 1.0 to Kablink Teaming 2.0</b>	<b>103</b>
15.1	Understanding the Update Process . . . . .	103
15.2	Preparing Your Teaming Site for Update . . . . .	103
15.2.1	Updating Your Operating Environment . . . . .	104
15.2.2	Backing Up Your Teaming Data . . . . .	104
15.2.3	Planning Your Teaming 2.0 Installation . . . . .	105
15.3	Updating a Single-Server Teaming Site. . . . .	105
15.3.1	Updating an Oracle Database . . . . .	107
15.4	Updating a Multiple-Server Teaming Site . . . . .	107
15.4.1	Remote Teaming Database. . . . .	107
15.4.2	Remote Lucene Index Server . . . . .	108

15.5	Performing Post-Update Tasks	109
<b>16</b>	<b>Updating from Kablink Teaming 1.0 to Novell Teaming 2.0</b>	<b>113</b>
<b>17</b>	<b>Changing from Kablink Teaming 2.0 to Novell Teaming 2.0</b>	<b>115</b>
<b>Part V</b>	<b>Appendixes</b>	<b>117</b>
<b>A</b>	<b>Teaming System Requirements Assistance</b>	<b>119</b>
A.1	Java Development Kit	119
A.1.1	Sun JDK on Linux	119
A.1.2	IBM JDK on Linux	120
A.1.3	Sun JDK on Windows	120
A.2	MySQL Database Server	121
A.2.1	MySQL on Linux	121
A.2.2	MySQL on Windows	123
<b>B</b>	<b>Third-Party Materials</b>	<b>125</b>
B.1	ANTLR 3 License	125
B.2	Colt License Agreement	126
B.3	Dom4j License	126
B.4	iCal4j License	127
B.5	ICU4J license (ICU4J 1.3.1 and later)	127
B.6	Java Portlet Specifications 1.0: JSR 168	128
B.7	Java Transaction API (JTA) 1.0.16	128
B.8	JavaServer Pages Standard Tag Library (JSLT) 1.0.5	129
B.9	JAXEN License	130
B.10	Jung	130



# About This Guide

The *Kablink Teaming 2.0 Installation Guide* covers the installation and configuration of the Kablink® Teaming software. The guide is divided into the following sections:

- ♦ Part I, “Basic Installation,” on page 11
- ♦ Part II, “Advanced Installation and Reconfiguration,” on page 73
- ♦ Part III, “Multi-Server Configurations and Clustering,” on page 89
- ♦ Part IV, “Update,” on page 99
- ♦ Part V, “Appendixes,” on page 117

For Teaming site setup instructions, see the *Kablink Teaming 2.0 Administration Guide*

## Audience

This guide is intended for Kablink Teaming administrators.

## Feedback

We want to hear your comments and suggestions about this manual and the other documentation included with this product. Please use the User Comments feature at the bottom of each page of the online documentation, or go to [www.novell.com/documentation/feedback.html](http://www.novell.com/documentation/feedback.html) and enter your comments there.

## Documentation Updates

For the most recent version of the *Kablink Teaming 2.0 Installation Guide* and other documentation, visit the [Kablink Teaming 2.0 Documentation Web site \(http://www.novell.com/documentation/kablinkteaming2\)](http://www.novell.com/documentation/kablinkteaming2).

## Additional Documentation

You can find more information in the Kablink Teaming documentation, which is accessible from links within Kablink Teaming:

- ♦ Kablink Teaming Help system
- ♦ *Kablink Teaming Quick Start*
- ♦ *Kablink Teaming User Guide*
- ♦ *Kablink Teaming Advanced User Guide*
- ♦ *Kablink Teaming Administration Guide*
- ♦ *Kablink Teaming Developer Guide*

To access the Kablink Teaming Help system, log in to the Teaming site, then click the *Help* icon (question mark), then click a yellow Help spot for context-sensitive help.

To access the Kablink Teaming guides from within Teaming, click the *Help* icon (question mark), then click *Teaming Manuals*.

## Documentation Conventions

In Novell documentation, a greater-than symbol (>) is used to separate actions within a step and items in a cross-reference path.

A trademark symbol (® , ™ , etc.) denotes a Novell trademark. An asterisk (\*) denotes a third-party trademark.

When a single pathname can be written with a backslash for some platforms or a forward slash for other platforms, the pathname is presented with a backslash. Users of platforms that require a forward slash, such as Linux\* or UNIX\* , should use forward slashes as required by your software.

# Basic Installation

- ♦ Chapter 1, “What Is Kablink Teaming?,” on page 13
- ♦ Chapter 2, “Teaming System Requirements,” on page 17
- ♦ Chapter 3, “Planning a Basic Teaming Installation,” on page 23
- ♦ Chapter 4, “Setting Up a Basic Teaming Site,” on page 45
- ♦ Chapter 5, “Adding Users to Your Teaming Site,” on page 59
- ♦ Chapter 6, “What’s Next,” on page 65
- ♦ Chapter 7, “Basic Teaming Installation Summary Sheet,” on page 67



# What Is Kablink Teaming?

# 1

Kablink® Teaming is an enterprise collaboration tool designed to increase individual productivity, team effectiveness, and organizational success by providing the right set of tools to the right people.

- ♦ [Section 1.1, “Teaming Capabilities,” on page 13](#)
- ♦ [Section 1.2, “Teaming Components,” on page 14](#)
- ♦ [Section 1.3, “Teaming Configurations,” on page 15](#)

## 1.1 Teaming Capabilities

KablinkTeaming users fall into three basic groups:

- ♦ [Section 1.1.1, “Content Consumers,” on page 13](#)
- ♦ [Section 1.1.2, “Content Providers,” on page 13](#)
- ♦ [Section 1.1.3, “Administrators,” on page 14](#)

### 1.1.1 Content Consumers

Content consumers use Kablink Teaming to work with important information that pertains to them. Content consumers:

- ♦ Maintain their personal workspaces, including setting up a personal blog, calendar, file folder, guestbook, photo album, and task folder
- ♦ Participate in team workspaces set up for content providers, in order to better collaborate with colleagues and facilitate their work assignments
- ♦ Search the Teaming site for people, places, and other information that pertains to their personal work assignments
- ♦ Identify subject-matter experts to assist them in their personal work assignments

The typical tasks performed by content consumers are covered in the *Kablink Teaming 2.0 User Guide*.

In many cases, content consumers quickly become content providers as well.

### 1.1.2 Content Providers

Content providers use Kablink Teaming to create and manage teams, customize the Teaming environment, and import data into the Teaming site for use by other Teaming users. Content providers:

- ♦ Create and manage team workspaces and folders
- ♦ Control user access to their team workspaces
- ♦ Establish unique branding for workspaces and folders to clearly differentiate them from other places on the Teaming site

- ♦ Create landing pages for workspaces that consolidate the most information workspace information into a single page
- ♦ Customize data entry forms for gathering information from users
- ♦ Create workflows to automate otherwise time-consuming manual processes

The typical tasks performed by content providers are covered in the *Kablink Teaming 2.0 Advanced User Guide*.

### 1.1.3 Administrators

A Kablink Teaming administrator is responsible for installing the Teaming software and setting up the Teaming site. This *Kablink 2.0 Installation Guide* provides instructions for Teaming software installation. After installation, the Teaming site administrator can:

- ♦ Set up user access to the Teaming site
- ♦ Create initial workspaces and populate them with information that is of interest to Teaming users
- ♦ Control user access to workspaces and folders
- ♦ Configure e-mail integration, so that Teaming users can receive notifications of updated information on the Teaming site and post to the Teaming site using e-mail messages
- ♦ Set up mirrored folders to make large sets of data that are already available on disk more easily available through the Teaming site
- ♦ Set up software extensions (add-ons) that enhance the power and usefulness of the Teaming site
- ♦ Set up remote applications that deliver data from a remote location, such as a remote database, for easy access on your Teaming site
- ♦ Manage users, workspaces, and folders as the Teaming site grows and evolves
- ♦ Perform regular backups to safeguard the data stored in the Teaming site

The typical tasks performed by Teaming site administrators are covered in the *Kablink Teaming 2.0 Administration Guide*.

## 1.2 Teaming Components

A Kablink Teaming site consists of four major components:

- ♦ [Section 1.2.1, “Teaming Software,” on page 14](#)
- ♦ [Section 1.2.2, “Teaming Database,” on page 15](#)
- ♦ [Section 1.2.3, “Teaming File Repository,” on page 15](#)
- ♦ [Section 1.2.4, “Lucene Index,” on page 15](#)

### 1.2.1 Teaming Software

The Kablink software is a customized version of Apache\* Tomcat. This software provides all the Web-based functionality you use as you access the Teaming site through your Web browser.

## 1.2.2 Teaming Database

The Kablink Teaming database is used for storing information about the Teaming site and its users:

- ♦ Structural information about workspaces, folders, and entries (for example, their location in the workspace tree)
- ♦ Identification information about workspaces, folders, and entries (for example, titles, descriptions, dates of creation/modification, and users associated with creation/modification)
- ♦ User profile information (for example, full name, phone number, and e-mail address)

The Teaming database disk space requirements are relatively modest, because it is not used for storing files.

## 1.2.3 Teaming File Repository

The Kablink Teaming file repository holds all files that are imported into Teaming, information related to the imported files, such as thumbnails and HTML renderings, and the search engine index.

The Teaming file repository disk space requirements depend on the size of the Teaming site. For a large Teaming site, disk space requirements can be substantial.

## 1.2.4 Lucene Index

The Lucene\* Index Server is a high-performance Java search engine. The Lucene index contains pointers to the actual data stored in the Teaming file repository. The index enables the Lucene search engine to perform very fast searches through large quantities of Teaming data.

## 1.3 Teaming Configurations

You can configure Kablink Teaming to run on a single server or multiple servers, depending on the size and needs of your Teaming site.

Configuration	Description
Single Server	By default, the Kablink Teaming Installation program installs all Teaming components on the same server.
Remote Database Server	For better performance and scalability, you can install the Teaming database on a remote server
Remote Lucene Index Server	For better performance and scalability, you can install the Lucene index on a remote server  This configuration is not available with Kablink Teaming.
Multiple Teaming Servers	By running Novell Teaming on multiple servers, you can achieve high availability functionality, including failover and load balancing, depending on how you configure your servers.  This configuration is not available with Kablink Teaming.

Configuration	Description
Multiple Remote Lucene Servers	<p>Your Novell Teaming site depends on the Lucene Index Server for full functionality. Running multiple Lucene Index Servers provides high availability functionality, so that if one Lucene Index Server goes down, Teaming users can still access the Teaming site because other Lucene Index Servers are still available.</p> <p>This configuration is not available with Kablink Teaming.</p>
Multiple Remote Database Servers	<p>The three databases supported by Teaming each have their own approach to clustering the database server. Information about clustering database servers is available on the Internet.</p>

For more information, see [Part III, “Multi-Server Configurations and Clustering,” on page 89](#).



# Teaming System Requirements

# 2

You, as a Kablink® Teaming site administrator, must ensure that your system meets Teaming system requirements, so that your Teaming site can be set up successfully. After your Teaming site is set up, you must ensure that users' browsers and office applications meet Teaming user requirements, so that users can access the Teaming site successfully.

- ♦ Section 2.1, “Teaming Server Requirements,” on page 17
- ♦ Section 2.2, “Teaming User Requirements,” on page 18
- ♦ Section 2.3, “Supported Environments,” on page 19
- ♦ Section 2.4, “Recommended Hardware Configurations,” on page 20

## 2.1 Teaming Server Requirements

- ♦ Hardware for the Kablink Teaming server:
  - ♦ 32-bit/x86 processor or 64-bit/x86 processor
  - ♦ Minimum 2 GHz processor
  - ♦ Multi-CPU systems preferred
  - ♦ Adequate server memory:
    - ♦ At least 3 GB RAM for a 32-bit processor
    - ♦ At least 4 GB RAM for a 64-bit processor

See Section 2.4, “Recommended Hardware Configurations,” on page 20 and Section 3.2.3, “Teaming Server Memory,” on page 24

- ♦ Any of the following supported server operating systems for the Teaming server:
  - ♦ Novell® Open Enterprise Server (OES) 2 Linux, plus the latest Support Pack
  - ♦ SUSE® Linux Enterprise Server (SLES) 10 or SLES 11, plus the latest Support Pack

---

**NOTE:** The X Window System is required by the Teaming Installation program. It is not required when running Teaming after installation.

---

- ♦ Windows\* Server\* 2003 or Windows Server 2008, plus the latest Service Pack

Kablink Teaming can be run on additional Linux and Windows operating systems. For more information, see the [Kablink Open Collaboration Web site \(http://www.kablink.org\)](http://www.kablink.org).

- ♦ Database server:
  - ♦ Linux:
    - ♦ MySQL\* 5.0.26 or later server and client, or MySQL 5.1 server and client

---

**NOTE:** MySQL 5.0.26 is included with SLES 10 SP1 and OES 2 Linux. MySQL 5.0.67 is included with SLES 11.

---

- ♦ Oracle\* 10g or Oracle 11g
- ♦ Windows:
  - ♦ MySQL 5.0.26 or later server and tools, or MySQL 5.1 server and tools

- ♦ Microsoft\* SQL Server\* 2005 or SQL Server 2008, plus the latest Service Pack
- ♦ Oracle 10g or Oracle 11g

More information about MySQL is available in [MySQL Database Server](#) in [Appendix A, “Teaming System Requirements Assistance,”](#) on page 119.

- ♦ Tomcat 6.0.18

---

**NOTE:** Tomcat 6.0.18 is included with Teaming on Linux and Windows.

---

- ♦ Java\* Developer Kit (JDK\*):

- ♦ Sun\* JDK 5.0 or JDK 6.0
- ♦ IBM\* JDK 5.0 or JDK 6.0

Java scripting must be enabled for proper Teaming site functionality.

More information about JDKs is available in [Java Development Kit](#) in [Appendix A, “Teaming System Requirements Assistance,”](#) on page 119.

- ♦ Directory service:

- ♦ Linux: Novell eDirectory™ 8.8 or later, plus the latest Support Pack

For information about eDirectory, see the [Novell eDirectory 8.8 Documentation Web site](http://www.novell.com/documentation/edir88) (<http://www.novell.com/documentation/edir88>).

- ♦ Windows: Microsoft Active Directory\*, plus the latest Service Pack, or Novell eDirectory 8.8 or later, plus the latest Support Pack

For information about Active Directory, see [Windows Server 2003 Active Directory](http://www.microsoft.com/windowsserver2003/technologies/directory/activedirectory) (<http://www.microsoft.com/windowsserver2003/technologies/directory/activedirectory>) or [Windows Server 2008 Active Directory](http://www.microsoft.com/windowsserver2008/en/us/active-directory.aspx) (<http://www.microsoft.com/windowsserver2008/en/us/active-directory.aspx>).

- ♦ Adequate server disk space:

- ♦ Teaming software: Approximately 250 MB
- ♦ Database server software: Approximately 250 MB
- ♦ Teaming file repository: Depends on the anticipated size of the Teaming site
- ♦ Database content: Substantially less than the Teaming file repository

See [Section 3.5, “Planning the Teaming Database,”](#) on page 29 to plan for the disk space needs of your Teaming site.

---

**NOTE:** Teaming 1.0 was integrated with the Liferay\* portal, but Teaming 2.0 is not. Teaming 2.0 includes its own portal functionality. If you are updating from Teaming 1.0 to Teaming 2.0, the Installation program backs up your existing Liferay data and reconfigures your Teaming site to run without integration with Liferay.

---

## 2.2 Teaming User Requirements

- ♦ Web browser:

- ♦ Linux: Mozilla\* Firefox\* 2.0 or later
- ♦ Windows: Microsoft Internet Explorer\* 6.0 or later; Mozilla Firefox
- ♦ Mac: Safari\* 3 or later; Mozilla Firefox 2.0 or later

- ♦ Office applications:
  - ♦ Linux: OpenOffice.org\* 3.0 or later
  - ♦ Windows: Microsoft Office 2007; OpenOffice.org 3.0 or later
  - ♦ Mac: OpenOffice.org 3.0 or later
- ♦ Collaboration clients:
  - ♦ Linux:
    - ♦ GroupWise® 8
    - ♦ GroupWise Messenger 2, plus the latest Support Pack
  - ♦ Windows:
    - ♦ GroupWise 8
    - ♦ GroupWise Messenger 2, plus the latest Support Pack
    - ♦ Outlook 2007 with iCal support enabled
    - ♦ Notes 7 with iCal support enabled

## 2.3 Supported Environments

- ♦ Section 2.3.1, “File Viewer Support,” on page 19
- ♦ Section 2.3.2, “IPV6 Support,” on page 19
- ♦ Section 2.3.3, “Clustering Support,” on page 20
- ♦ Section 2.3.4, “Xen Virtualization Support,” on page 20
- ♦ Section 2.3.5, “VMware Support,” on page 20
- ♦ Section 2.3.6, “Linux File System Support,” on page 20

### 2.3.1 File Viewer Support

In Kablink Teaming, file viewing capabilities are provided by [OpenOffice.org \(http://www.openoffice.org\)](http://www.openoffice.org) viewer technology. For more information, see:

- ♦ Section 4.1.5, “Configuring the Document Converter on Linux,” on page 51
- ♦ Section 4.2.3, “Configuring the Document Converter on Windows,” on page 55

The file viewers also support data indexing by the Lucene Index Server.

### 2.3.2 IPV6 Support

Kablink Teaming supports the IPV6 protocol when it is available on the server. If it is available, Teaming detects it and supports IPV6 by default, along with IPV4.

### 2.3.3 Clustering Support

You can set up your Kablink Teaming site in any of the following clustering environments:

- ♦ Novell Cluster Services™ on Linux.

For information about Novell Cluster Services on Linux, see the Clustering (High Availability) section of the [Open Enterprise Server 2 SP1 Documentation Web site \(http://www.novell.com/documentation/oes2/cluster-services.html#cluster\)](http://www.novell.com/documentation/oes2/cluster-services.html#cluster).

- ♦ Microsoft Clustering Services in Windows

For more information, see [Windows 2003 Server Cluster \(http://www.microsoft.com/windowsserver2003/enterprise/clustering.mspx\)](http://www.microsoft.com/windowsserver2003/enterprise/clustering.mspx) or [Windows Server 2008 High Availability \(http://www.microsoft.com/windowsserver2008/en/us/high-availability.aspx\)](http://www.microsoft.com/windowsserver2008/en/us/high-availability.aspx).

In addition, you can install Teaming components on multiple servers to provide failover support, as described in [Part III, “Multi-Server Configurations and Clustering,” on page 89](#).

### 2.3.4 Xen Virtualization Support

You can install Kablink Teaming in virtual environments where a software program enables one physical server to function as if it were two or more physical servers. Xen\* virtualization technology in Novell Open Enterprise Server (Linux version) and SUSE Linux Enterprise Server is supported. For more information, see:

- ♦ [Open Enterprise Server 2 Virtualization Documentation Web site \(http://www.novell.com/documentation/oes2/virtualization.html#virtualization\)](http://www.novell.com/documentation/oes2/virtualization.html#virtualization)
- ♦ [SLES Virtualization Technology Documentation Web site \(http://www.novell.com/documentation/vmserver\)](http://www.novell.com/documentation/vmserver).

### 2.3.5 VMware Support

Kablink Teaming is supported on the following versions of VMware\*:

- ♦ VMware Server (formally GSX Server), an enterprise-class virtual infrastructure for x86-based servers
- ♦ VMware ESX Server, a data-center-class virtual infrastructure for mission-critical environments

For more information, see the [VMWare Web site \(http://www.vmware.com\)](http://www.vmware.com).

### 2.3.6 Linux File System Support

For best Kablink Teaming performance on Linux, the `ext3` file system is recommended. If you are running OES Linux and need the feature-rich environment of the NSS file system, Teaming is also supported there. The `reiser3` file system is also supported.

## 2.4 Recommended Hardware Configurations

The hardware configuration that you set up for your Teaming site should be based on the number of active users that the Teaming site must support.

Active Users	Teaming Components	CPU	Memory	Java Heap
10	1 dedicated Teaming server with: <ul style="list-style-type: none"> <li>♦ Tomcat</li> <li>♦ Lucene</li> <li>♦ SQL</li> </ul>	x86	2 GB	1 GB
50	1 dedicated Teaming server with: <ul style="list-style-type: none"> <li>♦ Tomcat</li> <li>♦ Lucene</li> <li>♦ SQL</li> </ul>	x64 dual core	4 GB	2 GB
100	Multiple Teaming servers: <ul style="list-style-type: none"> <li>♦ 1 dedicated Tomcat server</li> <li>♦ 1 or more dedicated SQL servers</li> </ul>	x64 dual core	4 GB	2 GB

Server machines can be physical or virtual.

You can perform a Basic Installation to set up a single-server configuration, as described in [Chapter 3, “Planning a Basic Teaming Installation,” on page 23](#) and [Chapter 4, “Setting Up a Basic Teaming Site,” on page 45](#).

You can perform a Basic Installation to set up a multiple-server configuration, but the remote database must be created manually and in advance of performing the installation, as described in [Part III, “Multi-Server Configurations and Clustering,” on page 89](#).



# Planning a Basic Teaming Installation

# 3

The Kablink® Teaming Installation program helps you install the Teaming software and file repository to the appropriate locations.

- ♦ [Section 3.1, “What Is a Basic Teaming Installation?,” on page 23](#)
- ♦ [Section 3.2, “Selecting the Operating Environment for Your Teaming Server,” on page 24](#)
- ♦ [Section 3.3, “Selecting a Java Development Kit,” on page 26](#)
- ♦ [Section 3.4, “Gathering Network Information for Your Teaming Site,” on page 27](#)
- ♦ [Section 3.5, “Planning the Teaming Database,” on page 29](#)
- ♦ [Section 3.6, “Gathering Outbound E-Mail Information,” on page 32](#)
- ♦ [Section 3.7, “Enabling Inbound E-Mail,” on page 34](#)
- ♦ [Section 3.8, “Planning Site Security,” on page 36](#)
- ♦ [Section 3.9, “Gathering Directory Services Information,” on page 37](#)
- ♦ [Section 3.10, “Accommodating Multiple Languages,” on page 42](#)

## 3.1 What Is a Basic Teaming Installation?

The Kablink Teaming Installation program provides two installation types: Basic and Advanced. When you perform a Basic installation, the result is a fully functional Teaming site with all required options configured and with typical defaults in use for optional settings. This section helps you make informed decisions about the basic required options:

- ♦ Server platform (Linux or Windows)
- ♦ Server architecture (32-bit or 64-bit)
- ♦ Physical server memory requirements
- ♦ File locations (Teaming software and data)
- ♦ Java Development Kit (JDK) version (Sun or IBM)
- ♦ Database type (MySQL, Microsoft SQL Server, or Oracle)
- ♦ Database creation (during installation or before installation)
- ♦ Database authentication (username and password)
- ♦ Network information (Teaming server hostname and ports)
- ♦ Outbound e-mail configuration (SMTP vs. SMTPS, hostname, SMTP port, time zone, authentication)
- ♦ Inbound e-mail configuration (SMTP address, SMTP port, and TLS support)
- ♦ User and group for running the Teaming software (Linux only)

If you are new to Teaming, the easiest way to get started is to perform a Basic installation first, with all Teaming components installed on the same server, then add advanced configuration options to your Teaming site after the Basic installation has been successfully tested. However, experienced

Teaming administrators can choose to perform an Advanced installation immediately, which includes all installation and configuration options, as described in [Part II, “Advanced Installation and Reconfiguration,” on page 73](#).

---

**IMPORTANT:** The following Teaming configurations require that you perform an Advanced installation as your initial installation of the Teaming software:

- ♦ Setting up the Teaming file repository so that some types of files are located outside the Teaming file repository root directory. See [Section 8.2, “Distributing Different Data Types to Different Locations,” on page 75](#) for Advanced installation instructions. You cannot move subdirectories within the Teaming file repository after they have been created.

If you want to implement an Advanced installation option, you should perform a Basic installation first, in a test environment, before performing the Advanced installation to set up your permanent Teaming site.

---

## 3.2 Selecting the Operating Environment for Your Teaming Server

- ♦ [Section 3.2.1, “Teaming Server Platform,” on page 24](#)
- ♦ [Section 3.2.2, “Teaming Server Architecture,” on page 24](#)
- ♦ [Section 3.2.3, “Teaming Server Memory,” on page 24](#)
- ♦ [Section 3.2.4, “Teaming Installation Locations,” on page 26](#)

### 3.2.1 Teaming Server Platform

Kablink Teaming can run on the versions of Linux and Windows listed in [Section 2.1, “Teaming Server Requirements,” on page 17](#).

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Teaming Server Platform*, mark your operating system of choice.

---

### 3.2.2 Teaming Server Architecture

Kablink Teaming can run on 32-bit or 64-bit processors. A 64-bit processor is recommended for a large Teaming site where the processor load will be heavy and data storage will require a large amount of disk space.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Processor Architecture*, mark the processor capacity required for the size of Teaming site that you want to set up.

---

### 3.2.3 Teaming Server Memory

If a 32-bit processor is sufficient for your Kablink Teaming server, the server needs at least 3 GB of memory. If you plan to use a 64-bit processor in your Teaming server, the server needs more.



Teaming server memory usage is significantly affected by some factors and less affected by others:

- ♦ **Number of users logged in:** No significant effect.
- ♦ **Number of concurrent active sessions:** No significant effect.
- ♦ **Database server caches:** Significant memory usage.

When you follow the instructions for a Basic installation, the database is located on the same server as the Teaming software. After you have successfully tested your Basic installation, you can reconfigure Teaming to have its database on a remote server, so that the database uses separate memory resources, as described in [Chapter 12, “Creating the Teaming Database on a Remote Server,” on page 91](#).

- ♦ **Teaming internal data caches:** Significant memory usage.

When you follow the instructions for a Basic installation, the Teaming internal data caches are subdirectories of the `teamingdata` directory, described in [Section 3.2.4, “Teaming Installation Locations,” on page 26](#). The Teaming internal data caches are separate from any caching or memory usage by the database server itself.

- ♦ **Lucene index cache:** Significant memory usage.

The Lucene\* Index Server is a high-performance Java search engine. Large file repositories (particularly with large files or a large number of files) can create a very large data index. When you perform a Basic installation, the Lucene index is created on the same server where the Teaming software is installed.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Memory Requirements*, specify the amount of physical memory you plan to have in your Teaming server.

---

When you perform a Basic installation, the amount of memory allocated to the Java Virtual Machine (JVM\*) where the Teaming software defaults to 1 GB, which is adequate for a medium-sized Teaming site running on a 32-bit server. This memory allocation, called the Java “heap size,” does not include memory used by your database server or by the Lucene Index Server when these programs are running on the same server as the Teaming software.

A general rule is that no more than 75% of the available physical memory should be allocated to the JVM. Memory not allocated to the JVM must be sufficient to support the operating system, the database server, and the Lucene Index Server if they are also running on the Teaming server, and any other processes running on the Teaming server.

---

**IMPORTANT:** A JVM on a 32-bit server should not be configured to take more than 1.5 G of memory. However, large numbers of users and documents often need memory settings higher than 2 GB to provide adequate performance. Such a Teaming system should be set up on 64-bit hardware.

---

---

#### ADVANCED TEAMING INSTALLATION SUMMARY SHEET

---

Under *Java JDK Location*, specify the amount of memory to allocate to the JVM where Teaming runs.

---

Although it is possible to run Kablink Teaming with less than 1 GB of memory for the JVM, this applies only to very small test configurations, and is not suitable for production systems. In a test configuration, 512 MB is the minimum amount of memory required to produce a functioning Teaming installation.

## 3.2.4 Teaming Installation Locations

The default file location for the Kablink Teaming software varies by platform:

Linux:        /opt/novell/teaming

Windows:    c:\Program Files\Novell\Teaming

Included under the main Teaming software directory are subdirectories for Tomcat and file viewer software.

The default file location for the Kablink Teaming file repository also varies by platform:

Linux:        /var/opt/novell/teaming

Windows:    c:\Novell\Teaming

---

**IMPORTANT:** On Windows, the Teaming Installation program displays the Windows pathname using forward slashes (/) rather than the traditional back slashes (\). This syntax is necessary in the Installation program.

---

The Teaming file repository holds all files that are imported into Teaming, information related to the imported files, such as HTML renderings, and the search engine index.

---

### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *File Locations*, specify the directories where you want to install the Teaming software and data if you prefer not to use the default locations.

---

A Basic installation allows you to change the root directory for the Teaming software and the Teaming file repository.

---

**IMPORTANT:** If you want to organize the Teaming file repository so that some file types are not under the Teaming file repository root directory, you must perform an Advanced installation as your initial Teaming installation. You cannot move directories out of the Teaming file repository root directory after the initial installation has been performed. To perform an Advanced installation in order to organize the Teaming file repository to meet your needs, complete the planning steps for a Basic installation and complete the [Basic Teaming Installation Summary Sheet](#), then follow the additional instructions in [Distributing Different Data Types to Different Locations](#).

---

## 3.3 Selecting a Java Development Kit

As listed in [Section 2.1, “Teaming Server Requirements,” on page 17](#), you need to install a Java Development Kit (JDK) before you install Kablink Teaming. You can use either the Sun JDK or the IBM JDK for the platform where you are installing Teaming (Linux or Windows). The Sun JDK is available in 32-bit and 64-bit versions. The IBM JDK is available for 32-bit processors only.

---

### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Java Development Kit*, mark the JDK that you want to use with Teaming.

---

You must install the JDK on the Teaming server before you install the Teaming software. If you are not familiar with installing a JDK, see [Java Development Kit](#) in [Appendix A, “Teaming System Requirements Assistance,”](#) on page 119 for instructions.

---

**BASIC TEAMING INSTALLATION SUMMARY SHEET**

---

Under *Java Development Kit*, specify the directory where you install the JDK.

---

The Teaming Installation program uses this path as if you had set the `JAVA_HOME` environment variable. The path is stored for future reference in the `installer.xml` file so that you have to specify the path to the JDK only once.

## 3.4 Gathering Network Information for Your Teaming Site

When you perform a Basic installation, the Kablink Teaming Installation program needs basic hostname and HTTP port information about the server where you are installing Teaming.

- ♦ [Section 3.4.1, “Hostname,”](#) on page 27
- ♦ [Section 3.4.2, “Port Numbers,”](#) on page 27

### 3.4.1 Hostname

When you install Kablink Teaming, the Teaming installation program needs to know the hostname of the server where you are installing the Teaming software. The default is `localhost`.

---

**IMPORTANT:** To facilitate remote access, specify the actual hostname of the server.

---

---

**BASIC TEAMING INSTALLATION SUMMARY SHEET**

---

Under *Network Information*, specify the hostname to use for the Teaming server.

---

### 3.4.2 Port Numbers

When you install Kablink Teaming, Tomcat is installed along with the Teaming software. Teaming uses Tomcat as a standalone Web server for delivering data to Teaming users in their Web browsers. For more information about Tomcat, see the [Apache Tomcat Web site \(http://tomcat.apache.org\)](http://tomcat.apache.org).

---

**IMPORTANT:** If the server where you want to install Teaming already has a Web server running on it, shut it down while you install and test Teaming. The instructions for a Basic Teaming installation assume that no other Web server is running on the Teaming server. If you want to maintain another Web server on the Teaming server, you are responsible to resolve any port conflicts that might arise.

---

On the command line, use the `netstat` command to see what ports are currently in use on the server where you plan to install Teaming:

Linux:        `netstat -tan`

Windows: `netstat -a -n -p tcp`

Make sure that the port numbers that you specify during Teaming installation do not conflict with ports that are already in use on the server.

- ♦ “HTTP/HTTPS Ports” on page 28
- ♦ “Shutdown Port” on page 28
- ♦ “AJP Port” on page 29

## HTTP/HTTPS Ports

By default, standard Web servers such as Apache and Microsoft Internet Information Server (IIS) use port 80 for non-secure HTTP (Hypertext Transfer Protocol) connections and port 443 for secure HTTPS connections. HTTPS connections use SSL (Secure Sockets Layer) for added security. As a result, Web browsers default to port 80 when no port is specified in a non-secure HTTP URL and to port 443 when no port is specified in a secure HTTPS URL.

Tomcat defaults to port 8080 for non-secure HTTP connections and to port 8443 for secure HTTPS connections, so that it does not conflict with the standard Web server port numbers. If you configure Kablink Teaming with the Tomcat default port numbers, users must include the appropriate port number when providing the Teaming site URL. Typically, users prefer not to do this.

Unfortunately, the situation is not as simple as just configuring Teaming to use the default port numbers of 80 and 443. On Linux, non-`root` processes are not allowed access to port numbers lower than 1024 and you are counseled against running Teaming as `root` in [Section 3.8.2, “Linux User ID for Teaming,” on page 36](#). Also on Linux and Windows, the default Tomcat installation expects ports 8080 and 8443.

For a Basic installation, you can use the default port numbers as presented by the Teaming Installation program:

HTTP port: 80

Secure HTTP port: 443

Listen port: 8080

Secure listen port: 8443

---

### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Network Information*, the default port numbers have been provided for you. You only need to specify different port numbers if you anticipate port conflicts with other software on the Teaming server. Resolving port conflicts is beyond the scope of this Teaming documentation.

---

After you install Teaming on Linux, you need to complete the steps in [“Setting Up Port Forwarding” on page 49](#) so that users are not required to include the port number in the Teaming URL.

## Shutdown Port

By default, Kablink Teaming uses 8005 as its shutdown port. For an explanation of the shutdown port, see [Tomcat - Shutdown Port \(http://www.wellho.net/mouth/837\\_Tomcat-Shutdown-port.html\)](http://www.wellho.net/mouth/837_Tomcat-Shutdown-port.html).

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Network Information*, specify the port you want Teaming to use as its shutdown port if the default of 8005 is already in use on the Teaming server.

---

#### AJP Port

By default, Kablink Teaming uses 8009 as its AJP port. For an explanation of the Apache JServ Protocol port, see *The AJP Connector* (<http://tomcat.apache.org/tomcat-6.0-doc/config/ajp.html>).

---

**IMPORTANT:** If you are installing Teaming on Novell Open Enterprise Server 2, port 8009 is already in use, so you need to select a different port (for example 8010).

---

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Network Information*, specify the port you want Teaming to use as its AJP port if the default of 8009 is already in use on the Teaming server.

---

## 3.5 Planning the Teaming Database

Kablink Teaming database disk space requirements are relatively modest. Files that are imported into Teaming are saved in the Teaming file repository, as described in [Section 3.2.4, “Teaming Installation Locations,”](#) on page 26.

The Teaming database is primarily used for storing:

- ♦ Structural information about workspaces, folders, and entries (for example, their location in the workspace tree)
- ♦ Identification information about workspaces, folders, and entries (for example, titles, descriptions, dates of creation/modification, and users associated with creation/modification)
- ♦ User profile information (for example, full name, phone number, and e-mail address)

You or your database administrator must make the following decisions about the Teaming database:

- ♦ [Section 3.5.1, “Database Type,”](#) on page 29
- ♦ [Section 3.5.2, “Database Setup Method,”](#) on page 30
- ♦ [Section 3.5.3, “Database Location,”](#) on page 30
- ♦ [Section 3.5.4, “Database Credentials,”](#) on page 31
- ♦ [Section 3.5.5, “Database Encryption Algorithm,”](#) on page 32

### 3.5.1 Database Type

By default, Kablink Teaming uses open source MySQL as its database on Linux and on Windows. On Linux, Teaming also supports Oracle. On Windows, Teaming also supports Microsoft SQL Server and Oracle.

---

## BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Database Type*, mark the type of database that you want to use with Teaming.

---

Make sure that a supported version of the database server, as listed in [Section 2.1, “Teaming Server Requirements,” on page 17](#), is installed and running before you install Teaming.

### 3.5.2 Database Setup Method

If you plan to use a MySQL database or a Microsoft SQL database, the Kablink Teaming Installation program can automatically set up the database for you. This is the easiest way to get started.

If you plan to use an Oracle database, you must have your database administrator set up the database for you. Instructions for your database administrator are provided in [Section 12.4, “Creating an Oracle Database,” on page 93](#).

---

## BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Database Setup Method*, mark whether you want the Teaming Installation program to automatically set up a MySQL or Microsoft SQL database, or you need your database administrator to manually set up an Oracle database before you install Teaming.

---

### 3.5.3 Database Location

When you have the Kablink Teaming Installation program create the database for you, the database is created on the same server where you install the Teaming software. This is the preferable location for your Basic installation. The default database name is `sitescape`, a reference to the company that previously developed the Teaming software.

---

Database Server	Default Linux Location	Default Windows Location
MySQL	<code>/var/lib/mysql</code>	<code>c:\Documents and Settings\All Users\Application Data\MySQL\MySQL Server version\Data</code>
Microsoft SQL	N/A	<code>c:\Program Files\Microsoft SQL Server\MSSQL\Data</code>
Oracle	N/A	N/A

---

You can have your database administrator create a database on a remote server later, after you have successfully tested your Basic installation. See [Chapter 12, “Creating the Teaming Database on a Remote Server,” on page 91](#).

If you need to have your database administrator create an Oracle database, you must decide before installation whether you want the database on the Teaming server or on a remote server. See [Section 12.4, “Creating an Oracle Database,” on page 93](#).

Teaming knows where to find its database from the JDBC\* (Java Database Connectivity) URL that you provide during installation. For a database that is local to the Teaming software, the default JDBC URL that provides `localhost` as the hostname of the Teaming server is appropriate. If the database is on a remote server, the JDBC URL must provide the hostname of the remote database server.

The JDBC URL also includes the port number on which Teaming can communicate with the database server. The default port number depends on the database server you are using:

Database Server	Default Port Number
MySQL	3306
Microsoft SQL	1433
Oracle	1521

Use this port number unless it is already in use by another process on the database server.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *JDBC URL*, specify the appropriate hostname for the database server (`localhost` or the hostname of a remote server) and the port number it will use to communicate with Teaming.

---

### 3.5.4 Database Credentials

When you have the Kablink Teaming Installation program create the database for you, it defaults to the following administrator usernames for the database server:

Database	Default Administrative Username
MySQL	<code>root</code>
	<b>IMPORTANT:</b> The MySQL <code>root</code> username is not the same as the Linux <code>root</code> user on a Linux server.
Microsoft SQL	<code>sa</code> (system administrator)
Oracle	(no default)

For an Oracle database, your database administrator establishes the administrator username and password for the database server.

Check with your database administrator to see if the default administrator username is still in use for your database server, and obtain the administrator password for the database server before you run the Teaming Installation program.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Database Credentials*, specify the administrator username and password for the database server so that Teaming can access its database.

---

### 3.5.5 Database Encryption Algorithm

Different encryption algorithms provide differing encryption strength. The supported algorithms for encrypting the Kablink Teaming database password are listed below, in order from least strength to most strength.

- ♦ MD5
- ♦ SHA (default)
- ♦ SHA-256

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Database Encryption Algorithm*, mark the encryption algorithm you want to use for Teaming passwords.

---

## 3.6 Gathering Outbound E-Mail Information

Your Kablink Teaming site can be configured to send outbound e-mail through an existing e-mail system. E-mail from the Teaming site is useful for the following activities:

- ♦ Teaming users can subscribe to e-mail notifications, so that they automatically receive a message whenever a content of interest changes. For more information, see “[Subscribing to a Folder or Entry](#)” in “[Getting Informed](#)” in the *Kablink Teaming 2.0 User Guide*.
- ♦ From the Teaming site, users can send e-mail messages to individual users or to teams. For more information, see “[Sending E-Mail From within Teaming](#)” in “[Connecting With Your Co-Workers](#)” in the *Kablink Teaming 2.0 User Guide*.
- ♦ If your e-mail client is iCal-enabled, appointments created in a Teaming Calendar folder can be sent to your e-mail client for posting in your e-mail client Calendar.

In order for your Teaming site to communicate with your e-mail system, you need to gather the following information about your e-mail system.

- ♦ [Section 3.6.1, “Outbound E-Mail Protocol,” on page 32](#)
- ♦ [Section 3.6.2, “Outbound E-Mail Host,” on page 33](#)
- ♦ [Section 3.6.3, “Outbound E-Mail Authentication,” on page 33](#)
- ♦ [Section 3.6.4, “Outbound E-Mail Send Restriction,” on page 34](#)

After installation, outbound e-mail can be disabled and enabled again on the Teaming site, as described in “[Configuring E-Mail Integration](#)” in “[Site Setup](#)” in the *Kablink Teaming 2.0 Administration Guide*. However, you must configure outbound e-mail in the Teaming Installation program.

### 3.6.1 Outbound E-Mail Protocol

E-mail systems communicate using SMTP (Simple Mail Transfer Protocol). You need to determine whether the e-mail system that you want your Kablink Teaming site to communicate with is using SMTP or SMTPS (secure SMTP).



---

**BASIC TEAMING INSTALLATION SUMMARY SHEET**

---

Under *Outbound E-Mail Protocol*, mark SMTP or SMTPS to match the e-mail system that you want Teaming to communicate with.

---

If the e-mail system requires SMTPS, see “[Securing E-Mail Transfer](#)” in “[Site Security](#)” in the *Kablink Teaming 2.0 Administration Guide*.

## 3.6.2 Outbound E-Mail Host

In order to send messages to your e-mail system, Kablink Teaming needs to know the hostname of your SMTP mail server.

The default SMTP port of 25 is typically appropriate, unless the SMTP mail server requires port 465 or 587 for SMTPS connections.

When the Teaming site sends e-mail notifications for scheduled events, the messages are time-stamped according to the time zone you specify here during installation. This setting allows you to use a time zone for e-mail notifications that is different from the time zone where the server is located. The time zone list is grouped first by continent or region, optionally by country or state, and lastly by city. Some common selections for United States time zones are:

Time Zone	Continent/City
Pacific Time	America/Los Angeles
Mountain Time	America/Denver
Central Time	America/Chicago
Eastern Time	America/New_York

---

---

**BASIC TEAMING INSTALLATION SUMMARY SHEET**

---

Under *Outbound E-Mail Host*, specify the name of the mail host, the SMTP port number it uses, and the time zone for the time stamp you want on scheduled event notifications.

---

## 3.6.3 Outbound E-Mail Authentication

Many SMTP mail hosts require a valid e-mail address before they establish the SMTP connection. Some e-mail systems can construct a valid e-mail address if you specify only a valid username. Other e-mail systems require that you specify the full e-mail address for successful authentication.

Some e-mail systems also require a password. Some do not.

---

**BASIC TEAMING INSTALLATION SUMMARY SHEET**

---

Under *Outbound E-Mail Authentication*, indicate whether or not authentication is required for the Teaming site to communicate with your e-mail system, and if so, specify the username or e-mail address, and if necessary, the password for the e-mail account.

---

### 3.6.4 Outbound E-Mail Send Restriction

By default, the Kablink Teaming site allows Teaming users to send messages to all Teaming users using the All Users group on the Teaming site. On a very large Teaming site, this generates a very large number of e-mail messages. If desired, you can prevent messages from being sent to the All Users group.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Allow Sending E-Mail to All Users*, mark whether or not you want users to be able to send messages to the All Users group.

---

## 3.7 Enabling Inbound E-Mail

You can configure your Kablink Teaming site so that users can post comments by e-mailing them to the folder where they want to post the comment. In order to receive e-mail postings, folders must be properly configured, as described in “[Enabling Folders to Receive Entries through E-Mail](#)” in “[Managing Folders](#)” in the *Kablink Teaming 2.0 Advanced User Guide*. Also, users must know the e-mail address of the folder where they want to post their comment.

- ♦ [Section 3.7.1, “Internal Mail Host for Inbound E-Mail,” on page 34](#)
- ♦ [Section 3.7.2, “Inbound E-Mail Port Number,” on page 34](#)
- ♦ [Section 3.7.3, “Inbound E-Mail IP Address,” on page 35](#)
- ♦ [Section 3.7.4, “Inbound E-Mail Security,” on page 35](#)

After installation, inbound e-mail can be disabled and enabled again on the Teaming site, as described in “[Disabling/Enabling Inbound E-Mail Postings](#)” in “[Site Setup](#)” in the *Kablink Teaming 2.0 Administration Guide*. However, you must configure inbound e-mail in the Teaming Installation program.

### 3.7.1 Internal Mail Host for Inbound E-Mail

Inbound e-mail is disabled by default. When you enable it, the Kablink Teaming site starts an internal SMTP mail host to receive incoming messages and post them to the folders associated with the e-mail addresses to which the messages are addressed. By default, the internal SMTP mail host uses port 2525, so that it does not conflict with another mail host that might be running on the Teaming server.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Inbound E-Mail Configuration*, mark whether or not you want users to be able to post to the Teaming site from their e-mail clients.

---

### 3.7.2 Inbound E-Mail Port Number

Selecting the port number for the Kablink Teaming internal SMTP mail host presents the same issue that needs to be dealt with for the HTTP port numbers, as described in “[HTTP/HTTPS Ports](#)” on [page 28](#). You might want to configure the Teaming internal SMTP mail host to use the standard SMTP port of 25. How you handle the issue depends on whether you are installing on Linux or on Windows.

- Linux: Keep the default port number (2525) in the Teaming Installation program, then complete the steps in [Section 4.1.4, “Setting Up Port Forwarding,” on page 49](#) so that requests incoming on port 25 are forwarded to port 2525.
- Windows: Specify port 25 for incoming e-mail in the Teaming Installation program.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Inbound E-Mail Configuration*, specify the port number for the Teaming internal SMTP host to listen on.

---

### 3.7.3 Inbound E-Mail IP Address

If you want to install Kablink Teaming on a server where an SMTP mail host is already running, you can do so if the server has multiple IP addresses. The existing SMTP mail host can use port 25 on one IP address and Teaming can use port 25 on another IP address. During installation, you only need to specify an IP address if the server has multiple IP addresses and you want Teaming to bind to a specific IP address rather than all of them.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Inbound E-Mail Configuration*, specify the IP address for the Teaming internal SMTP host to listen on, if you are installing Teaming on a server with multiple IP addresses and you want Teaming to bind to just one of them.

---

### 3.7.4 Inbound E-Mail Security

You can choose whether the Kablink Teaming internal mail host uses TLS (Transport Layer Security) when it communicates with other SMTP mail hosts. In order for TLS to function properly, you must have a certificate on the Teaming server, as described in “[Securing E-Mail Transfer](#)” in “[Site Security](#)” in the *Kablink Teaming 2.0 Administration Guide*. When an SMTP mail host queries the Teaming mail host, the Teaming mail host communicates its ability or inability to handle TLS. The other SMTP mail host then communicates appropriately, taking into account how the Teaming internal mail host is configured. The default is to use TLS, because this provides more secure communication between mail hosts.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Inbound E-Mail Configuration*, mark whether or not you want the Teaming server to announce that it can use TLS.

---

You can install Teaming with *Announce TLS* selected, and then set up the certificate afterwards. However, if you select *Announce TLS*, inbound e-mail does not work until the certificate is available on the Teaming server.

## 3.8 Planning Site Security

- ♦ [Section 3.8.1, “Teaming Site Administrator Password,” on page 36](#)
- ♦ [Section 3.8.2, “Linux User ID for Teaming,” on page 36](#)

### 3.8.1 Teaming Site Administrator Password

When you first log in to the Kablink Teaming site, you use `Admin` as the Teaming administrator username and `admin` as the password. You should immediately change the password to one of your own choosing.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Teaming Administrator Credentials*, specify the password that you want to use whenever you log in as the Teaming site administrator.

---

### 3.8.2 Linux User ID for Teaming

For optimum security, Kablink Teaming should not run as the Linux `root` user. For example, if an intruder manages to assume the identity of the Teaming program, the intruder gains all the privileges of the commandeered process. If the process is running with `root` user privileges, the intruder has `root` access to your system. If the process is running as a user with minimal privileges, the intruder has only restricted access to your system. Therefore, your system is more secure if the Teaming program does not run as `root`. For example, you might want to create a user named `teamingadmin` for the Teaming program to run as. Linux users require a full name and a password.

In addition to creating a Linux user for the Teaming program to run as, you can also create a Linux group for that user to belong to. This enables the Teaming program to create directories and files with consistent ownership and permissions. For example, you might want to create a group named `teamingadmin` for the `teamingadmin` user to belong to. Groups do not require passwords.

As an alternative to creating a custom Linux username and group for Teaming, you can use the existing `wwwrun` username and the `www` group. This account is typically used to start Web server processes.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Linux Username and Group*, specify the non-`root` Linux username and group name to use for running the Teaming program. If you are creating a new Linux user, specify its full name and password.

---

---

**IMPORTANT:** The non-`root` Linux username and group must exist before you start the Teaming Installation program. Instructions for creating the username and group are provided in [Section 4.1.1, “Performing Pre-Installation Tasks on Linux,” on page 45](#).

---

## 3.9 Gathering Directory Services Information

Unless you are planning a very small Kablink Teaming site, the most efficient way to create Teaming users is to synchronize initial user information from your network directory service (Novell eDirectory, Microsoft Active Directory, or other LDAP directory service) after you have installed the Teaming software. Over time, you can continue to synchronize user information from the LDAP directory to your Teaming site.

- ♦ [Section 3.9.1, “LDAP Directory Service,” on page 37](#)
- ♦ [Section 3.9.2, “LDAP Connections,” on page 37](#)
- ♦ [Section 3.9.3, “LDAP Synchronization Options,” on page 40](#)

---

**IMPORTANT:** Teaming performs one-way synchronization from the LDAP directory to your Teaming site. If you change user information on the Teaming site, the changes are not synchronized back to your LDAP directory.

---

### 3.9.1 LDAP Directory Service

You can synchronize initial Kablink Teaming user information from any LDAP directory. This guide provides instructions for synchronizing user information from eDirectory and Active Directory. If you are using another LDAP directory, the instructions provide guidelines for the tasks you need to perform.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *LDAP Directory Service*, mark the LDAP directory service from which you want to synchronize Teaming user information.

---

### 3.9.2 LDAP Connections

You can configure one or more LDAP connections. Each connection requires the following configuration information:

- ♦ [“LDAP Server” on page 37](#)
- ♦ [“User Attribute” on page 38](#)
- ♦ [“User and Group Object Locations” on page 38](#)

#### LDAP Server

In order to synchronize initial user information, Kablink Teaming needs to access an LDAP server where your directory service is running. You need to provide the hostname of the server using a URL of the following format:

```
ldap://hostname
```

If the LDAP server requires a secure SSL connection, use the following format:

```
ldaps://hostname
```

If the LDAP server is configured with a default port number (389 for non-secure connections or 636 for secure SSL connections), you do not need to include the port number in the URL. If the LDAP server uses a different port number, use the following format for the LDAP URL:

```
ldap://hostname:port_number
ldaps://hostname:port_number
```

In addition, Teaming needs the username and password of a user on the LDAP server who has sufficient rights to access the user information stored there. You need to provide the username, along with its context in your LDAP directory tree, in the format expected by your directory service.

Directory Service	Format for Username
eDirectory	<code>cn=username,ou=organizational_unit,o=organization</code>
Active Directory	<code>cn=username,ou=organizational_unit,dc=domain_component</code>

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *LDAP Server*, specify the LDAP URL of the server, a fully qualified username with sufficient rights to read the user information, and the password for that user.

---

If the LDAP server requires a secure SSL connection, additional setup is required. You need to complete the steps in “[Securing LDAP Synchronization](#)” in “[Site Security](#)” in the *Kablink Teaming 2.0 Administration Guide* to create a public-key certificate for the Teaming server.

### User Attribute

LDAP directories differ in the LDAP attribute used to identify a User object. eDirectory and Active Directory both use the `cn` (common name) attribute. Other LDAP directories might use the `uid` (unique ID) attribute. Kablink Teaming needs to know which attribute to look for in order to find User objects.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *LDAP User Attribute*, mark `cn` or `uid`, based on the convention used by your LDAP directory service for User objects.

---

Teaming calls the User object attribute `screenName`, so when you configure LDAP synchronization, you map `screenName` to either `cn` or `uid`.

As needed, other LDAP attributes can be used for logging in to the Teaming site, as long as the attribute is unique for each User object. For example, the `mail` LDAP attribute on User objects could be used to enable Teaming users to log in to the Teaming site using their e-mail addresses.

### User and Group Object Locations

Kablink Teaming can find and synchronize initial user information from User objects located in one or more containers in the LDAP directory tree. A container under which User objects are located is called a base DN (distinguished name). The format you use to specify a base DN depends on your directory service.

Directory Service	Format for the User Container
eDirectory	<i>ou=organizational_unit,o=organization</i>
Active Directory	<i>ou=organizational_unit,dc=domain_component</i>

To identify potential Teaming users, Teaming by default filters on the following LDAP directory object attributes:

- ♦ Person
- ♦ orgPerson
- ♦ inetOrgPerson

If you want to create Teaming groups based on information in your LDAP directory, Teaming filters on the following LDAP directory object attributes:

- ♦ group
- ♦ groupOfNames
- ♦ groupOfUniqueNames

You can add attributes to the user or group filter list if necessary. You can use the following operators in the filter:

- ♦ | OR (the default)
- ♦ & AND
- ♦ ! NOT

You can choose whether you want Teaming to search for users (and optionally, groups) in containers underneath the base DN (that is, in subtrees).

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *LDAP User Context*, specify a base DN, along with object attributes if any, and mark whether you want subtrees searched for Teaming users.

Under *LDAP Group Context*, specify a base DN, along with object attributes if any, and mark whether you want subtrees searched for Teaming groups.

---

You might find it convenient to create a group that consists of all the users that you want to set up in Teaming, regardless of where they are located in your LDAP directory. After you create the group, you can use the following filter to search for User objects that have the specified group membership attribute:

```
(groupMembership=cn=group_name,ou=organizational_unit,o=organization)
```

---

**IMPORTANT:** Be sure to include the parentheses in your filter.

---

### 3.9.3 LDAP Synchronization Options

The following synchronization options apply to all LDAP configurations within the same Kablink Teaming zone:

- ♦ “Synchronization Schedule” on page 40
- ♦ “User Synchronization Options” on page 40
- ♦ “Group Synchronization Options” on page 41

---

**NOTE:** Because the synchronization options apply to all LDAP configurations within the same zone, you cannot have customized synchronization settings for each LDAP configuration. A Novell Teaming site can have multiple zones. A Kablink Teaming site has one zone.

---

#### Synchronization Schedule

When you enable LDAP synchronization, you can set up a schedule for when it is convenient for synchronization to occur. In planning the schedule, take into account how often your LDAP directory user (and, optionally, group) information changes and the server resources required to perform the synchronization for the number of users (and, optionally, groups) that you have.

You can choose to have LDAP synchronization performed every day (for example, on Saturday), or you can select specific days of the week when you want it performed (for example, on Monday, Wednesday, and Friday). You can choose to have it performed once a day at a specified time (for example, at 2:00 a.m.), or you can set a time interval, so that it is performed multiple times each day (for example, every four hours). The smallest time interval you can set is .25 hours (every 15 minutes).

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Synchronization Schedule*, record the schedule for when you want LDAP synchronization to take place.

---

#### User Synchronization Options

The following options are available for enabling and configuring user synchronization from your LDAP directory to your Kablink Teaming site:

- ♦ **Synchronize User Profiles:** Select this option to synchronize the following user information from the LDAP directory into Teaming and to continue to synchronize it whenever the LDAP directory information changes:
  - ♦ First name
  - ♦ Last name
  - ♦ Phone number
  - ♦ E-mail address
  - ♦ Description

If you do not select this option, you must create Teaming users manually, as described in [Section 5.2, “Creating a User,” on page 60](#).



- ♦ **Register LDAP User Profiles Automatically:** Select this option to automatically add LDAP users to the Teaming site. However, workspaces are not created until users log into the Teaming site for the first time.
- ♦ **Delete Users That Are Not in LDAP:** Select this option to delete users that exist on the Teaming site but do not exist in your LDAP directory. Use this option under the following conditions:
  - ♦ You have deleted users from your LDAP directory and you want the LDAP synchronization process to delete them from Teaming as well.
  - ♦ In addition to the users synchronized from LDAP, you create some Teaming users manually, as described in [Section 5.2, “Creating a User,” on page 60](#), and you want the LDAP synchronization process to delete the manually created users.
  - ♦ In addition to the users synchronized from LDAP, you allow Guest users to self-register, as described in [“Allowing Guest Access to Your Teaming Site” in “Site Setup” in the \*Kablink Teaming 2.0 Administration Guide\*](#), and you want the LDAP synchronization process to delete the self-registered users.
- ♦ **When Deleting Users, Delete Associated User Workspaces and Content:** Select this option to remove obsolete information along with the user accounts.
- ♦ **Time Zone for New Users** Select this option to set the time zone for user accounts that are synchronized from the LDAP directory into your Teaming site. The time zone list is grouped first by continent or region, optionally by country or state, and lastly by city. Some common selections for United States time zones are:

Time Zone	Continent/City
Pacific Time	America/Los Angeles
Mountain Time	America/Denver
Central Time	America/Chicago
Eastern Time	America/New_York

---

## BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *LDAP User Options*, mark the synchronization options you want to use.

---

### Group Synchronization Options

The following options are available for enabling and configuring user and group synchronization from your LDAP directory to your Kablink Teaming site:

- ♦ **Synchronize Group Profiles:** Select this option to synchronize group information, such as the group description, to the Teaming site whenever this information changes in LDAP.
- ♦ **Register LDAP Group Profiles Automatically:** Select this option to automatically add LDAP groups to the Teaming site.
- ♦ **Synchronize Group Membership:** Select this option so that the Teaming group includes the same users (and possibly groups) as the group in your LDAP directory. If you do not select this option, when you make changes to group membership in the LDAP directory, the changes are not reflected on your Teaming site.

- ♦ **Delete Local Groups That Are Not in LDAP:** Select this option to delete groups that exist on the Teaming site but do not exist in your LDAP directory. Use this option under the following conditions:
  - ♦ You have deleted groups from your LDAP directory and you want the LDAP synchronization process to delete them from Teaming as well.
  - ♦ In addition to the groups synchronized from LDAP, you create some Teaming groups manually, as described in “[Creating Groups of Users](#)” in “[Site Setup](#)”, in the *Kablink Teaming 2.0 Administration Guide*, and you want the LDAP synchronization process to delete the manually created groups.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *LDAP Group Options*, mark the synchronization options you want to use.

---

## 3.10 Accommodating Multiple Languages

The Kablink Teaming Installation program runs in English only. When you install the Teaming software, you can choose to have the primary language of the Teaming site to be any of the following languages:

- ♦ Chinese-Simplified
- ♦ Chinese Traditional
- ♦ Danish
- ♦ Dutch
- ♦ English
- ♦ French
- ♦ German
- ♦ Hungarian
- ♦ Italian
- ♦ Japanese
- ♦ Polish
- ♦ Portuguese
- ♦ Russian
- ♦ Spanish
- ♦ Swedish

Some languages have an additional distinction by locale (the country where the language is spoken).

The language you select during installation establishes the language of the global text that displays in locations where all Teaming users see it, such as in the workspace tree above the Workspace toolbar:



The language you select also establishes the default interface language and locale for creating new workspaces.

---

**BASIC TEAMING INSTALLATION SUMMARY SHEET**

---

Under *Default Locale*, mark the default language and specify the default country for your Teaming site.

---

Additional language customization can be done after installation, as described in “[Managing a Multi-Language Teaming Site](#)” in “[Site Setup](#)” in the *Kablink Teaming 2.0 Administration Guide*



# Setting Up a Basic Teaming Site

# 4

Follow the setup instructions for the platform where you are installing the Kablink® Teaming software:

- ♦ [Section 4.1, “Linux: Setting Up a Basic Teaming Site,” on page 45](#)
- ♦ [Section 4.2, “Windows: Setting Up a Basic Teaming Site,” on page 53](#)

## 4.1 Linux: Setting Up a Basic Teaming Site

You should already have reviewed [Chapter 3, “Planning a Basic Teaming Installation,” on page 23](#) and filled out the [Basic Teaming Installation Summary Sheet](#). The following sections step you through the process of installing and starting Kablink Teaming on Linux.

- ♦ [Section 4.1.1, “Performing Pre-Installation Tasks on Linux,” on page 45](#)
- ♦ [Section 4.1.2, “Running the Linux Teaming Installation Program,” on page 46](#)
- ♦ [Section 4.1.3, “Configuring Teaming to Start Automatically on Reboot,” on page 49](#)
- ♦ [Section 4.1.4, “Setting Up Port Forwarding,” on page 49](#)
- ♦ [Section 4.1.5, “Configuring the Document Converter on Linux,” on page 51](#)
- ♦ [Section 4.1.6, “Starting Teaming on Linux,” on page 52](#)
- ♦ [Section 4.1.7, “Checking the Status of the Teaming Server,” on page 52](#)
- ♦ [Section 4.1.8, “Restarting Teaming,” on page 52](#)
- ♦ [Section 4.1.9, “Stopping Teaming,” on page 53](#)
- ♦ [Section 4.1.10, “Uninstalling Teaming,” on page 53](#)

### 4.1.1 Performing Pre-Installation Tasks on Linux

- 1 Make sure that the Linux server where you plan to install Teaming meets the system requirements listed in [Section 2.1, “Teaming Server Requirements,” on page 17](#).
- 2 In a terminal window, become `root` by entering `su -` and the `root` password.
- 3 Set the Linux open file limit to meet the needs of the Teaming software:
  - 3a Open the `/etc/security/limits.conf` file in an ASCII text editor.
  - 3b Add the following lines to the bottom of the list, following the format of the example lines:

```
*      hard    nofile    65535
*      soft    nofile    4096
```
  - 3c Save the file, then exit the text editor.
- 4 Perform the following conditional tasks if needed:
  - ♦ [“Stopping and Disabling an Existing Web Server” on page 46](#)
  - ♦ [“Creating a Teaming User and Group” on page 46](#)

## Stopping and Disabling an Existing Web Server

For example, to stop the Apache Web server and its associated instance of Tomcat:

- 1 Enter the following commands to stop Apache and Tomcat:  

```
/etc/init.d/tomcat5 stop  
/etc/init.d/apache2 stop
```
- 2 Enter the following commands to make sure that Apache and Tomcat do not start again when you reboot the server:  

```
chkconfig --del apache2  
chkconfig --del tomcat5
```

## Creating a Teaming User and Group

If the user and group that you want to use for Teaming, as described in [Section 3.8.2, “Linux User ID for Teaming,” on page 36](#) do not exist yet, create them. It is easier if you create the group first.

- 1 Create the Linux group that you want to own the Teaming software and data store directories:
  - 1a In YaST, click *Security and Users > User Management* to display the User and Group Administration page.
  - 1b Click *Groups*, then click *Add*.
  - 1c Specify the group name, then click *Accept* or *OK*.  
The group does not need a password.
- 2 Create the Linux user that you want Teaming to run as:
  - 2a Click *Users*, then click *Add*.
  - 2b On the *User Data* tab, specify the user’s full name, username, and password, then select *Disable User Login*.  
Like any Linux system user, the Teaming Linux user does not need to manually log in. The Teaming Linux user does not need a password, either, but YaST requires you to provide one.
  - 2c Click the *Details* tab.
  - 2d In the *Login Shell* drop-down list, select */bin/false*, because this user does not need to manually log in.
  - 2e In the *Default Group* drop-down list, select the Linux group that you created in [Step 1](#).
  - 2f In the *Groups* list, select the Linux group that you created in [Step 1](#).
  - 2g Click *Accept* or *OK*.
- 3 Exit YaST.

### 4.1.2 Running the Linux Teaming Installation Program


When you run the Kablink Teaming Installation program for the first time, you typically want to use the GUI interface. However, if you are installing Teaming on a server where the X Window System\* is not available, a text-based Installation program is also available. After you are familiar with the Teaming installation process, you can use a silent installation to automate the process.

- ♦ [“Using the GUI Installation Program” on page 47](#)


- ♦ “Using the Text-Based Installation Program” on page 48
- ♦ “Performing a Silent Installation” on page 48

## Using the GUI Installation Program

- 1 In a terminal window, enter `su -` to become the `root` user, then enter the `root` password.  
You need `root` permissions in order to install the Teaming software, but you should not run the Teaming software as `root`.
- 2 Change to the directory where you downloaded and extracted the Teaming software.
- 3 Enter the following command to start the Teaming Installation program:  
`./installer-teaming.linux`
- 4 Accept the License Agreement, then click *Next*.



- 5 Click *Next* to accept the default of *New installation*.



- 6 Click *Next* to accept the default of *Basic*.
- 7 Use the information that you have gathered on the **Basic Teaming Installation Summary Sheet** to provide the information that the Teaming Installation program prompts you for:

Installation Locations

Default Locale for Kablink Teaming

User ID for Kablink Teaming

Network Information

Database Selection

Database Type

JDBC URL

Credentials

Setup

Encryption Algorithm

Java JDK Location

Outbound E-Mail Configuration

Protocol

Host, Port, and Time Zone  
Username, Password, and Authentication  
Allow Sending E-Mail to All Users  
Inbound E-Mail Configuration

The Installation program stores the information it gathers in the `installer.xml` file in the same directory where you started the Installation program.

- 8 After you have provided all the requested information, click *Install* to begin the Teaming installation.
- 9 When the installation is completed, click *Finish* to exit the Teaming Installation program.  
Information about the installation process is written to the `installer.log` file in the same directory where you ran the Installation program. If a problem arises during the installation, the `installer.log` file provides information that can help you resolve the problem.
- 10 Continue with [Section 4.1.3, “Configuring Teaming to Start Automatically on Reboot,”](#) on [page 49](#).

## Using the Text-Based Installation Program

If you try to start the GUI Teaming Installation program in an environment where the X Windows System is not running, the text-based Teaming Installation program starts instead.

If you want to use the text-based Installation program in an environment where it is starting with a GUI by default, use the following command in the directory where the Installation program is located:

```
./installer-teaming.linux --text
```

The text-based Installation program gathers the same configuration information as the GUI Installation program does. This information is stored in the `installer.xml` file in the directory where you run the Installation program.

The Installation program does not write the information it gathers into the `installer.xml` file until you exit the Installation program, and you cannot back up when using the text-based Installation program. Therefore, when you use the text-based Installation program, you should plan your installation carefully in advance, using the [Basic Teaming Installation Summary Sheet](#) or the [Advanced Teaming Installation Summary Sheet](#). If you make a mistake during the installation, continue to the end of the installation process and exit the Installation program normally, so that all information is saved. Then run the text-based Installation program again. Your previous information is supplied as defaults and you can change the information as needed.

## Performing a Silent Installation

If your Kablink Teaming system expands beyond one server, you might need to repeatedly install the same Teaming components. A silent installation makes this an easy process. Edit an existing `installer.xml` file so that it has the hostname of the server where you want to perform the silent installation and copy it to that server. In the directory where the Installation program is located, use the appropriate command to run the Teaming installation program, depending on the action that you want the silent installation to perform:

```
./installer-teaming.linux --silent install  
./installer-teaming.linux --silent update  
./installer-teaming.linux --silent reconfigure
```



The Installation program obtains all the information it needs from the `installer.xml` file and completes the installation without user interaction.

### 4.1.3 Configuring Teaming to Start Automatically on Reboot

You can configure Kablink Teaming to start automatically each time you reboot the Linux server.

- 1 As the Linux `root` user, enter the following command:

```
chkconfig --add teaming
```

- 2 To verify that automatic startup is turned on, enter the following command:

```
chkconfig teaming
```

### 4.1.4 Setting Up Port Forwarding

In order to make Kablink Teaming available on the default HTTP/HTTPS ports of 80 and 443, you must set up port forwarding in order to forward the browser default ports (80 and 443) to the Teaming server ports (8080 and 8443). In addition, you must set up port forwarding if you want to forward the default SMTP mail host port (25) to the default Teaming internal mail host port (2525).

You can set up port forwarding in one of two ways, depending on whether or not you are using the Teaming server as a firewall.

- ♦ [“Using the SuSEfirewall2 File” on page 49](#)
- ♦ [“Using iptables Commands” on page 50](#)

#### Using the SuSEfirewall2 File

To enable port forwarding on a SUSE Linux server that leverages `SuSEfirewall12`:

- 1 As the Linux `root` user, open the following file:

```
/etc/sysconfig/SuSEfirewall12
```

- 2 Find the following line:

```
FW_REDIRECT=""
```

- 3 Between the quotation marks, copy and insert the following string:

```
0/0,ip_address,tcp,80,8080 0/0,ip_address,tcp,443,8443
                                0/
0,ip_address,tcp,25,2525
```

- 4 Replace `ip_address` with the IP address of the Teaming server.

- 5 Save the `SuSEfirewall12` file, then exit the text editor.

- 6 Use the following command to restart the firewall:

```
/sbin/SuSEfirewall12 start
```

- 7 Use the following command to verify that the default browser ports (80 and 443) have been forwarded to the Teaming server ports (8080 and 8443) and that the default SMTP mail host port (25) has been forwarded to the Teaming internal mail host:

```
iptables-save | grep REDIRECT
```

Now, users do not need to include a port number in the Teaming site URL.

## Using iptables Commands

To leverage iptables commands to enable port forwarding on any type of Linux server:

- 1 As the Linux root user, change to the `/etc/init.d` directory.
- 2 In a text editor, create a new file for a set of iptables commands, for example:

```
gedit teaming-iptables
```

- 3 Copy and paste the following lines into the `teaming-iptables` file:

```
iptables -t nat -A OUTPUT -d localhost -p tcp --dport 80
-j REDIRECT --to-ports 8080

iptables -t nat -A OUTPUT -d hostname -p tcp --dport 80
-j REDIRECT --to-ports 8080

iptables -t nat -A PREROUTING -d hostname -p tcp --dport 80
-j REDIRECT --to-ports 8080

iptables -t nat -A OUTPUT -d localhost -p tcp --dport 443
-j REDIRECT --to-ports 8443

iptables -t nat -A OUTPUT -d hostname -p tcp --dport 443
-j REDIRECT --to-ports 8443

iptables -t nat -A PREROUTING -d hostname -p tcp --dport 443
-j REDIRECT --to-ports 8443

iptables -t nat -A OUTPUT -d localhost -p tcp --dport 25
-j REDIRECT --to-ports 2525

iptables -t nat -A OUTPUT -d hostname -p tcp --dport 25
-j REDIRECT --to-ports 2525

iptables -t nat -A PREROUTING -d hostname -p tcp --dport 25
-j REDIRECT --to-ports 2525
```

In this example, the lines are wrapped for readability. When you paste them into the text editor, if the lines are still wrapped, remove the hard returns from the middle of the commands, so that you have six iptables commands, each on its own line.

- 4 Replace `hostname` with the hostname of the Teaming server.
- 5 Save the `teaming-iptables` file, then exit the text editor.
- 6 Use the following command to make the file executable:

```
chmod +x teaming-iptables
```

- 7 Restart the firewall to put the iptables commands into effect:

**7a** Click *Security and Users > Firewall*.

**7b** Click *Stop Firewall Now*, click *Start Firewall Now*, then click *Next > Accept*.

**7c** Exit YaST, then return to the terminal window where you are logged in as root.

- 8 Use the following command to verify that the default browser ports (80 and 443) have been forwarded to the Teaming server ports (8080 and 8443) and that the default SMTP mail host port (25) has been forwarded to the Teaming internal mail host:

```
iptables-save | grep REDIRECT
```

Now, users do not need to include a port number in the Teaming site URL.

## 4.1.5 Configuring the Document Converter on Linux

Kablink Teaming uses OpenOffice.org converters to prepare documents for indexing by the Lucene Index Server. The OpenOffice.org converters are also used on the Teaming site for viewing documents (by converting them to HTML).

- ♦ “Installing OpenOffice.org as the Document Converter for Teaming” on page 51
- ♦ “Running OpenOffice.org as the Document Converter for Teaming” on page 51

### Installing OpenOffice.org as the Document Converter for Teaming

- 1 Download the OpenOffice.org software for Linux from [OpenOffice.org \(http://www.openoffice.org\)](http://www.openoffice.org) to a convenient temporary location on the Teaming server.
- 2 Extract the contents of the downloaded file, then change to the subdirectory into which the software files have been extracted.
- 3 Run the OpenOffice.org Installation program.  
`./setup`
- 4 Click *Next* to begin the installation.
- 5 Select *Custom*, then click *Next*.
- 6 Click the blue down-arrow to select all optional components for installation, then click *Next*.  
This includes the OpenOffice.org Java Runtime Environment (JRE\*) and other components required for document conversion.
- 7 Click *Install Now*.  
The OpenOffice.org software is installed to:  
`/opt/openoffice.org3`
- 8 Click *Finish*.
- 9 Continue with [Running OpenOffice.org as the Document Converter for Teaming](#).

### Running OpenOffice.org as the Document Converter for Teaming

OpenOffice.org must be running as a daemon process on the Teaming server in order for indexing and viewing to take place for Teaming users.

- 1 Use the following command to start the OpenOffice.org converters:  

```
soffice "-accept=socket,host=localhost,port=8100;urp;
StarOffice.ServiceManager" -nologo -
headless
```

---

**IMPORTANT:** Execute the command as a Linux user that has full permissions to the Teaming file repository.

---

- 2 Use the following command to verify that OpenOffice.org is running as a daemon:  
`ps -eaf | grep soffice`

- 3 Test HTML conversion on your Teaming site by viewing a document that has been added as a File Entry in your Teaming site.
- 4 Configure the Teaming server so that OpenOffice.org is always running as a daemon whenever Teaming is running.

### 4.1.6 Starting Teaming on Linux

The Kablink Teaming Installation program created a `teaming` startup script in the `/etc/init.d` directory.

- 1 In a terminal window, enter the following command:

```
/etc/init.d/teaming start
```

---

**IMPORTANT:** Do not run Teaming as the Linux `root` user.

---

You should see output similar to the following example:

```
Using CATALINA_BASE:    /opt/teaming/apache-tomcat-6.0.18
Using CATALINA_HOME:    /opt/teaming/apache-tomcat-6.0.18
Using CATALINA_TMPDIR:  /opt/teaming/apache-tomcat-6.0.1/temp
Using JRE_HOME:         /use/java/jdk1.5.0_17/jre
```

- 2 To make sure that Teaming is ready for work:

- 2a Change to the following directory:

```
/opt/novell/teaming/apache-tomcat-version/logs
```

where *version* is the version number of Tomcat that was installed along with Teaming (for example, 6.0.18)

- 2b Enter the following command to display the end of the Tomcat log:

```
tail --f catalina.out
```

At the end of the log file listing, you should see:

```
INFO: Server startup in nnnn ms
```

- 3 Press `Ctrl+C` when you are finished viewing the end of the `catalina.out` file.

### 4.1.7 Checking the Status of the Teaming Server

You can see if Kablink Teaming is running by checking for its process ID (PID).

- 1 In a terminal window, enter the following command:

```
ps -eaf | grep teaming
```

You should see the Teaming PID number, along with a listing of configuration settings.

### 4.1.8 Restarting Teaming

You need to restart Kablink Teaming whenever you use the Teaming Installation program to make configuration changes, as described in [Chapter 9, “Performing an Advanced Teaming Installation,” on page 83](#).

- 1 In a terminal window, enter the following command:

```
/etc/init.d/teaming restart
```

You should see the same output as when you originally started Teaming.

### 4.1.9 Stopping Teaming

- 1 In a terminal window, enter the following command:

```
/etc/init.d/teaming stop
```

You should see the same output as when you started Teaming.

- 2 To verify that Teaming has stopped, check for its PID number:

```
ps -eaf | grep teaming
```

The Teaming PID number, along with a listing of configuration settings, should no longer be displayed.

### 4.1.10 Uninstalling Teaming

If you move the Kablink Teaming site to a different server, you can delete the Teaming files from the original server to reclaim disk space. The default Teaming file locations are:

Teaming Software	/opt/novell/teaming
Teaming File Repository	/var/opt/novell/teaming
MySQL Database	/var/lib/mysql

For a complete list of your Teaming files, check the `installer.xml` file in the directory where you originally ran the Teaming Installation program.

## 4.2 Windows: Setting Up a Basic Teaming Site

You should already have reviewed [Chapter 3, “Planning a Basic Teaming Installation,” on page 23](#) and filled out the [Basic Teaming Installation Summary Sheet](#). The following sections step you through the process of installing and starting Kablink Teaming on Windows.

- ♦ [Section 4.2.1, “Performing Pre-Installation Tasks on Windows,” on page 53](#)
- ♦ [Section 4.2.2, “Running the Windows Teaming Installation Program,” on page 54](#)
- ♦ [Section 4.2.3, “Configuring the Document Converter on Windows,” on page 55](#)
- ♦ [Section 4.2.4, “Running Teaming as a Windows Service,” on page 57](#)
- ♦ [Section 4.2.5, “Running Teaming as a Windows Application,” on page 58](#)
- ♦ [Section 4.2.6, “Uninstalling Teaming,” on page 58](#)

### 4.2.1 Performing Pre-Installation Tasks on Windows


- 1 Make sure that the Windows server where you plan to install Kablink Teaming meets the system requirements listed in [Section 2.1, “Teaming Server Requirements,” on page 17](#).
- 2 If a Web server is currently running on the Teaming server, stop it, and preferably disable it.

For example, to stop and disable the Internet Information Services (IIS) Web server:


- 2a** On the Windows desktop, click *Start > Administrative Tools > Services*.
  - 2b** Right-click *World Wide Web Publishing Service*, then click *Properties*.
  - 2c** In the *Startup type* drop-down list, select *Disabled*.
  - 2d** Click *Stop*, then click *OK*.
  - 3** Make sure that the Windows PATH environment variable includes the path to your database server.
    - 3a** Right-click *My Computer*, then click *Properties*.
    - 3b** On the *Advanced* tab, click *Environment Variables*.
    - 3c** In the *System Variables* list, locate the PATH environment variable.
    - 3d** If the path includes your database server software directory, click *Cancel*.
- or
- If the path does not include your database server software directory, add the directory, then click *OK*.

## 4.2.2 Running the Windows Teaming Installation Program

- 1** Log in to the Windows server as a user with Administrator rights.
- 2** In Windows Explorer, browse to the directory where you downloaded and extracted the Kablink Teaming software.
- 3** Double-click the `installer-teaming.exe` file to start the Teaming Installation program.
- 4** Accept the License Agreement, then click *Next*.



- 5** Click *Next* to accept the default of *New installation*.



- 6** Click *Next* to accept the default of *Basic*.
- 7** Use the information that you have gathered on the **Basic Teaming Installation Summary Sheet** to provide the information that the Teaming Installation program prompts you for:

**Installation Locations**

**Default Locale for Kablink Teaming**

Network Information

Database Selection

Database Type

JDBC URL

Credentials

Setup

Encryption Algorithm

Java JDK Location

Outbound E-Mail Configuration

Protocol

Host, Port, and Time Zone

Username, Password, and Authentication

Allow Sending E-Mail to All Users

Inbound E-Mail Configuration

The Installation program stores the information it gathers in the `installer.xml` file in the same directory where you started the Installation program.

- 8 After you have provided all the requested information, click *Install* to begin the Teaming installation.
- 9 When the installation is completed, click *Finish* to exit the Teaming Installation program.

Information about the installation process is written to the `installer.log` file in the same directory where you ran the Installation program. If a problem arises during the installation, the `installer.log` file provides information that can help you resolve the problem.
- 10 Continue with one of the following sections, depending on how you want to run the Teaming software:
  - ♦ [Section 4.2.4, “Running Teaming as a Windows Service,” on page 57](#)
  - ♦ [Section 4.2.5, “Running Teaming as a Windows Application,” on page 58](#)

## 4.2.3 Configuring the Document Converter on Windows

Kablink Teaming uses OpenOffice.org converters to prepare documents for indexing by the Lucene Index Server. The OpenOffice.org converters are also used on the Teaming site for viewing documents (by converting them to HTML).

- ♦ [“Installing OpenOffice.org as the Document Converter for Teaming” on page 55](#)
- ♦ [“Configuring OpenOffice.org for Proper HTML Conversion” on page 56](#)
- ♦ [“Running OpenOffice.org as the Document Converter for Teaming” on page 56](#)

### Installing OpenOffice.org as the Document Converter for Teaming

- 1 Download the OpenOffice.org software for Windows from [OpenOffice.org \(http://www.openoffice.org\)](http://www.openoffice.org) to a convenient temporary location on the Teaming server.
- 2 Run the downloaded executable, then click *Next* to unpack the OpenOffice.org software.
- 3 Browse to or select the destination directory for the unpacked files, then click *Unpack*.

This starts the OpenOffice.org Installation program.
- 4 Click *Next* to begin the installation.

- 5 Provide your customer information, then click *Next*.
- 6 Select *Custom*, then click *Next*.
- 7 In the *Optional Components* drop-down list, select *This feature, and all subfeatures, will be installed on local hard drive*, then click *Next*.

This includes the OpenOffice.org Java Runtime Environment (JRE) and other components required for document conversion.

- 8 Click *Install*.

The OpenOffice.org software is installed to:

c:\Program Files\OpenOffice.org 3

- 9 Click *Finish*.
- 10 Continue with [Configuring OpenOffice.org for Proper HTML Conversion](#).

### Configuring OpenOffice.org for Proper HTML Conversion

- 1 Start OpenOffice.org from the desktop.
- 2 Proceed through the Welcome pages.
- 3 Click *Tools > Options*.
- 4 Expand *Load/Save*, then click *HTML Compatibility*.
- 5 In the *Character Set* field, select *Unicode (UTF-8)*.
- 6 Click *OK* to save the character set setting, then exit OpenOffice.org.
- 7 Continue with [Running OpenOffice.org as the Document Converter for Teaming](#)

### Running OpenOffice.org as the Document Converter for Teaming

OpenOffice.org must be running as a background process on the Teaming server in order for indexing and viewing to take place for Teaming users.

- 1 Edit the properties of the OpenOffice.org desktop icon so that the *Target* field includes the following additional options:

```
"C:\Program Files\OpenOffice.org 3\program\soffice.exe"  
"-accept=socket,host=localhost,port=8100;urp;  
StarOffice.ServiceManager"  
-nologo -headless
```

- 2 Double-click the OpenOffice.org desktop icon to start OpenOffice.org as a background process.

---

**IMPORTANT:** Run OpenOffice.org as a user that has full rights to the Teaming file repository.

---

- 3 Use Windows Task Manager to observe that the `soffice.exe` and `soffice.bin` processes are running.
- 4 Test HTML conversion on your Teaming site by viewing a document that has been added as a File Entry in your Teaming site.
- 5 Configure the Teaming server so that OpenOffice.org is always running as a background process whenever Teaming is running.



## 4.2.4 Running Teaming as a Windows Service

- ♦ “Configuring Teaming as a Windows Service” on page 57
- ♦ “Starting Teaming as a Windows Service” on page 57
- ♦ “Configuring the Teaming Service to Start Automatically on Reboot” on page 57
- ♦ “Restarting the Teaming Service” on page 57
- ♦ “Stopping the Teaming Service” on page 57

### Configuring Teaming as a Windows Service

The Kablink Teaming Installation program created a `service.bat` file for configuring Teaming to run as a Windows service.

- 1 In a Command Prompt window, change to the following directory:

```
c:\Program Files\Novell\Teaming\apache-tomcat-version\bin
```

where *version* is the version number of Tomcat that was installed along with Teaming (for example, 6.0.18).

- 2 Use the following command to configure Teaming as a Windows service:

```
service.bat install Teaming
```

This creates a service named Apache Tomcat Teaming.

### Starting Teaming as a Windows Service

- 1 On the Windows desktop, click *Start > Administrative Tools > Services*.
- 2 Right-click *Apache Tomcat Teaming*, then click *Start*.

### Configuring the Teaming Service to Start Automatically on Reboot

When you run Kablink Teaming as a Windows service, you can configure Teaming to start automatically each time you reboot the Windows server.

- 1 On the Windows desktop, click *Start > Administrative Tools > Services*.
- 2 Right-click *Apache Tomcat Teaming*, then click *Properties*.
- 3 In the *Startup type* drop-down list, select *Automatic*, then click *OK*.

### Restarting the Teaming Service

You need to restart Kablink Teaming whenever you use the Teaming Installation program to make configuration changes, as described in [Chapter 9, “Performing an Advanced Teaming Installation,” on page 83](#).

- 1 On the Windows desktop, click *Start > Administrative Tools > Services*.
- 2 Right-click *Apache Tomcat Teaming*, then click *Restart*.
- 3 Close the Services window.

### Stopping the Teaming Service

- 1 On the Windows desktop, click *Start > Administrative Tools > Services*.

- 2 Right-click *Apache Tomcat Teaming*, then click *Stop*.
- 3 Close the Services window.

## 4.2.5 Running Teaming as a Windows Application

- ♦ “Starting Teaming as an Application” on page 58
- ♦ “Stopping Teaming as an Application” on page 58

### Starting Teaming as an Application

The Kablink Teaming Installation program created a `startup.bat` file for starting Teaming.

- 1 In a Command Prompt window, change to the following directory:  
`c:\Program Files\Novell\Teaming\apache-tomcat-version\bin`  
where *version* is the version number of Tomcat that was installed along with Teaming (for example, 6.0.18).
- 2 Run the `startup.bat` file to start Teaming as an application.

### Stopping Teaming as an Application

- 1 In a Command Prompt window, change to the following directory:  
`c:\Program Files\Novell\Teaming\apache-tomcat-version\bin`  
where *version* is the version number of Tomcat that was installed along with Teaming (for example, 6.0.18).
- 2 Run the `shutdown.bat` file to stop the Teaming application.

## 4.2.6 Uninstalling Teaming

If you move the Kablink Teaming site to a different server, you can delete the Teaming files from the original server to reclaim disk space. The default Teaming file locations are:

Teaming Software	<code>c:\Program Files\Novell\Teaming</code>
Teaming File Repository	<code>c:\Novell\Teaming</code>
MS SQL Database	<code>c:\Program Files\Microsoft SQL Server\MSSQL\Data</code>

For a complete list of your Teaming files, check the `installer.xml` file in the directory where you originally ran the Teaming Installation program.

# Adding Users to Your Teaming Site

# 5

After you have installed the Kablink® Teaming software and made sure that Teaming starts successfully, you are ready to access your Teaming site from your Web browser and add users.


- ♦ [Section 5.1, “Accessing Your Basic Teaming Site as the Site Administrator,” on page 59](#)
- ♦ [Section 5.2, “Creating a User,” on page 60](#)
- ♦ [Section 5.3, “Adding Teaming Users from Your LDAP Directory,” on page 61](#)
- ♦ [Section 5.4, “Preventing Users from Creating User Accounts,” on page 63](#)

## 5.1 Accessing Your Basic Teaming Site as the Site Administrator


- 1 In your Web browser, specify one of the following URLs, depending on whether or not you are using a secure SSL connection:

`http://hostname`  
`https://hostname`

where *hostname* is the hostname of the Teaming server. If you have configured the HTTP ports correctly, you do not need to include the port number in the Teaming URL.



- 2 Log in using `Admin` as the login name and `admin` as the password.  
The Teaming administrator's personal workspace displays.



- 3 Change the default administrator password to a secure password.
  - 3a On the Workspace toolbar, click *Modify Profile*.
  - 3b Specify your own password for the Teaming administrator in the *New Password* and *Confirm New Password* fields.
  - 3c (Optional) Provide useful information in the additional fields of the Teaming administrator's profile.
  - 3d Click *OK* to return to the administrator's workspace.

## 5.2 Creating a User

For testing purposes or for a very small Kablink Teaming site, you can create each Teaming user manually.

- 1 Log in as the Teaming administrator, then click *Manage* on the Workspace toolbar.
- 2 Click *Site Administration*, then click *Add User*.

User

**Login Name**

**New Password**

**Confirm New Password**

**First Name**

**E-Mail Address**

**Middle Name**

**Mobile E-Mail Address**


**Last Name**

**Text Messaging E-Mail Address**

- 3 Specify at least the login name, password, first name, and last name.
- 4 (Optional) Provide useful information in the additional fields for the new user.
- 5 Click *OK*, then click *Close* to return to the administrator's workspace.

If you expand *Personal Workspaces* in the Workspace tree above the Workspace toolbar, you see that the workspace for the user you just created does not exist yet. Workspaces are not created for users until the users log in for the first time.

- 6 Click *Sign Out* to log out as the Teaming administrator.
- 7 On the Sign In page, provide the username and password for the Teaming user you just created, then click *OK* to see the workspace for the new user.



As each new user logs into the Teaming site, a personal workspace is created.

- 8 Click *Sign Out* to leave the new user's personal workspace.

## 5.3 Adding Teaming Users from Your LDAP Directory

Unless you have a very small Kablink Teaming site, you create Teaming users by synchronizing their user information from an LDAP directory service such as Novell eDirectory™ or Microsoft Active Directory.

---

**IMPORTANT:** For a large Teaming site with thousands of users, the synchronization process can consume substantial server resources and can take some time to complete. Perform the initial import from the LDAP directory at a time when this processing does not conflict with other activities on the server.

---

- 1 If the LDAP server requires a secure SSL connection in order to access the directory service, create a public-key certificate for the Teaming server.

For instructions, see “[Securing LDAP Synchronization](#)” in “[Site Security](#)” in the *Kablink Teaming 2.0 Administration Guide*.

- 2 In a Web browser, log in to the Teaming site as the Teaming administrator, then click *Manage* on the Workspace toolbar.
- 3 Click *Site Administration* > *Configure LDAP*, then click *Add a New LDAP Connection*.
- 4 Fill in the following fields based on the information you gathered on the [Basic Teaming Installation Summary Sheet](#):

## Configure LDAP Synchronization

**New LDAP connection**

Configuration for: New LDAP connection

[Delete This Configuration](#)

URL

Principal

Credentials

**Users**

LDAP Attribute That Identifies the User

In the box below, map the internal identifiers to the LDAP attribute names of the user record. Use the following syntax: internalID=ldapAttributeName

emailAddress=mail  
 firstName=gn  
 firstName=givenName  
 lastName=sn  
 lastName=surname  
 phone=telephoneNumber  
 description=description

Base

DN

Filter

☒ Search Subtree

[Delete](#)

[Add](#)

**Groups**

[Add](#)

LDAP Server URL

User DN

Password

LDAP User Attribute

Base DN

- 5 Set the following synchronization options based on the information you gathered on the **Basic Teaming Installation Summary Sheet**:

☐ Enable Schedule

☐ Run Immediately

**Schedule**

☒ Every Day

☐ Weekly (on the days selected below)

☐ ☐ ☐ ☐ ☐ ☐ ☐

Sun Mon Tue Wed Thu Fri Sat

☒ At Time

☐ Repeat Every

**Users**

☐ Synchronize User Profiles

☐ Register LDAP User Profiles Automatically

☐ Delete Users That are not in LDAP

☐ When Deleting Users, Delete Associated User Workspaces and Content

Use the following time zone when creating new users.

GMT

**Groups**

☐ Register LDAP Group Profiles Automatically

☐ Synchronize Group Membership

☐ Delete Local Groups That Are Not in LDAP

**Local user accounts**

☒ Allow Login for Local User Accounts, (i.e., user accounts not in LDAP)

[Apply](#) [Close](#)

Enable Schedule

Synchronize User Profiles

### Register LDAP User Profiles Automatically

- 6 Click *Apply* to save the information and settings.
- 7 Select *Run Immediately*, then click *Apply* to test LDAP synchronization.

A status box displays the users and groups that have been added, modified, or deleted on the Teaming site.

---

**IMPORTANT:** If you used an LDAP user attribute of `uid` and some users were not synchronized from the LDAP directory to Teaming, repeat the procedure using `cn` instead of `uid`.

The usernames `Admin` and `Guest` are reserved for use by Teaming. If your LDAP directory includes users with these names, LDAP information for these reserved usernames is not imported into the Teaming site.

---

- 8 Click *Close* to close the status box, then click *Close* to close the Configure LDAP Synchronization page.

Teaming performs one-way synchronization from the LDAP directory to your Teaming site. If you change user information on the Teaming site, the changes are not synchronized back to your LDAP directory.

---


**IMPORTANT:** At this point, users could log into the Teaming site by using their eDirectory or Active Directory usernames and passwords. However, you should not invite users to visit the Teaming site until after you have finished setting up the Teaming site, as described in “[Site Setup](#)” in the *Kablink Teaming 2.0 Administration Guide*.

---

## 5.4 Preventing Users from Creating User Accounts

By default, Kablink Teaming enables all users to create additional user accounts. In some contexts, you do not want Teaming users to be able to set up Teaming user accounts. You want Teaming account creation to be reserved for the Teaming administrator.

- 1 In the Workspace tree, click *Personal Workspaces* to list your existing Teaming users.



- 2 On the Workspace toolbar, click *Manage > Access Control*.

## Configure Access Control

**Configure Access Control** ⓘ

Current Workspace: **Personal Workspaces**  
 Workspace Owner: **admin (admin)** [edit]

[-] Home Workspace // [-] **Personal Workspaces**

**This folder inherits its access control settings from its parent.**

Inherit role membership from the parent folder or workspace? ⓘ

☒ yes ☐ no

- 3 Select *no*, then click *Apply* so that the workspace no longer inherits its access control settings from the parent workspace.

This activates the access control table.

✓ designates the access control setting of the parent workspace

Add User Names from Clipboard

			Add a Role ▼			
			Participant	Team Member	Visitor	Workspace and Folder Administrator
	Owner of Workspace or Folder		<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>
	Team Members		<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
<b>Add a Group ▼</b>	Group Title	Group Name	Participant	Team Member	Visitor	Workspace and Folder Administrator
	All Users	allUsers	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
<b>Add a User ▼</b>	User Title	User Id	Participant	Team Member	Visitor	Workspace and Folder Administrator
<b>Add an Application Group ▼</b>	Application Group Title	Application Group Name	Participant	Team Member	Visitor	Workspace and Folder Administrator
	All Applications	allApplications	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
<b>Add an Application ▼</b>	Application Title	Application Name	Participant	Team Member	Visitor	Workspace and Folder Administrator

[Note: admin (admin) has been designated as the default site administrator with privileges to perform any task on any workspace or folder.]

- 4 For the All Users group, deselect the check box in the *Participant* column.  
 This removes the *Add User* option from the list of Teaming users under *Personal Workspaces* for regular Teaming users. It is still available for the Teaming administrator.
- 5 Ensure that the check box in the *Visitor* column is selected.  
 This enables users to view all Teaming users in this folder.
- 6 Click *Save Changes*, then click *Close*.

Setting appropriate access controls for your Teaming site is an important task that is described in:

- ♦ “Planning User Access to Workspaces and Folders” in “Site Setup” in the *Kablink Teaming 2.0 Administration Guide*
- ♦ “Controlling User Access” in the *Kablink Teaming 2.0 Advanced User Guide*



# What's Next

# 6

After you have installed and started the Teaming software, there are still administrative tasks to perform before your Teaming site is ready for users to log in and use Teaming efficiently. Refer to sections of the *Kablink Teaming 2.0 Administration Guide* as you finish setting up your Teaming site.

- ♦ “Setting Up Initial Workspaces”
- ♦ “Planning User Access to Workspaces and Folders”
- ♦ “Setting Up User Access to the Teaming Site”
- ♦ “Configuring E-Mail Integration”
- ♦ “Configuring Real-Time Communication Tools”
- ♦ “Adding Software Extensions”
- ♦ “Using Remote Applications on Your Teaming Site”
- ♦ “Customizing Your Teaming Site by Editing Teaming Properties”
- ♦ “Managing a Multi-Language Teaming Site”



# Basic Teaming Installation Summary Sheet

# 7

Installation Program Field	Value for Your Teaming Site	Explanation
<b>Teaming Server Platform:</b>		See <a href="#">Section 3.2.1, "Teaming Server Platform,"</a> on page 24.
<ul style="list-style-type: none"> <li>♦ Windows</li> <li>♦ Linux</li> </ul>		
<b>Teaming Server Architecture:</b>		See <a href="#">Section 3.2.2, "Teaming Server Architecture,"</a> on page 24.
<ul style="list-style-type: none"> <li>♦ 32-bit</li> <li>♦ 64-bit</li> </ul>		
<b>Teaming Server Memory:</b>		See <a href="#">Section 3.2.3, "Teaming Server Memory,"</a> on page 24.
<ul style="list-style-type: none"> <li>♦ 4 GB</li> <li>♦ 8 GB</li> <li>♦ More</li> </ul>		
<b>Java Development Kit (JDK):</b>		See <a href="#">Section 3.3, "Selecting a Java Development Kit,"</a> on page 26.
<ul style="list-style-type: none"> <li>♦ Sun JDK</li> <li>♦ IBM JDK</li> </ul>		
<b>Teaming Installation Locations:</b>		See <a href="#">Section 3.2.4, "Teaming Installation Locations,"</a> on page 26.
<ul style="list-style-type: none"> <li>♦ Software</li> </ul> <p>Linux default:</p> <pre>/opt/novell/teaming</pre> <p>Windows default:</p> <pre>c:\Program Files\Novell\Teaming</pre>		
<ul style="list-style-type: none"> <li>♦ File repository</li> </ul> <p>Linux default:</p> <pre>/var/opt/novell/ teaming</pre> <p>Windows default:</p> <pre>c:\Novell\Teaming</pre>		

Installation Program Field	Value for Your Teaming Site	Explanation
<b>Teaming Site Locale:</b>		See <a href="#">Section 3.10</a> , “Accommodating Multiple Languages,” on page 42
Language:		
<ul style="list-style-type: none"><li>♦ Chinese-Simplified</li><li>♦ Chinese Traditional</li><li>♦ Danish</li><li>♦ Dutch</li><li>♦ English</li><li>♦ French</li><li>♦ German</li><li>♦ Hungarian</li><li>♦ Japanese</li><li>♦ Polish</li><li>♦ Portuguese</li><li>♦ Russian</li><li>♦ Spanish</li><li>♦ Swedish</li></ul>		
Country:		
<b>User ID for Kablink Teaming (Linux only):</b>		See <a href="#">Section 3.8.2</a> , “Linux User ID for Teaming,” on page 36.
<ul style="list-style-type: none"><li>♦ User ID:</li></ul>		
Full name:		
Password:		
<ul style="list-style-type: none"><li>♦ Group ID:</li></ul>		
<b>Network Information:</b>		Section 3.4, “Gathering Network Information for Your Teaming Site,” on page 27.
<ul style="list-style-type: none"><li>♦ Hostname:</li></ul>		
<ul style="list-style-type: none"><li>♦ HTTP port: 80</li></ul>		
<ul style="list-style-type: none"><li>♦ Secure HTTP port: 443</li></ul>		
<ul style="list-style-type: none"><li>♦ Listen port: 8080</li></ul>		
<ul style="list-style-type: none"><li>♦ Secure listen port: 8443</li></ul>		
<ul style="list-style-type: none"><li>♦ Shutdown port:</li></ul>		
<ul style="list-style-type: none"><li>♦ AJP port:</li></ul>		
<b>Database Type:</b>		See <a href="#">Section 3.5.1</a> , “Database Type,” on page 29.
<ul style="list-style-type: none"><li>♦ MySQL</li></ul>		
<ul style="list-style-type: none"><li>♦ Microsoft SQL</li></ul>		
<ul style="list-style-type: none"><li>♦ Oracle</li></ul>		

Installation Program Field	Value for Your Teaming Site	Explanation
<b>JDBC URL:</b> <ul style="list-style-type: none"><li>◆ Hostname:</li><li>◆ Port number:</li></ul>		See <a href="#">Section 3.5.3, “Database Location,”</a> on page 30.
<b>Database Credentials:</b> <ul style="list-style-type: none"><li>◆ Username:</li><li>◆ Password:</li></ul>		
<b>Database Setup Method:</b> <ul style="list-style-type: none"><li>◆ During installation (automatically by the Teaming Installation program)</li><li>◆ Before installation (manually by your database administrator)</li></ul>		See <a href="#">Section 3.5.2, “Database Setup Method,”</a> on page 30.
<b>Database Encryption Algorithm:</b> <ul style="list-style-type: none"><li>◆ SHA</li><li>◆ SHA-256</li><li>◆ MD5</li></ul>		See <a href="#">Section 3.5.5, “Database Encryption Algorithm,”</a> on page 32.
<b>Java JDK Location:</b> <ul style="list-style-type: none"><li>◆ Java home:</li><li>◆ JVM heap size:</li></ul>		See <a href="#">Section 3.3, “Selecting a Java Development Kit,”</a> on page 26.
<b>Outbound E-Mail Protocol:</b> <ul style="list-style-type: none"><li>◆ SMTP</li><li>◆ SMTPS</li></ul>		See <a href="#">Section 3.6.1, “Outbound E-Mail Protocol,”</a> on page 32.
<b>Outbound E-Mail Host:</b> <ul style="list-style-type: none"><li>◆ Hostname:</li><li>◆ SMTP port: Default: 25</li><li>◆ Time zone<ul style="list-style-type: none"><li>◆ Continent/region:</li><li>◆ Country/state:</li><li>◆ City:</li></ul></li></ul>		See <a href="#">Section 3.6.2, “Outbound E-Mail Host,”</a> on page 33.


Installation Program Field	Value for Your Teaming Site	Explanation
<b>Outbound E-Mail Authentication:</b>		See <a href="#">Section 3.6.3, “Outbound E-Mail Authentication,”</a> on page 33.
<ul style="list-style-type: none"> <li>◆ Username:</li> <li>◆ Password:</li> <li>◆ Authentication required? No / Yes</li> </ul>		
<b>Allow Sending E-Mail to All Users</b>		See <a href="#">Section 3.6.4, “Outbound E-Mail Send Restriction,”</a> on page 34.
Yes / No		
<b>Inbound E-Mail Configuration</b>		See <a href="#">Section 3.7, “Enabling Inbound E-Mail,”</a> on page 34.
<ul style="list-style-type: none"> <li>◆ Enable: No / Yes</li> <li>◆ SMTP bind address:</li> <li>◆ SMTP port:</li> <li>◆ Announce TLS: Yes / No</li> </ul>		
<b>Teaming Site Password:</b>		See <a href="#">Section 3.8.1, “Teaming Site Administrator Password,”</a> on page 36.
<ul style="list-style-type: none"> <li>◆ Administrator username: Admin</li> <li>◆ Default password: admin</li> <li>◆ Your password:</li> </ul>		
<b>LDAP Directory Service:</b>		See <a href="#">Section 3.9, “Gathering Directory Services Information,”</a> on page 37.
<ul style="list-style-type: none"> <li>◆ Novell eDirectory</li> <li>◆ Microsoft Active Directory</li> <li>◆ Other LDAP directory</li> </ul>		
<b>LDAP Server:</b>		See <a href="#">“LDAP Server”</a> on page 37.
<ul style="list-style-type: none"> <li>◆ LDAP server URL:</li> <li>◆ User DN:</li> <li>◆ Password:</li> </ul>		
<b>LDAP User Attribute:</b>		See <a href="#">“User Attribute”</a> on page 38.
<ul style="list-style-type: none"> <li>◆ cn screenName=cn</li> <li>◆ uid screenName=uid</li> </ul>		
<b>LDAP User Search Context:</b>		See <a href="#">“User and Group Object Locations”</a> on page 38.
<ul style="list-style-type: none"> <li>◆ Base DN:</li> <li>◆ Additional filter attributes:</li> <li>◆ Search subtree: Yes / No</li> </ul>		

Installation Program Field	Value for Your Teaming Site	Explanation
<b>LDAP Group Search Context:</b> <ul style="list-style-type: none"><li>◆ Base DNs:</li><li>◆ Additional filter attributes:</li><li>◆ Search Subtree: Yes / No</li></ul>		See “User and Group Object Locations” on page 38.
<b>LDAP Synchronization Schedule:</b> <ul style="list-style-type: none"><li>◆ Days<ul style="list-style-type: none"><li>◆ Every day</li><li>◆ Weekly S M T W T F S</li></ul></li><li>◆ Hours:<ul style="list-style-type: none"><li>◆ At time:</li><li>◆ Repeat every <i>nn</i> hours</li></ul></li></ul>		
<b>LDAP User Options:</b> <ul style="list-style-type: none"><li>◆ Synchronize user profiles</li><li>◆ Register LDAP user profiles automatically</li><li>◆ Delete users that are not in LDAP</li><li>◆ When deleting a user, delete associated user workspaces and content</li><li>◆ Time zone for new users</li></ul>		
<b>LDAP Group Options:</b> <ul style="list-style-type: none"><li>◆ Synchronize group profiles</li><li>◆ Register LDAP group profiles automatically</li><li>◆ Synchronize group membership</li><li>◆ Delete local groups that are not in LDAP</li></ul>		
		See “User Synchronization Options” on page 40.





# Advanced Installation and Reconfiguration



- ♦ Chapter 8, “Planning an Advanced Teaming Installation,” on page 75
- ♦ Chapter 9, “Performing an Advanced Teaming Installation,” on page 83
- ♦ Chapter 10, “Setting Configuration Options after Installation,” on page 85
- ♦ Chapter 11, “Advanced Teaming Installation Summary Sheet,” on page 87



# Planning an Advanced Teaming Installation

# 8

- ♦ [Section 8.1, “What Is an Advanced Installation?,” on page 75](#)
- ♦ [Section 8.2, “Distributing Different Data Types to Different Locations,” on page 75](#)
- ♦ [Section 8.3, “Using Advanced Network Information Settings,” on page 77](#)
- ♦ [Section 8.4, “Configuring Web Services,” on page 78](#)
- ♦ [Section 8.5, “Changing Your Lucene Index Server Configuration,” on page 78](#)
- ♦ [Section 8.6, “Managing RSS Feeds,” on page 79](#)
- ♦ [Section 8.7, “Configuring Presence,” on page 80](#)

## 8.1 What Is an Advanced Installation?

In addition to the Basic installation options described in [Section 3.1, “What Is a Basic Teaming Installation?,” on page 23](#), the Kablink® Teaming Installation program provides several optional advanced installation and configuration alternatives. You can implement the advanced options after performing a Basic installation option, or you can opt to have the Installation program present all the options together.

Compared to a Basic installation, an Advanced installation offers the following additional options:

- ♦ Changing the session timeout
- ♦ Specifying a keystore file
- ♦ Specifying different directories for different types of data
- ♦ Disabling and enabling four different Web services
- ♦ Changing the configuration of the Lucene Index Server
- ♦ Configuring a remote Lucene Index Server or a group of high-availability Lucene nodes
- ♦ Reconfiguring how RSS feeds are retained or disabling them entirely
- ♦ Enabling presence in conjunction with Conferencing
- ♦ Installing Teaming in a clustered environment

## 8.2 Distributing Different Data Types to Different Locations

The default location for the Kablink Teaming file repository varies by platform:

Linux:        /var/opt/novell/teaming

Windows:    c:\Novell\Teaming

Under the main Teaming file repository root directory are subdirectories for various kinds of data files that are not stored in the Teaming database (MySQL, Microsoft SQL Server, or Oracle). Using an Advanced installation, you can store Teaming data files in various locations.

The data files not stored in the Teaming database are divided up into several functional areas:

- ♦ **Simple file repository:** A large consumer of disk space.

All attachment files are stored in the file repository. All versions of files are also stored here.

- ♦ **Jackrabbit repository:** (Optional) Takes only a fraction of the space consumed by the file repository.

By default, Teaming stores all data files individually on disk, in the file repository. If you prefer to store data files in the database itself, you can use Apache Jackrabbit\* with Teaming. See the [Apache Jackrabbit Web site \(http://jackrabbit.apache.org\)](http://jackrabbit.apache.org) for setup instructions.

- ♦ **Extensions repository:** Depends on the number of extensions you add to your Teaming site.

An extension is a software program that you can incorporate into your Teaming site in order to enhance (extend) Teaming capabilities. Adblock Plus is an example of a browser extension for the Firefox Web browser that filters out advertisements. You or a Java developer can create custom extensions for your Teaming site. For more information about creating and using Teaming extensions, see the *Kablink Teaming 2.0 Developer Guide*.

- ♦ **Cache store:** Consumes less disk space than the file repository.

Information derived from the attachments, such as HTML renderings, scaled images, and word lists for indexing are stored in the cache store.

- ♦ **Lucene index:** Takes only a fraction of the space consumed by the file repository.

The Lucene index contains only pointers to the actual data stored in the file repository. The index enables the Lucene search engine to perform very fast searches through large quantities of data.

The directories for the various types of data can be on the Teaming server or on a remote server. Data access is fastest if the data is local, but depending on the size of your Teaming site and the types of data you store, the Teaming server might not be the best place to store all the Teaming data. If you want to store any of the data types on a remote server, you must ensure that the remote location of the data appears local to the Teaming server and that it is always available with read/write access.

Linux: Mount the file repository to the Teaming server.

Windows: Map a drive from the Teaming server to the file repository.

Linux and Windows Place the file repository on a SAN (storage area network) with read/write access. This alternative provides the most reliable remote location for the Teaming file repository.

---

#### ADVANCED TEAMING INSTALLATION SUMMARY SHEET

---

Under *Data Locations*, specify the directories where you want to store the various types of Teaming data.

---

Complete the planning process for additional Advanced installation features as needed, then perform the Advanced installation as described in [Chapter 9, “Performing an Advanced Teaming Installation,”](#) on page 83.

## 8.3 Using Advanced Network Information Settings

- ♦ [Section 8.3.1, “Changing the Teaming Session Timeout,” on page 77](#)
- ♦ [Section 8.3.2, “Providing a Secure Keystore File,” on page 77](#)

### 8.3.1 Changing the Teaming Session Timeout

By default, if a user’s Kablink Teaming session is idle for four hours (240 minutes), Teaming logs the idle user out. For increased convenience to Teaming users, you can make the session timeout interval longer. For increased security for your Teaming site, you can make the session timeout shorter.

---

#### ADVANCED TEAMING INSTALLATION SUMMARY SHEET

---

Under *Network Information*, specify the session timeout interval (in minutes) for your Teaming site.

---

Complete the planning process for additional Advanced installation features as needed, then perform the Advanced installation as described in [Chapter 9, “Performing an Advanced Teaming Installation,” on page 83](#).

### 8.3.2 Providing a Secure Keystore File

For your convenience, the Kablink Teaming software includes a self-signed public certificate that enables you to specify secure HTTP and listen ports during installation. This certificate is stored in the `.keystore` file in the following directory:

Linux: `/opt/novell/teaming/apache-tomcat-version/conf`

Windows: `c:\Program Files\Novell\Teaming\apache-tomcat-version\conf`

To ensure secure SSL connections for your Teaming site, you should replace the self-signed public certificate with a public certificate issued by a valid Certificate Authority.

---

#### ADVANCED TEAMING INSTALLATION SUMMARY SHEET

---

Under *Network Information*, specify the name and location of the public certificate.

---

If you do not already have a permanent public certificate for your Teaming server, see [“Securing HTTP Connections”](#) in [“Site Security”](#) in the *Kablink Teaming 2.0 Administration Guide*.

Complete the planning process for additional Advanced installation features as needed, then perform the Advanced installation as described in [Chapter 9, “Performing an Advanced Teaming Installation,” on page 83](#).

## 8.4 Configuring Web Services

When you install and set up your Kablink Teaming site, three Web services are enabled by default. A fourth is available for selection. These Web services enable programs to access information on your Teaming site just as users would. Allowing programmatic access to your Teaming site can be useful or can be viewed as a security risk.

- ♦ **WSS authentication:** Uses [OASIS Web Services Security \(WSS\)](http://www.oasis-open.org) (<http://www.oasis-open.org>).
- ♦ **HTTP Basic authentication:** Uses [HTTP Basic Access authentication](http://tools.ietf.org/html/rfc2617) (<http://tools.ietf.org/html/rfc2617>).
- ♦ **Token-based authentication:** Uses custom Teaming tokens to communicate with Teaming remote applications. For more information, see “[Using Remote Applications on Your Teaming Site](#)” in “[Site Setup](#)” in the *Kablink Teaming 2.0 Administration Guide*.
- ♦ **Anonymous access:** Allows access to your Teaming site without authentication. It is similar to the Guest access provided for users, as described in “[Allowing Guest Access to Your Teaming Site](#)” in “[Site Setup](#)” in the *Kablink Teaming 2.0 Administration Guide*.

---

### ADVANCED TEAMING INSTALLATION SUMMARY SHEET

---

Under *Web Services*, mark which Web services you want enabled for your Teaming site. The first three are enabled by default. The fourth is disabled by default.

---

Complete the planning process for additional Advanced installation features as needed, then perform the Advanced installation as described in [Chapter 9, “Performing an Advanced Teaming Installation,”](#) on page 83.

## 8.5 Changing Your Lucene Index Server Configuration

The default Lucene Index Server configuration is appropriate for a medium-sized Kablink Teaming site. If you have a larger Teaming site, you can change its Lucene Index Server configuration.

- ♦ [Section 8.5.1, “Understanding Indexing,”](#) on page 78
- ♦ [Section 8.5.2, “Changing Lucene Configuration Settings,”](#) on page 79

After planning your Lucene configuration, complete the planning process for additional Advanced installation features as needed, then perform the Advanced installation as described in [Chapter 9, “Performing an Advanced Teaming Installation,”](#) on page 83.

### 8.5.1 Understanding Indexing

The Lucene Index Server is responsible for indexing all data on the Kablink Teaming site so that Teaming users can easily use the Find and Search features to retrieve the information that they need. Text posted in folder entries is easy to index, because the formatting is simple. However, text in attached files arrives in many different file formats, many of which require conversion before the text in the files can be indexed. Therefore, the Lucene Index Server is dependent on the available file conversion technology in order to perform its indexing function. For information about the file viewers that Teaming uses, see [Section 2.3.1, “File Viewer Support,”](#) on page 19.

The Lucene Index Server provides additional services on your Teaming site in addition to indexing. In fact, you cannot access your Teaming site if the Lucene Index Server is not running. For this reason, Novell Teaming provides multi-server Lucene configuration options that are not available in Kablink Teaming.

## 8.5.2 Changing Lucene Configuration Settings

If you have an extremely large Kablink Teaming site and you need to reindex the Teaming data, you might see improved performance by increasing these settings.

- ♦ **Flush threshold:** The default is 100. This means that after 100 documents have been cached in memory, they are flushed to disk. Increasing the setting allows additional documents to be cached in memory before a flush occurs.
- ♦ **Max booleans:** The default is 10000. This means that 10,000 Boolean clauses are allowed in a query. You would only need to increase this if your Teaming site includes more than 10,000 users, groups, or teams.
- ♦ **Max merge documents:** The default is 1000. This means that the Lucene Index Server starts a new index segment after the current index segment contains 1000 documents. Only a very large Teaming site would benefit from increasing this.
- ♦ **Merge factor:** The default is 10. This sets the number of index segments that are created on disk. When additional index segments are needed, existing segments are merged to keep the merge factor constant. Only a very large Teaming site would benefit from increasing this.

---

### ADVANCED TEAMING INSTALLATION SUMMARY SHEET

---

Under *Lucene Configuration*, specify any Lucene configuration settings that you want to change.

---

## 8.6 Managing RSS Feeds

By default, Teaming users can set up RSS feeds in folders on the Teaming site, as described in “[Viewing Teaming Folders as RSS Feeds](#)” in “[Getting Informed](#)” in the *Novell Teaming 2.0 User Guide*.

- ♦ [Section 8.6.1, “Configuring RSS Feeds,” on page 79](#)
- ♦ [Section 8.6.2, “Disabling RSS Feeds,” on page 80](#)

After planning the RSS settings, complete the planning process for additional Advanced installation features as needed, then perform the Advanced installation as described in [Chapter 9, “Performing an Advanced Teaming Installation,” on page 83](#).

### 8.6.1 Configuring RSS Feeds

The following aspects of RSS functionality on your Kablink Teaming site are configurable:

- ♦ **Max elapsed days:** By default, items from RSS feeds are retained on the Teaming site for 31 days. You can decrease the number of days to reduce the amount of disk space occupied by the RSS files.
- ♦ **Max inactive days:** By default, if no one on the Teaming site accesses an RSS feed for 7 days, the feed is no longer updated. Increase or decrease the retention time for inactive feeds to meet the needs of Teaming users and disk space considerations.

---

**ADVANCED TEAMING INSTALLATION SUMMARY SHEET**

---

Under *RSS Configuration*, specify the number of days that meet the needs of your Teaming site.

---

## 8.6.2 Disabling RSS Feeds

Some administrators consider RSS feeds to be a security risk because the RSS feed URL includes username and password information. If you do not want Kablink Teaming site users to be able to subscribe to RSS feeds from the Teaming site, you can disable this feature.

---

**ADVANCED TEAMING INSTALLATION SUMMARY SHEET**

---

Under *RSS Configuration*, mark *No*.

---

## 8.7 Configuring Presence

If you are using Kablink Conferencing 1.0, you can configure Kablink Teaming to display a user's Conferencing presence icon anywhere on the Teaming site where that user's name displays. When you click the presence icon, contact options are presented. In addition, with Conferencing presence enabled, a link at the bottom of each workspace and folder page enables you to start an instant meeting with team members of a team workspace or with users who have created entries and comments in the folder.

In order to configure Conferencing presence in Teaming, you need the following information about the Conferencing system:

- ♦ **Jabber server:** Specify the IP address or DNS hostname of the Conferencing XML router. For more information, see “**Installing the Conferencing Server**” in the *Conferencing 1.0 Server Installation Guide*.
- ♦ **Broker admin ID:** The default admin ID is `admin`.
- ♦ **Broker admin password:** The default admin password is `admin`.
- ♦ **Jabber domain:** Specify the IP address or DNS hostname of the Conferencing XML router.
- ♦ **Default community ID:** Users in a Conferencing system are organized into groups called communities. When the Conferencing software is installed, a system community is created. For more information, see “**Conferencing Communities**” in the *Conferencing 1.0 Operations Guide*.

Specify the community ID where you want to obtain presence information.

- ♦ **Conferencing URL:** Specify the URL of the Conferencing server:

`http://ip_address_or_hostname:8000/imidio_api`

---

**ADVANCED TEAMING INSTALLATION SUMMARY SHEET**

---

Under *Presence Configuration*, list the information that the Teaming site needs to know in order to communicate with the Conferencing system.

---



Complete the planning process for additional Advanced installation features as needed, then perform the Advanced installation as described in [Chapter 9, “Performing an Advanced Teaming Installation,”](#) on page 83.

---

**IMPORTANT:** In order for Conferencing presence to display, the *Conferencing User Name* field of each user’s Teaming profile must contain the user’s Conferencing ID. Users can provide this information manually, or you can populate the *Conferencing User Name* field from your LDAP directory.

---




# Performing an Advanced Teaming Installation

# 9

You should already have reviewed [Chapter 3, “Planning a Basic Teaming Installation,”](#) on page 23 and filled out the [Basic Teaming Installation Summary Sheet](#). You should also have reviewed [Chapter 8, “Planning an Advanced Teaming Installation,”](#) on page 75 and filled out the [Advanced Teaming Installation Summary Sheet](#) for those aspects of an Advanced installation that you want to implement for your Kablink® Teaming site.

- 1 Follow the Basic installation instructions provided in [Chapter 4, “Setting Up a Basic Teaming Site,”](#) on page 45 for the platform where you are installing Teaming.
- 2 In the Choose Installation Type page, select *Advanced*.



- 3 Use the information that you have gathered on the [Basic Teaming Installation Summary Sheet](#) and the [Advanced Teaming Installation Summary Sheet](#) to provide the information that the Teaming Installation program prompts you for:

## Basic Installation Pages:

[Installation Locations](#)  
[Default Locale for Kablink Teaming](#)  
[User ID for Kablink Teaming \(Linux only\)](#)  
[Network Information](#)  
[Database Selection](#)  
[Java JDK Location](#)  
[Outbound E-Mail Configuration](#)  
[Inbound E-Mail Configuration](#)

Some Basic installation pages have additional options available when you perform an Advanced installation.

## Advanced Installation Pages:

[Web Services](#)  
[Lucene Configuration](#)  
[RSS Configuration](#)  
[Presence Configuration](#)

The Installation program stores the information it gathers in the `installer.xml` file in the same directory where you started the Installation program.

- 4 After you have provided all the requested information, click *Install* to begin the Advanced installation.


- 5** When the installation is completed, click *Finish* to exit the Teaming Installation program.  
Information about the installation process is written to the `installer.log` file in the same directory where you ran the Installation program. If a problem arises during the installation, the `installer.log` file provides information that can help you resolve the problem.
- 6** After you complete the Advanced installation, continue setting up your Teaming site, as described in [Chapter 5, “Adding Users to Your Teaming Site,” on page 59](#).

# Setting Configuration Options after Installation

# 10

After you install Kablink® Teaming following the instructions in [Part I, “Basic Installation,” on page 11](#) or [Part II, “Advanced Installation and Reconfiguration,” on page 73](#), you can rerun the Teaming Installation program to change configuration options or add new functionality to your Teaming site.

- 1 Stop Teaming.
- 2 Start the Teaming Installation program.




Because the Installation program finds an existing `installer.xml` file, it defaults to *Reconfigure settings*.

- 3 Click *Next*.

The Teaming Installation program asks you to verify that you have stopped Teaming.

- 4 Click *Yes*.



- 5 Select *Basic* or *Advanced*, depending on the configuration setting that you want to change, then click *Next*.
- 6 Click *Next* until you reach an installation page where you want to reconfigure settings.

## Basic Installation Pages:

[Installation Locations](#)

[Default Locale for Kablink Teaming](#)

[User ID for Kablink Teaming \(Linux only\)](#)

[Network Information](#)

[Database Selection](#)

[Java JDK Location](#)

[Outbound E-Mail Configuration](#)

[Inbound E-Mail Configuration](#)

### **Advanced Installation Pages:**

Web Services

Lucene Configuration

RSS Configuration

Presence Configuration

- 7** When you reach the Ready to Install page, click *Install* to implement the reconfigured settings.
- 8** Start Teaming.

# Advanced Teaming Installation Summary Sheet


# 11

Installation Program Field	Value for Your Teaming Site	Explanation
<b>Data Locations:</b>		See <a href="#">Section 8.2, "Distributing Different Data Types to Different Locations,"</a> on page 75.
Linux default:		
<code>/var/opt/novell/teaming</code>		
Windows default:		
<code>c:\Novell\Teaming</code>		
<ul style="list-style-type: none"><li>♦ Simple file repository</li><li>♦ Jackrabbit repository</li><li>♦ Extensions repository</li><li>♦ Cache store</li><li>♦ Lucene index</li></ul>		
<b>Network Information:</b>		See <a href="#">Section 8.3, "Using Advanced Network Information Settings,"</a> on page 77.
<ul style="list-style-type: none"><li>♦ Enable Web services: No / Yes</li><li>♦ Session timeout Default: 240 minutes</li><li>♦ Enable Tomcat access log: No / Yes</li><li>♦ Keystore file:</li></ul>		
<b>Web Services:</b>		See <a href="#">Section 8.4, "Configuring Web Services,"</a> on page 78.
<ul style="list-style-type: none"><li>♦ Enable WSS authentication</li><li>♦ Enable Basic authentication</li><li>♦ Enable token-based authentication</li><li>♦ Enable anonymous access</li></ul>		

Installation Program Field	Value for Your Teaming Site	Explanation
<b>Lucene Configuration:</b>		See <a href="#">Section 8.5.2, “Changing Lucene Configuration Settings,”</a> on page 79.
Configuration type: all		
♦ Flush threshold: Default: 100		
♦ Max booleans: Default: 10000		
♦ Max merge documents: Default: 1000		
♦ Merge factor: 10		
<b>RSS Configuration:</b>		See <a href="#">Section 8.6, “Managing RSS Feeds,”</a> on page 79.
Enable RSS: No / Yes		
♦ Max elapsed days: ♦ Max inactive days:		
<b>Presence Configuration:</b>		See <a href="#">Section 8.7, “Configuring Presence,”</a> on page 80.
Enable presence: No / Yes		
♦ Jabber server:		
♦ Broker admin ID:		
♦ Broker admin password:		
♦ Jabber domain:		
♦ Default community ID:		
♦ Conferencing URL:		



# Multi-Server Configurations and Clustering



- ♦ Chapter 12, “Creating the Teaming Database on a Remote Server,” on page 91
- ♦ Chapter 13, “Running Multiple Database Servers,” on page 97



# Creating the Teaming Database on a Remote Server

# 12

The default location for the Kablink<sup>®</sup> Teaming database is on the same server with the Teaming software, as described in [Section 3.5.3, “Database Location,” on page 30](#). However, for better performance and scalability, you can install the database server (MySQL, Microsoft SQL, or Oracle) on a remote server, then use the scripts that are included with the Teaming software to manually create the Teaming database in any location that you prefer.

- [Section 12.1, “Preparing to Manually Create a Database,” on page 91](#)
- [Section 12.2, “Creating a MySQL Database,” on page 92](#)
- [Section 12.3, “Creating a Microsoft SQL Database,” on page 93](#)
- [Section 12.4, “Creating an Oracle Database,” on page 93](#)
- [Section 12.5, “Installing Teaming with a Remote Database,” on page 95](#)

---

**NOTE:** This section assumes that you already have a Basic installation of Teaming up and running successfully. It is highly recommended to follow the instructions in [Part I, “Basic Installation,” on page 11](#) before attempting a more complex Teaming configuration.

---

## 12.1 Preparing to Manually Create a Database

Kablink Teaming includes scripts for creating the Teaming database on a remote server.

- 1 In the directory where the Teaming Installation program is located on the Teaming server, unzip the `teaming-2.0.0-sql.zip` file.  
This creates two new subdirectories, the `create` subdirectory for database creation scripts and the `update-1.0.0-2.0.0` directory for database update scripts.
- 2 Change to the `create` subdirectory.
- 3 Copy all the scripts for your database type to a convenient temporary location on the server where you want to create the database, and make sure that your database management utility is on your path so that you can run it from that directory

Database	Database Script	Database Management Utility
MySQL:	<code>*mysql.sql</code>	<code>mysql</code>
Microsoft SQL:	<code>*sqlserver.sql</code>	<code>osql</code>
Oracle:	<code>*oracle.sql</code>	<code>sqlplus</code>

- 4 Continue with the instructions for the type of database that you want to create:
  - [Section 12.2, “Creating a MySQL Database,” on page 92](#)
  - [Section 12.3, “Creating a Microsoft SQL Database,” on page 93](#)
  - [Section 12.4, “Creating an Oracle Database,” on page 93](#)

## 12.2 Creating a MySQL Database

- 1 Review the MySQL requirements listed in [Section 2.1, “Teaming Server Requirements,” on page 17](#)
- 2 Make sure that the MySQL database server and client have been installed and configured, as described in [Section A.2, “MySQL Database Server,” on page 121](#).
- 3 Make sure that the MySQL database client is also installed on the Teaming server  
The Teaming Installation program needs the MySQL client in order to communicate with the remote MySQL database server.
- 4 Make sure that you know the password for the MySQL `root` administrator user.
- 5 Make sure that `innodb` support is enabled.  
It is enabled by default. You can verify the setting in the MySQL configuration file.

Linux: `/etc/my.cnf`

Windows: `c:\Program Files\MySQL\MySQL Server version\my.ini`

- 6 In the MySQL configuration file, make the following changes using a text editor:
  - 6a Under the `[client]` section, add the following line:  
`default_character_set = utf8`
  - 6b Under the `[mysqld]` section, add the following line:  
`character_set_server = utf8`  
Setting the character set to UTF-8 ensures that extended characters are handled correctly in the database.
  - 6c Also under the `[mysqld]` section, add the following line:  
`bind-address = teaming_server_address`  
where *teaming\_server\_address* is the IP address or DNS hostname of the Teaming server that is allowed to remotely access the MySQL database server.
  - 6d Save the updated configuration file, then exit the text editor.
- 7 In the directory where you copied the database scripts ([Step 3 in Section 12.1, “Preparing to Manually Create a Database,” on page 91](#)), enter the following command to run the MySQL database creation script:

```
mysql -uuser -ppassword < create-database-mysql.sql
```

- 8 Configure MySQL to allow access from a remote server:

```
mysql -uuser -ppassword
mysql> grant all privileges on *.*
-> to 'username'@'%'
-> identified by 'password'
-> with grant option
-> ;
```

- 9 Be familiar with standard database maintenance procedures.

For more information about MySQL, see the following references:

- ♦ [MySQL 5.1 Reference Manual](http://dev.mysql.com/doc/refman/5.1/en) (<http://dev.mysql.com/doc/refman/5.1/en>)
- ♦ [MySQL 5.0 Reference Manual](http://dev.mysql.com/doc/refman/5.0/en) (<http://dev.mysql.com/doc/refman/5.0/en>)

The following database tools can be helpful:

- ♦ [MySQL GUI Tools \(http://dev.mysql.com/downloads/gui-tools\)](http://dev.mysql.com/downloads/gui-tools)
- ♦ [SQLyog \(http://www.webyog.com\)](http://www.webyog.com)
- ♦ [Squirrel SQL Client \(http://squirrel-sql.sourceforge.net\)](http://squirrel-sql.sourceforge.net)

10 Skip to [Section 12.5, “Installing Teaming with a Remote Database,” on page 95.](#)

## 12.3 Creating a Microsoft SQL Database

- 1 Review the Microsoft SQL requirements listed in [Section 2.1, “Teaming Server Requirements,” on page 17.](#)
- 2 Make sure that the Microsoft SQL Server and Client have been installed and configured properly.

---

**IMPORTANT:** Make sure that TCP/IP is enabled for Microsoft SQL Server.

---

For more information, see [Microsoft SQL Server \(http://msdn.microsoft.com/en-us/library/bb545450.aspx\)](http://msdn.microsoft.com/en-us/library/bb545450.aspx).

- 3 Make sure that the Microsoft SQL database client is also installed on the Teaming server  
The Teaming Installation program needs the Microsoft SQL client in order to communicate with the remote Microsoft SQL database server.
- 4 When you install Microsoft SQL Server, select *SQL Server and Windows* for authentication.  
The default is *Windows Only*, which is not appropriate for Teaming
- 5 Immediately establish the database administrator username and password for the SQL database server.
- 6 Change to the directory where you copied the database scripts in [Step 3 in Section 12.1, “Preparing to Manually Create a Database,” on page 91.](#)
- 7 Enter the following command to run the Microsoft SQL database creation script:

```
osql -Uuser -Ppassword -i create-database-sqlserver.sql
```

- 8 Be familiar with standard database maintenance procedures.

For more information about Microsoft SQL, see the following references:

- ♦ [Microsoft SQL Server 2008 Learning Resources \(http://www.microsoft.com/sqlserver/2008/en/us/learning.aspx\)](http://www.microsoft.com/sqlserver/2008/en/us/learning.aspx)
- ♦ [Microsoft SQL Server 2005 Learning Resources \(http://www.microsoft.com/sqlserver/2005/en/us/learning-resources.aspx\)](http://www.microsoft.com/sqlserver/2005/en/us/learning-resources.aspx)

The following database tool can be helpful:

- ♦ [Squirrel SQL Client \(http://squirrel-sql.sourceforge.net\)](http://squirrel-sql.sourceforge.net)

9 Skip to [Section 12.5, “Installing Teaming with a Remote Database,” on page 95.](#)

## 12.4 Creating an Oracle Database

When you use an Oracle database, your database administrator must create it for you. The Kablink Teaming Installation program cannot create an Oracle database.

---

## BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Database Creation*, make sure you have marked that you want your database administrator to manually create the Oracle database before installation.

---

- 1 Review the Oracle database requirements listed in [Section 2.1, “Teaming Server Requirements,”](#) on page 17.
- 2 Make sure that the Oracle database server and client software has been installed and configured properly.  
For more information, see [Oracle Database \(http://www.oracle.com/database\)](http://www.oracle.com/database).
- 3 Make sure that the Oracle database client is also installed on the Teaming server  
The Teaming Installation program needs the Oracle client in order to communicate with the remote Oracle database server.
- 4 Make sure that you know the password for the Oracle database administrator user.
- 5 Set up the Oracle database character set to support Unicode character encodings.  
Teaming requires either the UTF-8 or AL32UTF8 character set for proper operation. Oracle recommends the use of AL32UTF8, because it has increased support for certain Asian languages. For more information, see [Choosing a Character Set \(http://download.oracle.com/docs/cd/B19306\\_01/server.102/b14225/ch2charset.htm\)](http://download.oracle.com/docs/cd/B19306_01/server.102/b14225/ch2charset.htm) in the *Oracle Database Globalization Support Guide*.
- 6 Change to the directory where you copied the Oracle database scripts in [Step 3](#) in [Section 12.1, “Preparing to Manually Create a Database,”](#) on page 91.
- 7 Edit the `create-database-oracle.sql` script with your Oracle database password.

### Original:

```
drop user sitescape cascade;
create user sitescape identified by sitescape;
grant connect, resource to sitescape;
connect sitescape/sitescape;
```

---

**NOTE:** SiteScape® is the name of the company that previously owned the Teaming software.

---

### Updated:

```
drop user sitescape cascade;
create user sitescape identified by your_oracle_password;
grant connect, resource to sitescape;
connect sitescape/your_oracle_password;
```

---

**IMPORTANT:** Unless you are very familiar with editing scripts, change only the password. Do not attempt to change the name of the database from the legacy default of `sitescape`.

---

- 8 Enter the following commands to run the database creation script:

```
sqlplus "/ as sysdba"
SQL> spool create-database-oracle.out;
SQL> @create-database-oracle;
SQL> quit
```
- 9 Check the resulting `create-database-oracle.out` file for errors and resolve them.
- 10 Be familiar with standard database maintenance procedures.

For more information about your Oracle database, see the following reference:

- ♦ [Oracle Product Documentation \(http://www.oracle.com/technology/documentation\)](http://www.oracle.com/technology/documentation)
- ♦ [Oracle SQL\\*Plus Documentation \(http://www.oracle.com/technology/docs/tech/sql\\_plus\)](http://www.oracle.com/technology/docs/tech/sql_plus)

The following database tool can be helpful:

- ♦ [Squirrel SQL Client \(http://squirrel-sql.sourceforge.net\)](http://squirrel-sql.sourceforge.net)

- 11 (Conditional) If you created the Oracle database on the Teaming server, skip to [Chapter 4, “Setting Up a Basic Teaming Site,”](#) on page 45 or [Chapter 9, “Performing an Advanced Teaming Installation,”](#) on page 83.

---

**IMPORTANT:** On the Database Selection page in the Installation program, be sure to select *Database already exists or has already been created*.

---

or

(Conditional) If you created the Oracle database on a remote server, continue with [Installing Teaming with a Remote Database](#).

## 12.5 Installing Teaming with a Remote Database

- 1 Run the Kablink Teaming Installation program, as described in [Chapter 4, “Setting Up a Basic Teaming Site,”](#) on page 45 or [Chapter 9, “Performing an Advanced Teaming Installation,”](#) on page 83.
- 2 When you get to the Database Selection page:

The screenshot shows the 'Database Selection' window of the 'Teaming 2.0.0 Installation Program'. The window has a title bar with standard OS controls. Inside, there's a section titled 'Database Selection' with the instruction 'Select your database and set the database options.' Below this, a note states 'The database server you select must already be installed.' The form contains several fields: 'Database type:' with a dropdown menu showing 'MySql'; 'JDBC URL:' with a text field containing 'jdbc:mysql://localhost:3306/sitescape?useUnicode=true&characterEncoding=UTF-8'; 'Credentials' section with 'Username:' (text field with 'root') and 'Password:' (password field); 'Setup' section with two radio buttons: 'Create the database during installation' (disabled) and 'Database already exists or has already been created' (selected); and 'Encryption algorithm' section with a text field 'User passwords are encrypted using the selected algorithm:' and a dropdown menu showing 'SHA'.

- 2a Fill in the fields:

**Database type:** Select the type of database that you just created.

**JDBC URL:** Replace `localhost` with the hostname of the server where you created the Teaming database.

**Credentials:** Specify the password for the database administrator user.

**Setup:** Select *Database already exists or has already been created* so that the Installation program does not create one for you.

**Encryption algorithm:** Set the encryption appropriate for the security needs of the Teaming site. For more information, see [Section 3.5.5, “Database Encryption Algorithm,” on page 32](#).

**2b** Click *Next*.

The Teaming Installation program tries to connect to the database. If it connects successfully, you can continue with the installation. If the Teaming Installation program cannot connect to the database, you must resolve the problem with the database before you can continue with the Teaming installation.

**2c** When the Teaming Installation program can successfully connect to the remote database, continue as usual with the installation.



# Running Multiple Database Servers

# 13

The three databases supported by Kablink® Teaming (MySQL, Microsoft SQL, and Oracle) each have their own approach to clustering the database server. Information about clustering database servers is available on the Internet, for example:

- [MySQL Cluster \(http://www.mysql.com/products/database/cluster\)](http://www.mysql.com/products/database/cluster)
- [SQL Server Clustering \(http://www.sql-server-performance.com/articles/clustering/clustering\\_intro\\_p1.aspx\)](http://www.sql-server-performance.com/articles/clustering/clustering_intro_p1.aspx)
- [Oracle Real Application Clusters \(http://www.oracle.com/technology/products/database/clustering\)](http://www.oracle.com/technology/products/database/clustering)

---

**NOTE:** It is highly recommended to follow the instructions in **Part I, “Basic Installation,”** on **page 11** before attempting a more complex Teaming configuration.

---



# Update

# IV

- ♦ Chapter 14, “What’s New in Kablink Teaming 2.0,” on page 101
- ♦ Chapter 15, “Updating from Kablink Teaming 1.0 to Kablink Teaming 2.0,” on page 103
- ♦ Chapter 16, “Updating from Kablink Teaming 1.0 to Novell Teaming 2.0,” on page 113
- ♦ Chapter 17, “Changing from Kablink Teaming 2.0 to Novell Teaming 2.0,” on page 115



# What's New in Kablink Teaming 2.0

# 14

- ♦ [Section 14.1, “Teaming 2.0 User Enhancements,” on page 101](#)
- ♦ [Section 14.2, “Teaming 2.0 Installation Enhancements,” on page 101](#)
- ♦ [Section 14.3, “Teaming 2.0 Administration Enhancements,” on page 101](#)

## 14.1 Teaming 2.0 User Enhancements

For a list of Kablink® Teaming enhancements and instructions for use, see:

- ♦ [“What's New in Teaming 2.0” in the \*Kablink Teaming 2.0 User Guide\*](#)
- ♦ [“What's New in Teaming 2.0” in the \*Kablink Teaming 2.0 Advanced User Guide\*](#)

## 14.2 Teaming 2.0 Installation Enhancements

- ♦ **No Liferay dependency:** Kablink Teaming 2.0 is a standalone application with no dependency on Liferay.
- ♦ **Built-in mail server for incoming posts:** Teaming 2.0 includes a build-in SMTP mail server for incoming e-mail. This allows Teaming users to easily post to folders in the Teaming site from their e-mail clients. For configuration instructions, see [Section 3.7, “Enabling Inbound E-Mail,” on page 34](#).

## 14.3 Teaming 2.0 Administration Enhancements

- ♦ **Multiple LDAP queries:** Kablink Teaming 2.0 can search multiple LDAP containers for User objects so that Teaming user accounts can be set up for users distributed throughout your LDAP directory. For setup instructions, see [Section 5.3, “Adding Teaming Users from Your LDAP Directory,” on page 61](#).
- ♦ **Software extensions:** You can enhance the functionality of your Teaming site by implementing software extensions. For setup instructions, see [“Adding Software Extensions” in “Site Setup” in the \*Kablink Teaming 2.0 Administration Guide\*](#).
- ♦ **Remote applications:** You can also expand the functionality of your Teaming site by running remote applications from the Teaming site. For setup instructions, see [“Using Remote Applications on Your Teaming Site” in “Site Setup” in the \*Kablink Teaming 2.0 Administration Guide\*](#).



# Updating from Kablink Teaming 1.0 to Kablink Teaming 2.0

# 15

- Section 15.1, “Understanding the Update Process,” on page 103
- Section 15.2, “Preparing Your Teaming Site for Update,” on page 103
- Section 15.3, “Updating a Single-Server Teaming Site,” on page 105
- Section 15.4, “Updating a Multiple-Server Teaming Site,” on page 107
- Section 15.5, “Performing Post-Update Tasks,” on page 109

## 15.1 Understanding the Update Process

The major change when you update from Kablink® Teaming 1.0 to Kablink Teaming 2.0 is that the Liferay portal is no longer used by your Teaming site. The Teaming Installation program backs up your Teaming data and disconnects your Teaming site from the Liferay software that was installed as part of Teaming 1.0. No Teaming data is lost in this process.

During the update from Teaming 1.0 to Teaming 2.0, the following aspects of your Teaming site are modified:

- The Teaming software is updated from version 1.0 to 2.0.
- The Teaming database is updated with a new database structure to support the new features in 2.0. All teams, groups, roles, workspaces, and folders are preserved throughout the update process.
- The Lucene Index Server is updated for improved functionality.
- Teaming no longer uses an external e-mail system for inbound message delivery. Teaming 2.0 includes an internal SMTP mail host for incoming messages. This implementation allows for the easy creation of simple URLs to facilitate posting to the Teaming site from e-mail clients.
- The Liferay portal is eliminated from your Teaming installation. The Liferay data is backed up, so if you have made customizations to Liferay, they remain intact, but the Liferay portal is not left in a usable state after the Teaming files are removed from it. If you want to continue to use Liferay, you must set up a new, independent installation of Liferay and transfer any customizations that you have made to the Teaming version into the new, independent version. To obtain the latest version of Liferay, see [Liferay Portal \(http://www.liferay.com\)](http://www.liferay.com).

## 15.2 Preparing Your Teaming Site for Update

- Section 15.2.1, “Updating Your Operating Environment,” on page 104
- Section 15.2.2, “Backing Up Your Teaming Data,” on page 104
- Section 15.2.3, “Planning Your Teaming 2.0 Installation,” on page 105

## 15.2.1 Updating Your Operating Environment

The following components of the Kablink Teaming operating environment were supported for Teaming 1.0 but are not supported for Teaming 2.0:

- ♦ Red Hat\* Enterprise Linux 3 and 4
- ♦ Oracle 9g
- ♦ Microsoft SQL Server 2000

If the operating environment for your Teaming system includes any of these components, you must update the components before your update to Teaming 2.0. For currently supported versions, see [Chapter 2, “Teaming System Requirements,” on page 17](#)

## 15.2.2 Backing Up Your Teaming Data

Kablink Teaming data is stored in the Teaming file repository and in the Teaming database. Make sure that you back up both kinds of Teaming data. In addition, you might want to back up your log files.

- ♦ [“Teaming File Repository” on page 104](#)
- ♦ [“Teaming Database” on page 104](#)
- ♦ [“Teaming and Tomcat Log Files” on page 104](#)

### Teaming File Repository

The default file location for the Kablink Teaming 1.0 file repository varies by platform:

Linux:        /icecore/teamingdata

Windows:    c:\teaming

The default locations for Teaming 2.0 are different, as listed in [Section 3.2.4, “Teaming Installation Locations,” on page 26](#), but the Teaming Installation program does not move the data as part of the update process. If you have performed an Advanced installation and have distributed different types of Teaming data to different locations, check the `installer.xml` file located in the same directory with the Teaming 1.0 Installation program to make sure that you have backed up all different types of Teaming data.

### Teaming Database

The default database locations have remained the same from Kablink Teaming 1.0 to Kablink Teaming 2.0, as listed in [Section 3.5.3, “Database Location,” on page 30](#). However, if your database administrator created the Teaming database in a different location, either on the Teaming server or on a remote server, you need to know where it is and make sure that it is backed up before you perform the Teaming update. Check the `installer.xml` file for the location, if necessary.

### Teaming and Tomcat Log Files

The update process eliminates all existing Teaming and Tomcat log files. If you want to retain these log files, copy them to a location outside of the Teaming software directory structure.



**Linux:**        /opt/icecore/liferay-portal-tomcat-version-jdk5-version/  
                        webapps/ssf/WEB-INF/logs

**Windows:** c:\icecore\liferay-portal-tomcat-version-jdk5-version\  
                        webapps\ssf\WEB-INF\logs

**Linux:** `/opt/icecore/liferay-portal-tomcat-version-jdk5-version/logs`


**Windows:** `c:\icecore\liferay-portal-tomcat-version-jdk5-version\logs`

After confirming that you have backed up your Kablink Teaming data, the Teaming Installation program performs either a Basic installation or an Advanced installation of Teaming 2.0. As defaults, it uses the configuration information stored in the `installer.xml` file. In preparation for the update, review [Chapter 3, “Planning a Basic Teaming Installation,” on page 23](#) and fill out the [Basic Teaming Installation Summary Sheet](#). If you performed an Advanced installation for Teaming 1.0, review [Chapter 8, “Planning an Advanced Teaming Installation,” on page 75](#) and fill out the [Advanced Teaming Installation Summary Sheet](#).

When you update a single-server Kablink Teaming installation from version 1.0 to version 2.0, the Teaming Installation program can perform the entire update in a single process, unless the Teaming site uses an Oracle database.

- If you need assistance with this task, see the detailed installation instructions for the platform where you are updating Teaming:

- 6** Accept the License Agreement, then click *Next*.



Because you provided your Teaming 1.0 `installer.xml` file in the directory with the Teaming Installation program, the *Update software and settings* installation option is selected by default.

- 7 Click *Next* to continue.
- 8 Click *Yes* to let the Installation program know that you have stopped Teaming.
- 9 Select the check box to let the Installation program know that you have backed up all of your Teaming data, then click *Next*.
- 10 Select *Basic* or *Advanced*, depending on the type of Teaming installation you are updating, then click *Next*.
- 11 Continue through the installation process using the configuration information gathered on the *Installation Summary Sheet*.
- 12 Click *Install* when you are ready to perform the update.

The Installation program might seem to pause at this point. It needs to update tables and indexes in the Teaming database. If you have a large database, this process can be time consuming.
- 13 Click *Finish* when the update is completed.
- 14 Start Teaming 2.0.

Linux: New command:

```
/etc/init.d/teaming start
```

For more information, see [Section 4.1.6, “Starting Teaming on Linux,” on page 52](#).

Windows: Same command, different directory:

```
c:\icecore\apache-tomcat-version\bin\startup.bat
```

---

**NOTE:** The default locations for Teaming 2.0 are different, as listed in [Section 3.2.4, “Teaming Installation Locations,” on page 26](#), but the Teaming Installation program does not move it as part of the update process.

---

For more information, see [Section 4.2.4, “Running Teaming as a Windows Service,” on page 57](#) and [Section 4.2.5, “Running Teaming as a Windows Application,” on page 58](#).

When you start Teaming for the first time after the update, it takes longer to start than usual because data in the Teaming database must be updated before the Teaming site is ready to use.

- 15 Skip to [Section 15.5, “Performing Post-Update Tasks,” on page 109](#).

---

**IMPORTANT:** The post-update tasks include:

- ♦Resetting custom forms, views, and workflows

- ♦Reindexing your Teaming site
- ♦Updating LDAP synchronization settings

You must perform the post-update tasks, or your updated Teaming site does not function correctly.

---

### 15.3.1 Updating an Oracle Database

The Kablink Teaming Installation program can update MySQL and Microsoft SQL databases as part of the Teaming software update, but it cannot update an Oracle database. Therefore, you must manually run the Teaming 2.0 database update script after you have stopped Teaming.

- 1 Change to the directory where the Teaming Installation program is located.
- 2 Unzip the `teaming-2.0.n-sql.zip` file to create the `update-1.0.0-2.0.n` directory  
The `update-1.0.0-2.0.n` directory contains an update script for each type of database (MySQL, Microsoft SQL, and Oracle).

- 3 Run the `update-oracle.sql` script.

```
sqlplus "/ as sysdba"
SQL>spool update-oracle.out;
SQL>@update-oracle;
SQL>quit;
```

- 4 Return to [Section 15.3, “Updating a Single-Server Teaming Site,”](#) on page 105.

## 15.4 Updating a Multiple-Server Teaming Site

If your Kablink Teaming 1.0 system is distributed across multiple servers, the Teaming Installation program can update Teaming components on the Teaming server, but you must manually update any Teaming components that you have placed on remote servers.

- ♦ [Section 15.4.1, “Remote Teaming Database,”](#) on page 107
- ♦ [Section 15.4.2, “Remote Lucene Index Server,”](#) on page 108

### 15.4.1 Remote Teaming Database

In order to update the Kablink Teaming database when it is not located on the Teaming server, you must run the Teaming 2.0 database update script.

- 1 Stop Teaming.
- 2 Change to the directory where the Teaming Installation program is located.
- 3 Unzip the `teaming-2.0.n-sql.zip` file to create the `update-1.0.0-2.0.n` directory  
The `update-1.0.0-2.0.n` directory contains an update script for each type of database (MySQL, Microsoft SQL, and Oracle).
- 4 Copy the script for your database type to the server where the Teaming database is located.
- 5 Use the client utility for your database type to run the script:

```
MySQL:  mysql -uusername -ppassword < /path/update-mysql.sql
```

Microsoft `osql -Uusername -Ppassword -i update-sqlserver.sql`  
SQL: You can also use the script with the [SQL Server Express Utility \(http://www.microsoft.com/downloads/details.aspx?familyid=fa87e828-173f-472e-a85c-27ed01cf6b02&displaylang=en\)](http://www.microsoft.com/downloads/details.aspx?familyid=fa87e828-173f-472e-a85c-27ed01cf6b02&displaylang=en) to update the database.

Oracle: `sqlplus "/ as sysdba"`  
`SQL>spool update-oracle.out;`  
`SQL>@update-oracle`  
`SQL>quit;`

**6** After you have updated the Teaming database:

(Conditional) If your Lucene Index Server is also on a remote server, continue with [Section 15.4.2, “Remote Lucene Index Server,” on page 108.](#)

or

(Conditional) If all Teaming components that need to be updated are on the Teaming server, follow the instructions in [Section 15.3, “Updating a Single-Server Teaming Site,” on page 105.](#)

## 15.4.2 Remote Lucene Index Server

In order to update your Kablink Teaming index when the Lucene Indexing Server is not located on the Teaming server, you need to run the Remote Lucene Server Installation program.

The default location for a remote Lucene index has changed between Teaming 1.0 and Teaming 2.0.

Teaming 1.0: `/opt/icecore/luceneserver`

Teaming 2.0: `/opt/novell/teaming/luceneserver`

Because you need to reindex your Teaming site after performing the update in any case, you can update the Lucene Index Server software in its current location (`/opt/icecore/luceneserver`) or you can install to the new default location (`/opt/novell/teaming/luceneserver`).

- 1 Stop Teaming.
- 2 Stop the Lucene Index Server by using the following command in the directory where the Lucene Index Server is currently installed:

Linux: `./indexserver-stop.sh`

Windows: `indexserver-stop.bat`

- 3 Copy the Remote Lucene Server Installation program and the Teaming license file (`license-key.xml`) from the directory where the Teaming 2.0 Installation program is located to a convenient directory on the server where the remote Lucene Index Server is located.

The name of the Remote Lucene Server Installation program varies by platform:

Linux: `lucene-installer.linux`

Windows: `lucene-installer.exe`

- 4 Start the Remote Lucene Server Installation program.

- 5 Accept the License Agreement, then click *Next*.
- 6 Select *Update software and settings* to install to the current location.  
or  
Select *New installation* to install to the new location.
- 7 Click *Next* to continue.
- 8 Click *Next* to accept the installation location.
- 9 Click *Next* to accept the Java JDK location.
- 10 In the *Host* field, specify the hostname where you are installing the remote Lucene Index Server.
- 11 Change Lucene configuration settings as needed, then click *Next*.  
For information about Lucene configuration settings, see [Section 8.5.2, “Changing Lucene Configuration Settings,” on page 79](#).
- 12 Click *Install* to install the updated Lucene Index Server software.
- 13 Click *Finish* when the update is completed.
- 14 Start the Lucene Index Server.

Linux: `./indexserver-startup.sh`

Windows: `indexserver-startup.bat`

- 15 Now that all remote Teaming components have been updated, follow the instructions in [Section 15.3, “Updating a Single-Server Teaming Site,” on page 105](#).

## 15.5 Performing Post-Update Tasks

After you start Kablink Teaming 2.0, you can access your Teaming site as usual. However, you need to reindex the site and reset some aspects of the interface before you allow users to access the updated site. The reindex process can consume a substantial amount of time for a large Teaming site. The interface reset affects only those definitions and templates that are included with the Teaming product. If you have created custom definitions and templates, they are unaffected by the interface reset.

---


**IMPORTANT:** If you have manually customized any definitions or templates that are included with the Teaming product, back up the files you have modified before performing the interface reset.

---

- 1 Log in to the Teaming site as the Teaming administrator.
- 2 Click *Manage > Site Administration > Form and View Designer*, click *Reset*, then click *Close*.


## Form and View Designers

### Public Form and View definitions




- 3 On the Site Administration page, click *Manage Workspace and Folder Templates*, click *Reset*, then click *Close*.

## Manage Workspace and Folder Templates



- 4 On the Site Administration page, click *Manage the Search Index*, select the *Home Workspace*, then click *OK*.

## Manage the Search Index



- 5 When the indexing is completed, click *Close*.
- 6 Update the LDAP configuration for your Teaming site.

In Teaming 2.0, if you did not want Teaming to search the entire directory service for users, you specified the search context right after the URL for the LDAP server. In Teaming 2.0, you specify the search context in a separate field. The syntax that worked for Teaming 1.0 does not work for Teaming 2.0.

- 6a On the Site Administration page, click *Configure LDAP*.

## Configure LDAP Synchronization

**ldap://edir.corporate.net**

Configuration for: ldap://edir.corporate.net

[Delete This Configuration](#)

The LDAP server URL format is, ldap://host:port For example: ldap://localhost:389

LDAP server URL:

User DN:

Password:

**Users**

LDAP Attribute That Identifies the User:

In the box below, map the internal identifiers to the LDAP attribute names of the user record. Use the following syntax: internalID=ldapAttrName

lastName=surname  
screenName=cn  
lastName=surname  
firstName=gn  
description=description  
emailAddress=mail  
phone=telephoneNumber  
firstName=givenName

Base DN:

Filter:

☒ Search Subtree

[Delete](#) [Add](#)

**Groups**

[Add](#)

**6b** If the *LDAP server URL* field includes an object context, move that object context down to the *Base DN* field.

**7** Select *Run Immediately*, then click *Apply* to test your change.

**8** If your revised LDAP connection is valid, click *Close*.

Your Teaming 2.0 site is now ready for use.

---

**IMPORTANT:** If Teaming users encounter problems displaying any pages on the Teaming site after the update, simply have them clear the browser cache.

---





# Updating from Kablink Teaming 1.0 to Novell Teaming 2.0

# 16

To update from Kablink® Teaming 1.0 to Novell® Teaming 2.0, you must first purchase Novell Teaming 2.0 in the [Novell Customer Center \(http://www.novell.com/customercenter\)](http://www.novell.com/customercenter). After you obtain the license and download the Novell Teaming 2.0 software, following the instructions in “Updating from Novell Teaming 1.0 to Novell Teaming 2.0” in the *Novell Teaming 2.0 Installation Guide* ([http://www.novell.com/documentation/teaming2/team2\\_inst/data/bookinfo.html](http://www.novell.com/documentation/teaming2/team2_inst/data/bookinfo.html)).

See also [Chapter 17, “Changing from Kablink Teaming 2.0 to Novell Teaming 2.0,”](#) on page 115.



# Changing from Kablink Teaming 2.0 to Novell Teaming 2.0

# 17

To change from Kablink® Teaming 2.0 to Novell® Teaming 2.0, you must first purchase Novell Teaming 2.0 in the [Novell Customer Center \(http://www.novell.com/customercenter\)](http://www.novell.com/customercenter).

After you obtain the license and download the Novell Teaming 2.0 software:

- 1** Stop Kablink Teaming.
- 2** In the directory where you downloaded the Novell Teaming 2.0 software, rename the license file that came with the software to the name `license-key.xml`.  
The Novell Teaming Installation program does not start unless there is a `license-key.xml` file in the same directory with the Installation program.
- 3** Install Novell Teaming using the same options that you used to install Kablink Teaming, as described in:
  - ♦ Chapter 3, “Planning a Basic Teaming Installation,” on page 23
  - ♦ Chapter 8, “Planning an Advanced Teaming Installation,” on page 75
- 4** Start Novell Teaming, as described for the platform where you installed Teaming:
  - ♦ Section 4.1.6, “Starting Teaming on Linux,” on page 52
  - ♦ Section 4.2.4, “Running Teaming as a Windows Service,” on page 57
  - ♦ Section 4.2.5, “Running Teaming as a Windows Application,” on page 58
- 5** Verify that your Teaming license has been updated from Kablink to Novell:
  - 5a** Log in to the Teaming site as the Teaming administrator.
  - 5b** Click *Manage > Site Administration > Reports > Licensing*.
  - 5c** Verify that a Novell Teaming license is now listed.



# Appendixes



- ♦ [Appendix A, “Teaming System Requirements Assistance,” on page 119](#)
- ♦ [Appendix B, “Third-Party Materials,” on page 125](#)



# Teaming System Requirements Assistance

# A

The Kablink® Teaming system requirements include supporting components that might or might not already be installed on your Teaming server. This section helps you meet the Teaming system requirements if you are not already familiar with how to install these supporting components.

- ♦ [Section A.1, “Java Development Kit,” on page 119](#)
- ♦ [Section A.2, “MySQL Database Server,” on page 121](#)

## A.1 Java Development Kit

The Kablink Teaming software runs inside a Java Virtual Machine (JVM). At present, Teaming requires a Java Development Kit (JDK) not a Java Runtime Environment (JRE\*) in order to run properly. You can use either the Sun JDK or the IBM JDK. Follow the instructions in the section below for your operating system and JDK preference:

- ♦ [Section A.1.1, “Sun JDK on Linux,” on page 119](#)
- ♦ [Section A.1.2, “IBM JDK on Linux,” on page 120](#)
- ♦ [Section A.1.3, “Sun JDK on Windows,” on page 120](#)

### A.1.1 Sun JDK on Linux

- 1 Go to the following URL:  
[Java SE Downloads \(http://java.sun.com/javase/downloads/index.jsp\)](http://java.sun.com/javase/downloads/index.jsp)  
The update you need is listed as “JDK 6 Update *nn*.”
- 2 Click *Download* next to this update.
- 3 In the *Platform* field, select *Linux* or *Linux x64* depending on the processor in your Teaming server.
- 4 Select *I agree...*, then click *Continue* to accept Sun’s License Agreement.
- 5 Click the `jdk-6unn-linux-version-rpm.bin` file., then save the file to an empty temporary directory on your Linux server.
- 6 As the `root` user, change to that temporary directory, then use the following command to make sure that the download arrived safely:  

```
ls -l
```

  
You should see a file named `jdk-6unn-linux-version-rpm.bin`.
- 7 Change the permissions on the file to include execute permissions:  

```
chmod +x jdk-6unn-linux-version-rpm.bin
```
- 8 Run the self-extracting file:  

```
./jdk-6unn-linux-version-rpm.bin
```
- 9 Scroll through the License Agreement, then enter `y` to accept it.

This creates a file named `jdk-6unn-linux-version.rpm`, and a directory named `/usr/java/jdk.1.6.0_nn` with the Sun JDK software in it.

The Sun JDK is now installed on your Linux server.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Java JDK Location* on the [Basic Teaming Installation Summary Sheet](#), specify the directory where you install the JDK. The Teaming Installation program prompts you for this location.

---

### A.1.2 IBM JDK on Linux

The IBM JDK is available with SUSE® Linux Enterprise Server (SELS) 10. You can install it using YaST.

- 1 In YaST, click *Software > Software Management*.
- 2 In the *Search* field, type `ibm`, then click *Search*.
- 3 Select *Java 5 SDK, Standard Edition* (`java-1_5_0-ibm-devel`), then click *Accept*.
- 4 Click *Continue* to accept the suggested dependencies, then click *No* because you don't need any more packages.
- 5 Exit YaST.

This creates a directory named `/usr/lib/jvm/java-1_5_0-ibm-1.5.0_sr3` with the IBM JDK software in it.

---

#### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Java JDK Location* on the [Basic Teaming Installation Summary Sheet](#), specify the directory where you install the JDK. The Teaming Installation program prompts you for this location.

---

### A.1.3 Sun JDK on Windows

- 1 Go to the following URL:  
[Java SE Downloads \(http://java.sun.com/javase/downloads/index.jsp\)](http://java.sun.com/javase/downloads/index.jsp)  
The update you need is listed as “JDK 6 Update *nn*.”
- 2 Click *Download* next to this update.
- 3 In the *Platform* field, select *Windows* or *Windows x64* depending on the processor in your Teaming server.
- 4 Select *I agree...*, then click *Continue* to accept Sun's License Agreement.
- 5 Click the `jdk-6unn-windows-version.exe` file., then save the file to an empty temporary directory on your Windows server.
- 6 Change to that temporary directory, then run the downloaded executable.

This creates a directory named `c:\Program Files\Java\jdk6unn` with the Sun JDK software in it.

The Sun JDK is now installed on your Windows server.



Under *Java JDK Location* on the [Basic Teaming Installation Summary Sheet](#), specify the directory where you install the JDK. The Teaming Installation program prompts you for this location.

---

## A.2 MySQL Database Server

- ♦ [Section A.2.1, “MySQL on Linux,” on page 121](#)
- ♦ [Section A.2.2, “MySQL on Windows,” on page 123](#)

### A.2.1 MySQL on Linux

Depending on the options you select when installing Open Enterprise Server 2 and SUSE Linux Enterprise Server (SLES), the MySQL database server might be installed along with the operating system. Check for the following directory:

```
/usr/bin/mysql
```

If the `/usr/bin/mysql` directory does not exist, you need to install the MySQL database server. If MySQL is already installed, you still need to configure it for use with Teaming.

- ♦ [“Installing MySQL on SUSE Linux Enterprise Server 11” on page 121](#)
- ♦ [“Installing MySQL on Open Enterprise Server 2 and SUSE Linux Enterprise Server 10” on page 121](#)
- ♦ [“Configuring MySQL” on page 122](#)
- ♦ [“Learning More about MySQL” on page 122](#)

#### Installing MySQL on SUSE Linux Enterprise Server 11

- 1 In YaST, click *Software > Software Management*.
- 2 In the *Search* field, type `mysql`, then click *Search*.
- 3 Select *mysql*, then click *Accept*.
- 4 Click *Continue* to resolve dependencies.
- 5 Click *Continue* to acknowledge package support status.  
MySQL is then installed from the SLES 11 media.
- 6 Continue with [“Configuring MySQL” on page 122](#).

#### Installing MySQL on Open Enterprise Server 2 and SUSE Linux Enterprise Server 10

- 1 In your Web browser, go to the following URL:  
[MySQL 5.1 Downloads \(http://dev.mysql.com/downloads/mysql/5.1.html\)](http://dev.mysql.com/downloads/mysql/5.1.html)
- 2 Scroll down, then click the type of Linux operating system you are using.
- 3 Click *Download* on the *Server* line.
- 4 Save the `.tar.gz` file to a convenient temporary directory.
- 5 Extract the contents of the file, then install the MySQL database server software.

- 6 Repeat **Step 3** through **Step 5** for the *Client* line to download and install the MySQL client.
- 7 Continue with **Configuring MySQL**.

## Configuring MySQL

When MySQL is initially installed, it is not configured with an administrator password, nor is it configured to start automatically. Follow the steps below to set up the MySQL database server for use with Teaming:

- 1 In YaST, click *System > System Services*.
- 2 Scroll to and select the MySQL service, then click *Enable*.
- 3 Click *Continue* to install dependencies, then click *OK* to close the status box.
- 4 Click *Finish > Yes*, then exit YaST.
- 5 In a terminal window, become the `root` user.
- 6 To verify that the MySQL database server has started, use the following command:

```
ps -eaf | grep mysql
```

You should see MySQL processes running.

- 7 Set the administrator password for the MySQL database server:

```
mysqladmin -u root password new_password
```

This command changes the password for the MySQL `root` user, which is the default administrator username for the MySQL database server. This command is part of the MySQL client package.

---

**IMPORTANT:** The MySQL `root` username is not the same as the Linux `root` user. The Linux `root` user has a password established for it when you install Linux. In a parallel fashion, the MySQL `root` user needs to have a password established for it when you install MySQL.

---

---

## BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Database Credentials* on the **Basic Teaming Installation Summary Sheet**, specify the MySQL administrator password. The Teaming Installation program prompts you for this information.

---

## Learning More about MySQL

The following are some basic and useful MySQL commands:

Action	Command
Stop MySQL	<code>/etc/initd/mysql stop</code>
Start MySQL	<code>/etc/initd/mysql start</code>
Show MySQL status	<code>mysqladmin -u root -p extended-status</code>

If you want to administer MySQL using a GUI interface, you can download tools from:

[MySQL GUI Tools Downloads \(http://dev.mysql.com/downloads/gui-tools/5.0.html\)](http://dev.mysql.com/downloads/gui-tools/5.0.html)

For more information about MySQL, see:

## A.2.2 MySQL on Windows

- 1 In your Web browser, go to the following URL:  
[MySQL 5.1 Downloads \(http://dev.mysql.com/downloads/mysql/5.1.html\)](http://dev.mysql.com/downloads/mysql/5.1.html)
- 2 Scroll down if necessary, then click the type of Windows operating system you are using (32-bit or 64-bit).
- 3 On the *Windows Essentials* line, click *Download*.
- 4 Click *Save File*, browse to and select a convenient temporary directory, then click *Save*.
- 5 In Windows Explorer, browse to the directory where you saved the MySQL .exe file.
- 6 Double-click the MySQL .exe file to start the MySQL Setup Wizard.
- 7 Follow the on-line instructions to install the MySQL software on the Windows server, then continue with configuring the server.
- 8 Unless you are already familiar with configuring MySQL on a Windows server, select *Standard Configuration*, then click *Next*.
- 9 Select *Include Bin Directory in Windows PATH*, then click *Next*.
- 10 Set the MySQL root user password, then click *Next*.

---

### BASIC TEAMING INSTALLATION SUMMARY SHEET

---

Under *Database Credentials* on the [Basic Teaming Installation Summary Sheet](#), specify the MySQL administrator password. The Teaming Installation program prompts you for this information.

---

- 11 Click *Execute* to configure the MySQL database server, then click *Finish*.  
Some messages report the status of your MySQL installation.
- 12 To monitor the MySQL database server, click *Start > All Programs*, then click *MySQL > MySQL Server 5.1 > MySQL Command Line Client*.



# Third-Party Materials

# B

- ♦ Section B.1, “ANTLR 3 License,” on page 125
- ♦ Section B.2, “Colt License Agreement,” on page 126
- ♦ Section B.3, “Dom4j License,” on page 126
- ♦ Section B.4, “iCal4j License,” on page 127
- ♦ Section B.5, “ICU4J license (ICU4J 1.3.1 and later),” on page 127
- ♦ Section B.6, “Java Portlet Specifications 1.0: JSR 168,” on page 128
- ♦ Section B.7, “Java Transaction API (JTA) 1.0.16,” on page 128
- ♦ Section B.8, “JavaServer Pages Standard Tag Library (JSLT) 1.0.5,” on page 129
- ♦ Section B.9, “JAXEN License,” on page 130
- ♦ Section B.10, “Jung,” on page 130

## B.1 ANTLR 3 License

Copyright (c) 2003-2008, Terence Parr

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met

- ♦ Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- ♦ Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- ♦ Neither the name of the author nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## B.2 Colt License Agreement

### Packages `cern.colc*`, `cern.jet*`, `cern.clhep`

Copyright (c) 1999 CERN - European Organization for Nuclear Research.

Permission to use, copy, modify, distribute and sell this software and its documentation for any purpose is hereby granted without fee, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation. CERN makes no representations about the suitability of this software for any purpose. It is provided “as is” without expressed or implied warranty.

### Packages `hep.aida.*`

Written by Pavel Binko, Dino Ferrero Merlino, Wolfgang Hoeschek, Tony Johnson, Andreas Pfeiffer, and others. Check the FreeHEP home page for more info. Permission to use and/or redistribute this work is granted under the terms of the LGPL License, with the exception that any usage related to military applications is expressly forbidden. The software and documentation made available under the terms of this license are provided with no warranty.

## B.3 Dom4j License

Copyright 2001-2005 (C) MetaStuff, Ltd. All Rights Reserved.

Redistribution and use of this software and associated documentation (“Software”), with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain copyright statements and notices. Redistributions must also contain a copy of this document.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. The name “DOM4J” must not be used to endorse or promote products derived from this Software without prior written permission of MetaStuff, Ltd. For written permission, please contact [dom4j-info@metastuff.com](mailto:dom4j-info@metastuff.com).
4. The name “DOM4J” must not be used to endorse or promote products derived from this Software without prior written permission of MetaStuff, Ltd. For written permission, please contact [dom4j-info@metastuff.com](mailto:dom4j-info@metastuff.com).
5. Products derived from this Software may not be called “DOM4J” nor may “DOM4J” appear in their names without prior written permission of MetaStuff, Ltd. DOM4J is a registered trademark of MetaStuff, Ltd.
6. Due credit should be given to the DOM4J Project (<http://www.dom4j.org>).

THIS SOFTWARE IS PROVIDED BY METASTUFF, LTD. AND CONTRIBUTORS “AS IS” AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL METASTUFF, LTD. OR ITS CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY

OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Copyright 2001-2005 (C) MetaStuff, Ltd. All Rights Reserved.

## **B.4 iCal4j License**

Copyright (c) 2008, Ben Fortuna

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- ♦ Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- ♦ Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- ♦ Neither the name of Ben Fortuna nor the names of any other contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## **B.5 ICU4J license (ICU4J 1.3.1 and later)**

COPYRIGHT AND PERMISSION NOTICE

Copyright (c) 1995-2001 International Business Machines Corporation and others

All rights reserved.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, provided that the above copyright notice(s) and this permission notice appear in all copies of the Software and that both the above copyright notice(s) and this permission notice appear in supporting documentation.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OF THIRD PARTY RIGHTS. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR HOLDERS INCLUDED IN THIS NOTICE BE LIABLE FOR ANY CLAIM, OR ANY SPECIAL INDIRECT OR CONSEQUENTIAL DAMAGES, OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Except as contained in this notice, the name of a copyright holder shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization of the copyright holder.

## **B.6 Java Portlet Specifications 1.0: JSR 168**

Copyright 1994-2009 Sun Microsystems, Inc. All Rights Reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- ♦ Redistribution of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- ♦ Redistribution in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

Neither the name of Sun Microsystems, Inc. or the names of contributors may be used to endorse or promote products derived from this software without specific prior written permission.

This software is provided "AS IS," without a warranty of any kind. ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE HEREBY EXCLUDED. SUN MICROSYSTEMS, INC. ("SUN") AND ITS LICENSORS SHALL NOT BE LIABLE FOR ANY DAMAGES SUFFERED BY LICENSEE AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THIS SOFTWARE OR ITS DERIVATIVES. IN NO EVENT WILL SUN OR ITS LICENSORS BE LIABLE FOR ANY LOST REVENUE, PROFIT OR DATA, OR FOR DIRECT, INDIRECT, SPECIAL, CONSEQUENTIAL, INCIDENTAL OR PUNITIVE DAMAGES, HOWEVER CAUSED AND REGARDLESS OF THE THEORY OF LIABILITY, ARISING OUT OF THE USE OF OR INABILITY TO USE THIS SOFTWARE, EVEN IF SUN HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

## **B.7 Java Transaction API (JTA) 1.0.16**

Copyright 1994-2009 Sun Microsystems, Inc. All Rights Reserved.



Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- ♦ Redistribution of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- ♦ Redistribution in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

Neither the name of Sun Microsystems, Inc. or the names of contributors may be used to endorse or promote products derived from this software without specific prior written permission.

This software is provided “AS IS,” without a warranty of any kind. ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE HEREBY EXCLUDED. SUN MICROSYSTEMS, INC. (“SUN”) AND ITS LICENSORS SHALL NOT BE LIABLE FOR ANY DAMAGES SUFFERED BY LICENSEE AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THIS SOFTWARE OR ITS DERIVATIVES. IN NO EVENT WILL SUN OR ITS LICENSORS BE LIABLE FOR ANY LOST REVENUE, PROFIT OR DATA, OR FOR DIRECT, INDIRECT, SPECIAL, CONSEQUENTIAL, INCIDENTAL OR PUNITIVE DAMAGES, HOWEVER CAUSED AND REGARDLESS OF THE THEORY OF LIABILITY, ARISING OUT OF THE USE OF OR INABILITY TO USE THIS SOFTWARE, EVEN IF SUN HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

## **B.8 JavaServer Pages Standard Tag Library (JSLT) 1.0.5**

Copyright 1994-2009 Sun Microsystems, Inc. All Rights Reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- ♦ Redistribution of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- ♦ Redistribution in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

Neither the name of Sun Microsystems, Inc. or the names of contributors may be used to endorse or promote products derived from this software without specific prior written permission.

This software is provided “AS IS,” without a warranty of any kind. ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE HEREBY EXCLUDED. SUN MICROSYSTEMS, INC. (“SUN”) AND ITS LICENSORS SHALL NOT BE LIABLE FOR ANY DAMAGES SUFFERED BY LICENSEE AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THIS SOFTWARE OR ITS DERIVATIVES. IN NO EVENT WILL SUN OR ITS LICENSORS BE LIABLE FOR ANY LOST REVENUE, PROFIT OR DATA, OR FOR DIRECT, INDIRECT, SPECIAL, CONSEQUENTIAL, INCIDENTAL OR PUNITIVE DAMAGES, HOWEVER CAUSED AND REGARDLESS OF

THE THEORY OF LIABILITY, ARISING OUT OF THE USE OF OR INABILITY TO USE THIS SOFTWARE, EVEN IF SUN HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

## B.9 JAXEN License

Copyright (C) 2000-2002 Bob McWhirter & James Strachan.

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions, and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions, and the disclaimer that follows these conditions in the documentation and/or other materials provided with the distribution.
3. The name “Jaxen” must not be used to endorse or promote products derived from this software without prior written permission. For written permission, please contact [license@jaxen.org](mailto:license@jaxen.org).
4. Products derived from this software may not be called “Jaxen,” nor may “Jaxen” appear in their name, without prior written permission from the Jaxen Project Management ([pm@jaxen.org](mailto:pm@jaxen.org)).

In addition, we request (but do not require) that you include in the end-user documentation provided with the redistribution and/or in the software itself an acknowledgement equivalent to the following:

“This product includes software developed by the Jaxen Project (<http://www.jaxen.org>).”

Alternatively, the acknowledgment may be graphical using the logos available at <http://www.jaxen.org>.

THIS SOFTWARE IS PROVIDED “AS IS” AND ANY EXPRESSED OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE Jaxen AUTHORS OR THE PROJECT CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

This software consists of voluntary contributions made by many individuals on behalf of the Jaxen Project and was originally created by bob mcwhirter ([bob@werken.com](mailto:bob@werken.com)) and James Strachan ([jstrachan@apache.org](mailto:jstrachan@apache.org)). For more information on the Jaxen Project, please see <http://www.jaxen.org>.

## B.10 Jung

THE JUNG LICENSE

Copyright (c) 2003-2004, Regents of the University of California and the JUNG Project

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- ♦ Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- ♦ Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- ♦ Neither the name of the University of California nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

