

Novell Cluster Services™ NetWare to Linux Conversion Guide

Open Enterprise Server 11

April 30, 2012

Novell.

Legal Notices

Novell, Inc., makes no representations or warranties with respect to the contents or use of this documentation, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc., reserves the right to revise this publication and to make changes to its content, at any time, without obligation to notify any person or entity of such revisions or changes.

Further, Novell, Inc., makes no representations or warranties with respect to any software, and specifically disclaims any express or implied warranties of merchantability or fitness for any particular purpose. Further, Novell, Inc., reserves the right to make changes to any and all parts of Novell software, at any time, without any obligation to notify any person or entity of such changes.

Any products or technical information provided under this Agreement may be subject to U.S. export controls and the trade laws of other countries. You agree to comply with all export control regulations and to obtain any required licenses or classification to export, re-export or import deliverables. You agree not to export or re-export to entities on the current U.S. export exclusion lists or to any embargoed or terrorist countries as specified in the U.S. export laws. You agree to not use deliverables for prohibited nuclear, missile, or chemical biological weaponry end uses. See the [Novell International Trade Services Web page \(http://www.novell.com/info/exports/\)](http://www.novell.com/info/exports/) for more information on exporting Novell software. Novell assumes no responsibility for your failure to obtain any necessary export approvals.

Copyright © 2010–2012 Novell, Inc. All rights reserved. No part of this publication may be reproduced, photocopied, stored on a retrieval system, or transmitted without the express written consent of the publisher.

Novell, Inc.
1800 South Novell Place
Provo, UT 84606
U.S.A.
www.novell.com

Online Documentation: To access the latest online documentation for this and other Novell products, see the [Novell Documentation Web page \(http://www.novell.com/documentation/\)](http://www.novell.com/documentation/).

Novell Trademarks

For Novell trademarks, see [the Novell Trademark and Service Mark list \(http://www.novell.com/company/legal/trademarks/tmlist.html\)](http://www.novell.com/company/legal/trademarks/tmlist.html).

Third-Party Materials

All third-party trademarks are the property of their respective owners.

Contents

About This Guide	7
1 Planning the Cluster Conversion	9
1.1 Supported Conversion Paths	10
1.2 Supported Mixed-Node Clusters	10
1.3 SBD Devices Must Be Marked as Shareable for Clustering	11
1.4 Syntax Translation Issues for Load and Unload Scripts	11
1.5 Adding a New NetWare Node to a Mixed-Node Cluster	11
1.6 Converting Multiple NetWare Cluster Nodes to OES 11	12
1.7 Converting Nodes that Contain the eDirectory Master Replica	12
1.8 Failing Over Service Cluster Resources in Mixed-Node Clusters	12
1.9 Failing Over Data Cluster Resources in Mixed-Node Clusters	12
1.10 Using Resources in Mixed-Node Clusters	13
1.11 Managing File Systems in Mixed-Node Clusters	13
1.12 Using Novell iManager in Mixed-Node Clusters	13
1.13 Using Novell Remote Manager Is Not Supported in Mixed-Node Clusters	14
1.14 Using ConsoleOne Is Not Supported in Mixed-Node Clusters	14
1.15 Using the Monitoring Function Is Not Supported in Mixed-Node Clusters	14
2 Planning the Conversion of Cluster Resources	15
3 Planning the Conversion of Load and Unload Scripts	19
3.1 Translation of Cluster Resource Scripts for Mixed NetWare and Linux Clusters	19
3.2 Comparing Script Length Limits for NetWare and Linux	20
3.3 Comparing Script Commands for NetWare and Linux	20
3.4 Comparing Master IP Address Scripts	21
3.4.1 Master IP Address Resource Load Script	21
3.4.2 Master IP Address Resource Unload Script	22
3.5 Comparing NSS Pool Resource Scripts	22
3.5.1 NSS Pool Resource Load Script	22
3.5.2 NSS Pool Resource Unload Script	23
3.6 Comparing File Access Protocol Resource Script Commands	23
3.6.1 File Access Protocol Resource Load Scripts	24
3.6.2 File Access Protocol Resource Unload Scripts	24
3.7 Customizing the Translation Syntax for Converting Load and Unload Scripts	25
3.8 Adding Monitoring Scripts on Linux	26
4 Converting NetWare 6.5 Clusters to OES 11	27
4.1 Converting NetWare Cluster Nodes to OES 11 (Rolling Cluster Conversion)	27
4.2 Adding New OES 11 Nodes to Your NetWare Cluster	30
4.3 Removing NetWare Nodes from the Cluster	32
4.4 Finalizing the Cluster Conversion	33

5	Novell AFP	35
6	Apache Web Server	37
6.1	Prerequisites	37
6.2	Converting the Apache Cluster Resource	37
6.3	Additional Information	40
6.3.1	Apache 2 Manual	40
6.3.2	Virtual Hosts Support	40
7	Novell Archive and Version Services	41
7.1	Prerequisites	41
7.2	Copying Database Files from MySQL to PostgreSQL	41
8	eDirectory Server Certificates	43
8.1	Server Certificate Changes in OES 11	43
8.2	Using Internal Certificates in a Cluster	44
8.3	Using External Certificates in a Cluster	44
9	Novell CIFS	45
10	Novell Distributed File Services VLDB	47
10.1	Cluster Migrating the Shared NSS Volume for the VLDB	47
10.2	Adding a Linux Server as a Replica Site	48
11	DHCP Server	49
11.1	Setting Up Novell DHCP on OES 11	49
11.2	Prerequisites for Migration	49
11.3	Migrating the DHCP Configuration from NetWare to Linux Clusters in the Same Tree	49
11.4	Post-Migration Tasks	50
12	DNS Server	51
12.1	Prerequisites for Migration	51
12.2	Migrating the DNS Configuration from NetWare to Linux Clusters in the Same Tree	51
12.3	Post-Migration Tasks	51
13	Novell iPrint	53
13.1	Installing iPrint on the OES 11 Nodes	53
13.2	Setting Up iPrint on the OES 11 Nodes	53
13.2.1	Preparing the OES 11 Nodes for iPrint	54
13.2.2	Setting Up iPrint on the OES 11 iPrint Cluster Resource	55
13.2.3	Setting Up Preferred Nodes for the OES 11 iPrint Cluster Resource	55
13.2.4	Editing the Load and Unload Scripts for the OES 11 iPrint Cluster Resource	55
13.2.5	Verifying the Status of the iPrint Setup	56
13.3	Migrating the iPrint Cluster Resource from NetWare to OES 11	56
13.4	Finalizing the Cluster Conversion	57
13.5	Additional Information	57

14 MySQL	59
14.1 Prerequisites for Clustering MySQL	60
14.2 Installing and Enabling MySQL	60
14.3 Creating an LVM Volume Group and Logical Volume	62
14.3.1 Sample Values	63
14.3.2 Setting Up the VG and LV (Overview)	64
14.3.3 Setting up the VG and LV (Detailed)	64
14.4 Configuring MySQL on the LVM Logical Volume	68
14.5 Cluster-Enabling MySQL on the Logical Volume	69
14.6 File Location	72
14.7 Security Considerations for the MySQL Configuration	73
14.7.1 MySQL Ports	73
14.7.2 Securing MySQL	73
14.8 Additional Information	74
15 QuickFinder Server	75
15.1 Prerequisites	75
15.2 Setting Up QuickFinder Server on Linux Cluster Nodes	75
15.3 Migrating QuickFinder Data from NetWare to Linux	76
15.4 Post-Migration Considerations	77
15.5 Searching the Cluster Volume	78
16 Novell Storage Services Pools	79
16.1 NSS Pool Cluster Migration	79
16.2 NSS File System Migration to NCP Volumes or Linux POSIX File Systems	79
16.3 Estimated Time Taken to Build the Trustee File on Linux	79
A Documentation Updates	81
A.1 April 30, 2012	81
A.1.1 Novell Storage Services Pools	81
A.1.2 Planning the Conversion of Load and Unload Scripts	81
A.2 January 31, 2012	82
A.2.1 Converting NetWare 6.5 Clusters to OES 11	82
A.2.2 Planning the Cluster Conversion	82

About This Guide

This guide describes how to convert Novell Cluster Services cluster nodes and resources from NetWare 6.5 Support Pack (SP) 8 (with the latest patches) to Novell Open Enterprise Server (OES) 11.

This guide includes the following sections:

- ♦ [Chapter 1, “Planning the Cluster Conversion,” on page 9](#)
- ♦ [Chapter 2, “Planning the Conversion of Cluster Resources,” on page 15](#)
- ♦ [Chapter 3, “Planning the Conversion of Load and Unload Scripts,” on page 19](#)
- ♦ [Chapter 4, “Converting NetWare 6.5 Clusters to OES 11,” on page 27](#)
- ♦ [Chapter 5, “Novell AFP,” on page 35](#)
- ♦ [Chapter 6, “Apache Web Server,” on page 37](#)
- ♦ [Chapter 7, “Novell Archive and Version Services,” on page 41](#)
- ♦ [Chapter 8, “eDirectory Server Certificates,” on page 43](#)
- ♦ [Chapter 9, “Novell CIFS,” on page 45](#)
- ♦ [Chapter 10, “Novell Distributed File Services VLDB,” on page 47](#)
- ♦ [Chapter 11, “DHCP Server,” on page 49](#)
- ♦ [Chapter 12, “DNS Server,” on page 51](#)
- ♦ [Chapter 13, “Novell iPrint,” on page 53](#)
- ♦ [Chapter 14, “MySQL,” on page 59](#)
- ♦ [Chapter 15, “QuickFinder Server,” on page 75](#)
- ♦ [Chapter 16, “Novell Storage Services Pools,” on page 79](#)
- ♦ [Appendix A, “Documentation Updates,” on page 81](#)

Audience

This guide is intended for Novell Cluster Services administrators and other administrators that are responsible for clustered services and data. It is assumed that readers of this guide have a basic understanding of Novell Cluster Services and of the services and file systems that are being clustered.

Feedback

We want to hear your comments and suggestions about this manual and the other documentation included with this product. Please use the User Comments feature at the bottom of each page of the online documentation.

Documentation Updates

For the most recent version of the *OES 11: Novell Cluster Services NetWare to Linux Conversion Guide*, visit the [OES 11 documentation Web site \(http://www.novell.com/documentation/oes11/cluster-services.html#cluster-services\)](http://www.novell.com/documentation/oes11/cluster-services.html#cluster-services).

Additional Documentation

For documentation on Novell Cluster Services and cluster resources management, see the [OES 11 Clustering \(High Availability\) documentation Web site \(http://www.novell.com/documentation/oes11/cluster-services.html#cluster-services\)](http://www.novell.com/documentation/oes11/cluster-services.html#cluster-services).

For information about managing a NetWare cluster, see the “Clustering NetWare Services” list on the [NetWare 6.5 SP8 Clustering \(High Availability\) documentation Web site \(http://www.novell.com/documentation/nw65/cluster-services.html#clust-config-resources\)](http://www.novell.com/documentation/nw65/cluster-services.html#clust-config-resources).

1 Planning the Cluster Conversion

Upgrading a NetWare 6.5 SP8 cluster to Novell Open Enterprise Server (OES) 11 is a multi-phase process referred to as a rolling cluster conversion. This approach lets you keep your cluster up and running and lets your users continue to access cluster resources while the conversion is in progress. During a rolling cluster conversion, one server is converted to OES 11 while the other servers in the cluster continue running NetWare 6.5. Then another server can be converted to OES 11, and then another, until all servers in the cluster have been converted. During the conversion, you can also add OES 11 servers to the cluster, and remove NetWare 6.5 servers from the cluster.

Before you begin a conversion, ensure that your system meets the requirements and caveats described in this section. In addition, your OES 11 nodes and network environment must meet the cluster requirements as described in [“Planning for Novell Cluster Services”](#) in the *OES 11: Novell Cluster Services 2.0 for Linux Administration Guide*.

- ♦ [Section 1.1, “Supported Conversion Paths,” on page 10](#)
- ♦ [Section 1.2, “Supported Mixed-Node Clusters,” on page 10](#)
- ♦ [Section 1.3, “SBD Devices Must Be Marked as Shareable for Clustering,” on page 11](#)
- ♦ [Section 1.4, “Syntax Translation Issues for Load and Unload Scripts,” on page 11](#)
- ♦ [Section 1.5, “Adding a New NetWare Node to a Mixed-Node Cluster,” on page 11](#)
- ♦ [Section 1.6, “Converting Multiple NetWare Cluster Nodes to OES 11,” on page 12](#)
- ♦ [Section 1.7, “Converting Nodes that Contain the eDirectory Master Replica,” on page 12](#)
- ♦ [Section 1.8, “Failing Over Service Cluster Resources in Mixed-Node Clusters,” on page 12](#)
- ♦ [Section 1.9, “Failing Over Data Cluster Resources in Mixed-Node Clusters,” on page 12](#)
- ♦ [Section 1.10, “Using Resources in Mixed-Node Clusters,” on page 13](#)
- ♦ [Section 1.11, “Managing File Systems in Mixed-Node Clusters,” on page 13](#)
- ♦ [Section 1.12, “Using Novell iManager in Mixed-Node Clusters,” on page 13](#)
- ♦ [Section 1.13, “Using Novell Remote Manager Is Not Supported in Mixed-Node Clusters,” on page 14](#)
- ♦ [Section 1.14, “Using ConsoleOne Is Not Supported in Mixed-Node Clusters,” on page 14](#)
- ♦ [Section 1.15, “Using the Monitoring Function Is Not Supported in Mixed-Node Clusters,” on page 14](#)

1.1 Supported Conversion Paths

The NetWare to Linux conversion is supported from NetWare 6.5 SP8 (with the latest patches applied) to OES 11 on the SUSE Linux Enterprise Server (SLES) 11 SP1 operating system. The following conversion paths are supported from NetWare to OES 11:

From this NetWare platform	Interim platform upgrade for all nodes	Before conversion to this platform
NetWare 6.5 SP8	Latest patches applied	OES 11 on SLES 11 SP1
NetWare 6.5 SP7 or earlier	NetWare 6.5 SP8 with the latest patches applied	OES 11 on SLES 11 SP1
NetWare 6.0	NetWare 6.5 SP8 with the latest patches applied	OES 11 on SLES 11 SP1
NetWare 5.1	NetWare 6.5 SP8 with the latest patches applied	OES 11 on SLES 11 SP1

Before converting NetWare 6.5 SP8 clusters to OES 11, you must apply all of the latest service packs and patches. For information, see [“Upgrading NetWare Clusters”](#) in the *NW6.5 SP8: Novell Cluster Services 1.8.5 Administration Guide*.

If you have a NetWare 6.5 SP7 or earlier cluster, you must upgrade all nodes to NetWare 6.5 SP8 (with the latest service packs and patches) before you convert any nodes to OES 11 or add OES 11 nodes to the cluster. For information, see [“Upgrading NetWare Clusters”](#) in the *NW6.5 SP8: Novell Cluster Services 1.8.5 Administration Guide*.

1.2 Supported Mixed-Node Clusters

During the conversion, the intermediate cluster is referred to as a *mixed-node* cluster because the cluster contains both NetWare and Linux nodes. This is a temporary configuration that is supported for the purpose of converting the cluster. It is not supported as a long-term operational state of the cluster.

A mixed-node cluster made up of NetWare 6.5 SP8 nodes and OES 11 nodes is supported for the purpose of converting the cluster from NetWare 6.5 SP8 (with the latest support packs and patches) to OES 11 or later.

A mixed-node cluster made up of NetWare 6.5 SP7 or earlier nodes and OES 11 nodes is not supported.

1.3 SBD Devices Must Be Marked as Shareable for Clustering

Novell Cluster Services for Linux requires that the devices used for the SBD partition be explicitly marked as Shareable for Clustering. When converting a NetWare cluster, ensure that the SBD device, or both devices for a mirrored SBD, are marked as Shareable for Clustering before you add the first Linux node to the cluster.

- 1 Log in to the master NetWare node as the `root` user, then open a terminal console.
- 2 At the console prompt, enter

```
nssmu
```
- 3 In the NSSMU main menu, select *Devices*, then press Enter.
- 4 Select the SBD device.
- 5 If *Shareable for Clustering* is set to *No*, press F6 to share the device.
Wait for the page to refresh. If the change is successful, *Shareable for Clustering* is set to *Yes*.
- 6 If the SBD is mirrored, repeat [Step 4](#) and [Step 5](#) for the device that is used as the SBD mirror.

1.4 Syntax Translation Issues for Load and Unload Scripts

Executing a script that is valid for the NetWare platform is not necessarily recognized on the OES 11 platform. When cluster migrating a resource from a NetWare node to a OES 11 node, the resource's Load script and Unload script need to be translated in-memory while the cluster contains mixed nodes. It is also translated in-memory when the cluster is finally converted from NetWare to Linux. This translation is done by the Cluster Translation Library script (`/opt/novell/ncs/bin/clstrlib.py`). For information about the script translations, see [Chapter 3, "Planning the Conversion of Load and Unload Scripts,"](#) on page 19.

IMPORTANT: If the commands in cluster resource's load or unload scripts are not part of the normal translation library, the cluster resource can end up in a comatose state.

Novell Cluster Services allows you to customize the translation syntax that is used for load and unload scripts in mixed-node clusters by defining them in the `/var/opt/novell/ncs/customized_translation_syntax` file that you create. The `clstrlib.py` script reads the additional translation syntax from the syntax file. For information, see [Section 3.7, "Customizing the Translation Syntax for Converting Load and Unload Scripts,"](#) on page 25.

1.5 Adding a New NetWare Node to a Mixed-Node Cluster

You cannot add additional NetWare nodes to your cluster after adding a new Linux node or changing an existing NetWare cluster node to a Linux cluster node. If you want to add NetWare cluster nodes after converting part of your cluster to Linux, you must first remove the Linux nodes from the cluster by using the `cluster leave` command on them.

1.6 Converting Multiple NetWare Cluster Nodes to OES 11

To concurrently convert multiple NetWare cluster servers to OES 11, we strongly recommend that you use the old NetWare node IP addresses for your Linux cluster servers. You should record the NetWare node IP addresses before converting them to Linux.

If you must assign new node IP addresses to the OES 11 nodes, we recommend that you only convert one node at a time.

If new cluster node IP addresses are required and new server hardware is being used, another option is to shut down the NetWare nodes that are to be removed and then add the new Linux cluster nodes. After adding the new Linux cluster nodes, you can remove the NetWare node's cluster-related objects as described in [Step 5 of Section 4.1, "Converting NetWare Cluster Nodes to OES 11 \(Rolling Cluster Conversion\)," on page 27](#).

IMPORTANT: Failure to follow these recommendations might result in NetWare server abends and Linux server restarts.

1.7 Converting Nodes that Contain the eDirectory Master Replica

When converting NetWare cluster servers to Linux, if the eDirectory master replica is a cluster node, wait to convert it until the end of the rolling cluster conversion. This also applies to a node that is running the Certificate Authority.

1.8 Failing Over Service Cluster Resources in Mixed-Node Clusters

For service cluster resources, the intention is to have a one-time cluster migration of the service from NetWare to OES 11. After you cluster migrate the resource to an OES 11 node, the relocated resource should be cluster migrated only between nodes running the OES 11 platform.

1.9 Failing Over Data Cluster Resources in Mixed-Node Clusters

Pool cluster resources that were created on NetWare cluster nodes and migrated or failed over to Linux cluster nodes can be migrated or failed back to NetWare cluster nodes.

Cluster resources that are created on Linux cluster nodes cannot be migrated or failed over to NetWare cluster nodes. If you need to create a new pool as part of a documented conversion procedure, create the pool on a NetWare node, then cluster migrate it to a Linux node. For more information, see [Section 1.11, "Managing File Systems in Mixed-Node Clusters," on page 13](#).

If you cluster migrate an NSS pool from a NetWare cluster server to a Linux cluster server, it could take several minutes for volume trustee assignments to synchronize between the NSS volumes and the NCP Server on Linux. Users might have limited access to the migrated volumes until after the trustee database is built on Linux.

1.10 Using Resources in Mixed-Node Clusters

In cases where a Linux converted script exceeds the imposed NetWare script size limit of 924 bytes, it is best to avoid bringing the resource online on OES 11 nodes until the final cluster convert command has been run. For information, see [Section 3.2, “Comparing Script Length Limits for NetWare and Linux,”](#) on page 20.

For example, the Linux script for GroupWise exceeds the length limit for NetWare scripts. Therefore, we recommend that you do not online GroupWise resources while running in mixed-node clusters.

1.11 Managing File Systems in Mixed-Node Clusters

In a mixed cluster of NetWare and OES 11 nodes, Linux POSIX file systems as cluster resources cannot be created until the entire cluster had been successfully converted to OES 11. Linux POSIX file systems as cluster resources cannot be migrated or failed over to NetWare cluster nodes.

Only NSS pool cluster resources that are created on a NetWare cluster node can be failed over between Linux and NetWare nodes of a mixed-node cluster.

NetWare-to-Linux failover of NSS pool cluster resources requires that the Linux node be configured for NSS and that the version of NSS supports the NSS media format and features that are currently being used by the NSS pool cluster resource on NetWare.

No storage management functions should be executed in a mixed-node cluster unless you are performing documented steps for the conversion. That is, do not create, delete, expand, or modify the properties for partitions, pools, or volumes for shared resources in the cluster unless the conversion instructions specifically guide you to do so.

WARNING: Attempting to reconfigure shared storage in a mixed cluster can cause data loss.

If you need to configure (or reconfigure) existing shared NSS pools and volumes in a mixed-node cluster, you must temporarily bring down all Linux cluster nodes prior to making changes, then make the configuration changes on a NetWare node. Ensure that the resources are working properly on NetWare before having the Linux cluster nodes rejoin the cluster.

1.12 Using Novell iManager in Mixed-Node Clusters

Use Novell iManager 2.7.4 or later for all cluster administration in the mixed-node cluster. Using the Clusters plug-in to iManager is required to manage the cluster after the first OES 11 node is added to the cluster.

The display of node IDs from the NetWare master node might be incomplete if you use other tools like ConsoleOne and Novell Remote Manager in a mixed-node cluster. However, you can use `cat /admin/Novell/Cluster/NodeConfig.xml` on any cluster node to get the node IDs.

1.13 Using Novell Remote Manager Is Not Supported in Mixed-Node Clusters

Do not use Novell Remote Manager when managing mixed-node clusters. Novell Remote Manager is not supported for cluster management on OES 11.

Because different time formats are used in the NCS Event log for NetWare and Linux, Novell Remote Manager might have difficulty displaying the time of logged events. To avoid this problem in a mixed-node cluster, use iManager to access the NCS Event log.

To reduce any confusion you might have when using Novell Remote Manager, you can unload module `pcluster.nlm` and delete its references in `ldnccs` and `uldnccs`. This removes the *Cluster* tab in Novell Remote Manager.

1.14 Using ConsoleOne Is Not Supported in Mixed-Node Clusters

Do not use ConsoleOne when managing mixed-node clusters. ConsoleOne is not supported for cluster management on OES 11.

1.15 Using the Monitoring Function Is Not Supported in Mixed-Node Clusters

In mixed-node clusters, the Monitor function in Novell Cluster Services for Linux is not available. You cannot enable the Monitor function or modify the Monitor script for cluster resources on the Linux nodes until the conversion is finalized and all nodes in the cluster are running OES 11. During the finalization, the monitor scripts are created automatically for each of the converted cluster resources; however, they are disabled by default. You can enable monitoring for a resource, and modify its monitoring script, as needed.

2 Planning the Conversion of Cluster Resources

In addition to changing the operating system, the software and file systems for various clustered services must be considered in your conversion from NetWare 6.5 to Novell Open Enterprise Server (OES) 11. This section provides an overview of the NetWare 6.5 services and their counterparts in OES 11. Before you begin a conversion, ensure that your system meets the general requirements and caveats described in this section.

Converting cluster resources for OES 11 services from NetWare to Linux might require more than a simple cluster migration from a NetWare node to a Linux node. For example, the service might require that you use Migration Tool to convert the service to Linux. Some services require post-conversion configuration to finalize the conversion. A few OES services on NetWare are not available on OES 11, so you must use the standard Linux service instead.

See [Table 2-1](#) for information about converting cluster resources for NetWare 6.5 SP8 services:

Table 2-1 Guidelines for Converting Service Cluster Resources from NetWare to Linux

Service on NetWare 6.5 SP8	Cluster Migrate the Resource	Converting the Service to OES 11
Apache Web Server	Yes	See Chapter 6, “Apache Web Server,” on page 37.
Apple Filing Protocol (AFP)	Yes	See Chapter 5, “Novell AFP,” on page 35.
Archive and Version Services	No, but you can migrate the database	See Chapter 7, “Novell Archive and Version Services,” on page 41.
CIFS (Windows File Services)	Yes	See Chapter 9, “Novell CIFS,” on page 45.
DFS VLDB (Distributed File Services volume location database)	Yes	See Chapter 10, “Novell Distributed File Services VLDB,” on page 47.
DHCP Server	Yes	See Chapter 11, “DHCP Server,” on page 49.
DNS Server	Yes	See Chapter 12, “DNS Server,” on page 51.
eDirectory	Not clustered, but requires special handling	See Section 1.7, “Converting Nodes that Contain the eDirectory Master Replica,” on page 12.

Service on NetWare 6.5 SP8	Cluster Migrate the Resource	Converting the Service to OES 11
eDirectory Certificate Server	Not clustered, but requires special handling	<p>The Certificate Authority (CA) service is not cluster-enabled for NetWare or OES 11. There are no cluster-specific tasks for the CA itself.</p> <p>The Server Certificate service issues Server Certificate objects that might need to reside on each node in a cluster, depending on the service that is clustered. NetWare and Linux generate certificates differently, so the NetWare server's certificate is not reused for the OES 11 server.</p> <p>See Chapter 8, "eDirectory Server Certificates," on page 43.</p>
exteNd Application Server and MySQL	Not applicable	<p>The exteNd Application Server was discontinued as an install option for NetWare 6.5 SP3. It is not available for Linux.</p> <p>See also MySQL in this table.</p>
FTP	No	<p>Use the Pure-FTPd service for Linux.</p> <p>For information, see "Novell FTP (Pure-FTPd) and OES 11" in the <i>OES 11: Planning and Implementation Guide</i>.</p>
iFolder	No, but you can migrate the settings and data	<p>Novell iFolder 2.1x is not available on OES 11. You must use Novell iFolder 3.x.</p> <p>After you add a Novell iFolder 3.x server to the NetWare cluster and before you finalize the cluster conversion, use iFolder migration procedures to migrate the iFolder 2.1x server configuration and user data from the source NetWare node to the target Linux node. For information, see "Migrating iFolder Services" in the <i>Novell iFolder 3.9 Administration Guide</i>.</p>
iPrint	Yes	See Chapter 13, "Novell iPrint," on page 53.
MySQL	No	<p>Use the MySQL 5.0.x software on OES 11 Linux that is offered under the GPL. A MySQL cluster template is available that uses a shared LVM volume group to store the database.</p> <p>See Chapter 14, "MySQL," on page 59.</p>
NetStorage	Not tested	For information, see " Configuring NetStorage with Novell Cluster Services " in the <i>OES 11: NetStorage Administration Guide for Linux</i> .
NFS	No	Use standard NFS service for Linux.

Service on NetWare 6.5 SP8	Cluster Migrate the Resource	Converting the Service to OES 11
QuickFinder (Server Synchronization Feature)	No, but you can migrate the settings and data	<p>You must create a new cluster resource. QuickFinder 5.0.x is supported only on OES 11. NetWare uses QuickFinder 4.2.0. QuickFinder does not support any automated procedure or scripts for a rolling upgrade from Netware to Linux.</p> <p>Instead of converting the resource, you can migrate the settings from NetWare after you set up a QuickFinder resource on Linux.</p> <p>See Chapter 15, “QuickFinder Server,” on page 75.</p>
NSS pools and volumes	Yes	See Chapter 16, “Novell Storage Services Pools,” on page 79.
Tomcat	No	Use the standard Tomcat 6.x service for Linux.

3 Planning the Conversion of Load and Unload Scripts

You can use a rolling cluster conversion to convert a Novell Cluster Services cluster from NetWare 6.5 SP8 to Novell Open Enterprise Server (OES) 11. This section describes how to prepare for and perform the conversion, and how to manage the temporarily mixed cluster during the conversion.

- ♦ [Section 3.1, “Translation of Cluster Resource Scripts for Mixed NetWare and Linux Clusters,” on page 19](#)
- ♦ [Section 3.2, “Comparing Script Length Limits for NetWare and Linux,” on page 20](#)
- ♦ [Section 3.3, “Comparing Script Commands for NetWare and Linux,” on page 20](#)
- ♦ [Section 3.4, “Comparing Master IP Address Scripts,” on page 21](#)
- ♦ [Section 3.5, “Comparing NSS Pool Resource Scripts,” on page 22](#)
- ♦ [Section 3.6, “Comparing File Access Protocol Resource Script Commands,” on page 23](#)
- ♦ [Section 3.7, “Customizing the Translation Syntax for Converting Load and Unload Scripts,” on page 25](#)
- ♦ [Section 3.8, “Adding Monitoring Scripts on Linux,” on page 26](#)

3.1 Translation of Cluster Resource Scripts for Mixed NetWare and Linux Clusters

Novell Cluster Services includes specialized script translation functionality, called the Cluster Translation Library script (`/opt/novell/ncs/bin/clstrlib.py`), to help NetWare and Linux servers coexist in the same cluster. It provides an automatic translation of the Master IP Address resource and cluster-enabled NSS pool resource load and unload scripts from NetWare to Linux. This functionality is also beneficial as you migrate NetWare cluster servers to Linux.

The Cluster Translation Library reads the NetWare load and unload scripts from eDirectory, converts them, and writes them as Linux load and unload scripts. The Linux load and unload script files are then searched for NetWare-specific command strings, and the command strings are then either deleted or replaced with Linux-specific command strings. Separate Linux-specific commands are also added, and the order of certain lines in the scripts is also changed to function with Linux.

During the rolling conversion, a resource’s Linux load and unload scripts is stored in cache on the Linux cluster node where the resource is mounted. The NetWare script for the resource continues to be stored in eDirectory until the conversion is finalized. The cluster resource name is used in the load and unload script file names. On Linux, scripts are stored in the `/var/opt/novell/ncs/` directory.

IMPORTANT: After the final conversion, you can use the *Properties > Scripts* page in the Clusters plug-in in iManager whenever you make manual changes to the load and unload scripts. The changes are automatically saved to the files.

The normal translations performed by the Cluster Translation Library are described in the following sections:

- [Section 3.3, “Comparing Script Commands for NetWare and Linux,” on page 20](#)
- [Section 3.4, “Comparing Master IP Address Scripts,” on page 21](#)
- [Section 3.5, “Comparing NSS Pool Resource Scripts,” on page 22](#)
- [Section 3.6, “Comparing File Access Protocol Resource Script Commands,” on page 23](#)

IMPORTANT: If the commands in cluster resource’s load or unload scripts are not part of the translation library, the cluster resource can end up in a comatose state.

Novell Cluster Services allows you to customize the translation syntax that is used for load and unload scripts in mixed-platform situations by defining new syntax translations to be used in addition to the normal translations. For information, see [Section 3.7, “Customizing the Translation Syntax for Converting Load and Unload Scripts,” on page 25](#).

3.2 Comparing Script Length Limits for NetWare and Linux

Scripts have different size limits on NetWare and OES 11. In a mixed-node cluster, the scripts for NetWare resources that are cluster migrated to OES 11 nodes are restricted to the NetWare script-size limits until the final `cluster convert` command is issued.

The maximum supported lengths for cluster scripts’ content are as follows:

Script	NetWare 6.5 Resources on NetWare Nodes	NetWare 6.5 Resources on OES 11 Nodes	OES 11 Resources and Converted NetWare Resources After the Final Conversion
Load script	924 bytes	924 bytes	3200 bytes
Unload script	924 bytes	924 bytes	3200 bytes
Monitor script	Not supported	Not supported	3200 bytes

In cases where a Linux converted script exceeds the imposed NetWare script size limit, it is best to avoid bringing the resource online on OES 11 nodes until the final `cluster convert` command has been run.

IMPORTANT: Because the Linux script for GroupWise exceeds the length limit for NetWare scripts, we recommend that you do not online GroupWise resources while running in mixed-node clusters.

3.3 Comparing Script Commands for NetWare and Linux

[Table 3-1](#) identifies some of the NetWare cluster load and unload script commands that the Cluster Translation Library script searches for and the Linux commands that it replaces them with (unless the commands are deleted).

Table 3-1 Cluster Script Command Comparison

Action	NetWare Cluster Command	Linux Cluster Command
Replace	IGNORE_ERROR add secondary ipaddress	ignore_error add_secondary_ipaddress
Replace	IGNORE_ERROR del secondary ipaddress	ignore_error del_secondary_ipaddress
Replace	del secondary ipaddress	ignore_error del_secondary_ipaddress
Replace	add secondary ipaddress	exit_on_error add_secondary_ipaddress
Delete	IGNORE_ERROR NUDP	(deletes the entire line)
Delete	IGNORE_ERROR HTTP	(deletes the entire line)
Replace	nss /poolactivate=	nss /poolact=
Replace	nss /pooldeactivate=	nss /pooldeact=
Replace	mount volume_name VOLID=number	exit_on_error ncpcon mount volume_name=number
Replace	NUDP ADD clusterservername ipaddress	exit_on_error ncpcon bind --ncpservername=ncpservername --ipaddress=ipaddress
Replace	NUDP DEL clusterservername ipaddress	ignore_error ncpcon unbind --ncpservername=ncpservername --ipaddress=ipaddress
Delete	CLUSTER CVSBIND	(deletes the entire line)
Delete	CIFS	(deletes the entire line)

3.4 Comparing Master IP Address Scripts

IMPORTANT: You can modify the Master IP Address of the cluster only after the cluster conversion is finalized. For information, see [“Moving a Cluster or Changing IP Addresses of Cluster Nodes and Resources”](#) in the *OES 11: Novell Cluster Services 2.0 for Linux Administration Guide*.

- ♦ [Section 3.4.1, “Master IP Address Resource Load Script,” on page 21](#)
- ♦ [Section 3.4.2, “Master IP Address Resource Unload Script,” on page 22](#)

3.4.1 Master IP Address Resource Load Script

This section provides examples of the master IP address resource load scripts on NetWare and Linux.

- ♦ [“NetWare” on page 22](#)
- ♦ [“Linux” on page 22](#)

NetWare

```
IGNORE_ERROR set allow ip address duplicates = on
IGNORE_ERROR CLUSTER CVSBIND ADD BCCP_Cluster 10.1.1.175
IGNORE_ERROR NUDP ADD BCCP_Cluster 10.1.1.175
IGNORE_ERROR add secondary ipaddress 10.1.1.175
IGNORE_ERROR HTTPBIND 10.1.1.175 /KEYFILE:"SSL CertificateIP"
IGNORE_ERROR set allow ip address duplicates = off
```

Linux

```
#!/bin/bash
. /opt/novell/ncs/lib/ncsfuns

ignore_error add_secondary_ipaddress 10.1.1.175 -np

exit 0
```

3.4.2 Master IP Address Resource Unload Script

This section provides examples of the master IP address resource unload scripts on NetWare and Linux.

- ♦ [“NetWare” on page 22](#)
- ♦ [“Linux” on page 22](#)

NetWare

```
IGNORE_ERROR HTTPUNBIND 10.1.1.175
IGNORE_ERROR del secondary ipaddress 10.1.1.175
IGNORE_ERROR NUDP DEL BCCP_Cluster 10.1.1.175
IGNORE_ERROR CLUSTER CVSBIND DEL BCCP_Cluster 10.1.1.175
```

Linux

```
#!/bin/bash
. /opt/novell/ncs/lib/ncsfuns
ignore_error del_secondary_ipaddress 10.1.1.175
exit 0
```

3.5 Comparing NSS Pool Resource Scripts

- ♦ [Section 3.5.1, “NSS Pool Resource Load Script,” on page 22](#)
- ♦ [Section 3.5.2, “NSS Pool Resource Unload Script,” on page 23](#)

3.5.1 NSS Pool Resource Load Script

This section provides examples of the NSS pool resource load scripts on NetWare and Linux.

- ♦ [“NetWare” on page 23](#)
- ♦ [“Linux” on page 23](#)

NetWare

```
nss /poolactivate=HOMES_POOL
mount HOMES VALID=254
CLUSTER CVSBIND ADD BCC_CLUSTER_HOMES_SERVER 10.1.1.180
NUDP ADD BCC_CLUSTER_HOMES_SERVER 10.1.1.180
add secondary ipaddress 10.1.1.180
CIFS ADD .CN=BCC_CLUSTER_HOMES_SERVER.OU=servers.O=lab.T=TEST_TREE.
```

Linux

```
#!/bin/bash
. /opt/novell/ncs/lib/ncsfuns
exit_on_error nss /poolact=HOMES_POOL
exit_on_error ncpcon mount HOMES=254
exit_on_error add_secondary_ipaddress 10.1.1.180

exit_on_error ncpcon bind --ncpservername=BCC_CLUSTER_HOMES_SERVER
--ipaddress=10.1.1.180

exit 0
```

3.5.2 NSS Pool Resource Unload Script

This section provides examples of the NSS pool resource unload scripts on NetWare and Linux.

- ♦ [“NetWare” on page 23](#)
- ♦ [“Linux” on page 23](#)

NetWare

```
del secondary ipaddress 10.1.1.180
CLUSTER CVSBIND DEL BCC_CLUSTER_HOMES_SERVER 10.1.1.180
NUDP DEL BCC_CLUSTER_HOMES_SERVER 10.1.1.180
nss /pooldeactivate=HOMES_POOL /overridetype=question
CIFS DEL .CN=BCC_CLUSTER_HOMES_SERVER.OU=servers.O=lab.T=TEST_TREE.
```

Linux

```
#!/bin/bash
. /opt/novell/ncs/lib/ncsfuns

ignore_error ncpcon unbind --ncpservername=BCC_CLUSTER_HOMES_SERVER
--ipaddress=10.1.1.180

ignore_error del_secondary_ipaddress 10.1.1.180
ignore_error nss /pooldeact=HOMES_POOL
exit 0
```

3.6 Comparing File Access Protocol Resource Script Commands

- ♦ [Section 3.6.1, “File Access Protocol Resource Load Scripts,” on page 24](#)
- ♦ [Section 3.6.2, “File Access Protocol Resource Unload Scripts,” on page 24](#)

3.6.1 File Access Protocol Resource Load Scripts

This section provides examples of the file access protocol commands for load scripts on NetWare and Linux.

- ♦ [“NetWare” on page 24](#)
- ♦ [“Linux” on page 24](#)

NetWare

Protocol	Script Command for Load Scripts
NCP	NUDP ADD NCS1_P1_SERVER 10.10.10.194
Novell AFP	AFPBIND ADD NCS1_P1_SERVER 10.10.10.204
Novell CIFS	CIFS ADD .CN=NCS1_P1_SERVER.O=novell.T=CLUSTER.

Linux

Protocol	Script Command for Load Scripts
NCP	<pre># mount the NCP volume exit_on_error ncpcon mount \$NCP_VOLUME=VOL_ID,PATH=\$MOUNT_POINT exit_on_error ncpcon bind --ncpservname=NCS1_P1_SERVER --ipaddress=10.10.10.194</pre>
Novell AFP	<pre>exit_on_error cluster_afp.sh add NCS1_P1_SERVER 10.10.10.204</pre>
Novell CIFS	<pre>exit_on_error novcifs --add --vserver=.CN=NCS1_P1_SERVER.O=novell.T=TREE-188. --ip- addr=<virtual_server_ip_address></pre>

3.6.2 File Access Protocol Resource Unload Scripts

This section provides examples of the Novell AFP commands for unload scripts on NetWare and Linux.

- ♦ [“NetWare” on page 24](#)
- ♦ [“Linux” on page 25](#)

NetWare

Protocol	Script Command for Unload Scripts
NCP	NUDP DEL NCS1_P1_SERVER 10.10.10.194
Novell AFP	AFPBIND DEL NCS1_P1_SERVER 10.10.10.204
Novell CIFS	CIFS DEL .CN=NCS1_P1_SERVER.O=novell.T=TREE-188.

Linux

Protocol	Script Command for Unload Scripts
NCP	<pre>ignore_error ncpcon unbind --ncpservname=NCS1_P1_SERVER --ipaddress=10.10.10.194 # dismount the NCP volume ignore_error ncpcon dismount \$NCP_VOLUME</pre>
Novell AFP	<pre>ignore_error cluster_afp.sh del NCS1_P1_SERVER 10.10.10.204</pre>
Novell CIFS	<pre>ignore_error novcifs --remove --vserver=.CN=NCS1_P1_SERVER.O=novell.T=TREE-188. --ip-addr=<virtual_server_ip_address></pre>

3.7 Customizing the Translation Syntax for Converting Load and Unload Scripts

The syntax for load and unload scripts differs for NetWare and Linux platforms. A script that is valid for the NetWare platform is not necessarily recognized on the OES 11 platform. In a mixed-platform cluster, a cluster resource's load script and unload script must be translated to use the proper syntax when running on the NetWare or Linux nodes. Translation occurs in-memory while the cluster contains mixed-platform nodes, and during the final cluster conversion of the cluster from NetWare to Linux.

The translation between NetWare and Linux versions of the load and unload scripts is performed by the Cluster Translation Library script (`/opt/novell/ncs/bin/clstrlib.py`). The normal translations in the library are described in [Section 3.1, "Translation of Cluster Resource Scripts for Mixed NetWare and Linux Clusters,"](#) on page 19. If the commands in a cluster resource's load or unload scripts are not part of the translation library, the cluster resource can end up in a comatose state.

Novell Cluster Services allows you to customize the translation syntax that is used for load and unload scripts in mixed-platform situations by defining new syntax translations in the `/var/opt/novell/ncs/customized_translation_syntax` file that you create. The `clstrlib.py` script reads the additional translation syntax from the syntax file, and processes them in addition to the normal translations in the Cluster Translation Library.

The customized translation supports using Python regular expressions to search for strings (`(\S+)`), digits (`(\d+)`), and other data types. The search is case insensitive.

NOTE: Refer to information about Python regular expressions to learn how to create searches for other data types.

In a text editor, create the `customized_translation_syntax` file with the additional translation syntax that you need, then copy the file to the `/var/opt/novell/ncs/` directory on each Linux node in the mixed-platform cluster.

The syntax file should contain a four-line command for each type of translation you want to add:

```
<R|D> search_string
[replacement_data]
[preceding_data]
```

You can have any number of the four-line commands in the file. Use the following guidelines for creating the syntax translation commands:

Line	Description
<R D>	Specify whether to replace (R) all matches or to delete (D) all matches of the data type you are looking for in the load or unload script.
<i>search_string</i>	Specify the search string that is used to locate a line in the scripts.
<i>[replacement_data]</i>	Specify the replacement data used to replace a line matched by the search performed. Leave this line empty if there is no replacement.
<i>[preceding_data]</i>	Specify a line to be inserted before the first line that is matched by the search performed. Leave this line empty if there is no line to be inserted before the first matching line.

The following four lines are sample code for a search command in the `customized_translation_syntax` file. The fourth line is intentionally left empty.

```
R
^\\s*bind\\s+IP\\s+(\\S+)\\s(\\S+)\\s+address=(\\d+\\.\\d+\\.\\d+\\.\\d+)
ignore_error bind IP \\1 \\2 address=\\3\\n
exit_on_error ip addr add \\3/32 dev \\1
```

You can use the `cluster convert preview` command to verify that the `customized_translation_syntax` file is working as intended for a particular resource.

- 1 On the master node, open a terminal console as the `root` user, then enter

```
cluster convert preview resource_name
```

3.8 Adding Monitoring Scripts on Linux

The monitoring script is available for cluster resources in Novell Cluster Services for OES 11. However, in a mixed-node cluster, the cluster resources that you cluster migrate from NetWare to Linux will not have a monitoring script during the conversion process. A monitoring script for each of the former NetWare cluster resources is created automatically after you perform the final cluster conversion step as described in [Section 4.4, “Finalizing the Cluster Conversion,” on page 33](#).

Sample monitoring scripts are available in the cluster resource templates for the various services on OES 11.

There might not be a monitoring script for iPrint. Print Manager has a built-in monitoring and restart capability. Using the iPrint commands in a cluster resource monitoring script for iPrint might cause a conflict.

4 Converting NetWare 6.5 Clusters to OES 11

You can use a rolling cluster conversion to convert a Novell Cluster Services cluster from NetWare 6.5 SP8 to Novell Open Enterprise Server (OES) 11. This section describes how to prepare for and perform the conversion, and how to manage the temporarily mixed cluster during the conversion.

- [Section 4.1, “Converting NetWare Cluster Nodes to OES 11 \(Rolling Cluster Conversion\),” on page 27](#)
- [Section 4.2, “Adding New OES 11 Nodes to Your NetWare Cluster,” on page 30](#)
- [Section 4.3, “Removing NetWare Nodes from the Cluster,” on page 32](#)
- [Section 4.4, “Finalizing the Cluster Conversion,” on page 33](#)

4.1 Converting NetWare Cluster Nodes to OES 11 (Rolling Cluster Conversion)

Performing a rolling cluster conversion from NetWare 6.5 to OES 11 lets you keep your cluster up and running and lets your users continue to access cluster resources while the conversion is being performed.

During a rolling cluster conversion, one server is converted to Linux while the other servers in the cluster continue running NetWare 6.5. Then another server can be converted to OES 11, and then another, until all servers in the cluster have been converted to Linux.

IMPORTANT: Before you begin, ensure that your system meets the requirements and caveats in “[Planning for Novell Cluster Services](#)” in the *OES 11: Novell Cluster Services 2.0 for Linux Administration Guide*. Also verify that your system meets the requirements in [Chapter 1, “Planning the Cluster Conversion,” on page 9](#).

If you are converting from NetWare on physical servers to OES 11 on virtual servers (guest operating systems running on virtual machines), you can use the same methods and processes as those used on a physical server. No additional changes or special configuration is required. For information, see “[Mixed Physical and Virtual Node Clusters](#)” in the *OES 11: Novell Cluster Services 2.0 for Linux Administration Guide*.

To perform a rolling cluster conversion from NetWare 6.5 to OES 11:

- 1 Before you add the first Linux node to the NetWare cluster, if the NetWare cluster uses an SBD, ensure that the device (or devices) being used by the SBD are marked as *Shareable for Clustering*. You can use NSSMU or iManager to mark the SBD devices as shareable. It is not necessary to bring the cluster down when changing the device attribute to *Shareable for Clustering*.

Using NSSMU:

- 1a** Log in to the master node of the NetWare cluster as the administrator user.
 - 1b** Enter `nssmu` at the server console prompt.
 - 1c** In the NSSMU main menu, select *Devices*.
 - 1d** In the *Devices* list, highlight the device that contains the SBD partition, then press F5 to select it.
 - 1e** Press F6 to mark the device as *Shareable for Clustering*.
 - 1f** If the SBD partition is mirrored, repeat [Step 1d](#) and [Step 1e](#) to also mark the mirror device as *Shareable for Clustering*.
 - 1g** Press Esc to exit NSSMU.
- 2** Make a note of the services that are installed on the server you are converting.
You might want to install the same components on the Linux node if they are available.
- 3** On the NetWare server that you want to convert to Linux, remove eDirectory.
You can do this by running NWConfig, then selecting *Product Options > Directory Options <install NDS> > Remove Directory Services from this server*.
- 4** Bring down the NetWare server you want to convert to Linux.
Any cluster resources that were running on the server should fail over to another server in the cluster.
You can also manually cluster migrate the resources to another server in the cluster prior to bringing down the server. This prevents the resources from failing back to the node after you have completed the upgrade.
- 5** In eDirectory, remove (delete) the NetWare node's Cluster Node object, the Server object, and all corresponding objects relating to the downed NetWare server.
Depending on your configuration, there could be 10 or more objects that relate to the downed NetWare server.
- 6** Run DSRepair from another server in the eDirectory tree to fix any directory problems.
If DSRepair finds errors or problems, run it multiple times until no errors are returned.
- 7** Install OES 11 on the server, but do not install the Novell Cluster Services option in OES Services at this time.
You can use the same server name and IP address that were used on the NetWare server. This is suggested, but not required.
See the [OES 11: Installation Guide](#) for more information.
- 8** Set up and verify SAN connectivity for the Linux node.
Consult your SAN vendor documentation for SAN setup and connectivity instructions.
- 9** Install Novell Cluster Services and add the node to your existing NetWare 6.5 cluster.
 - 9a** Log in to the OES 11 server as the `root` user.
 - 9b** In YaST, select *Open Enterprise Server > OES Install and Configuration*.
 - 9c** On the Software Selection page under *OES Services*, click *Novell Cluster Services*.
Services that you have already installed are indicated by a blue check mark in the status check box next to the service.
For information about other install options, see "[Installing Novell Cluster Services during a OES 11 Installation](#)" in the [OES 11: Novell Cluster Services 2.0 for Linux Administration Guide](#).

- 9d** Click *Accept* to begin the install, then click *Continue* to accept changed packages.
- 9e** Continue through the installation process until you reach the Novell Open Enterprise Server Configuration page.
- 9f** Reconfigure *LDAP Configuration of Open Enterprise Services* to specify the credentials for the container administrator user (or non-administrator user) who has the eDirectory rights needed to install Novell Cluster Services.

For information about what rights are needed, see “[Assigning Install Rights for Container Administrators \(or Non-Administrator Users\)](#)” in the *OES 11: Novell Cluster Services 2.0 for Linux Administration Guide*.

- 9f1** On the Novell Open Enterprise Server Configuration page under *LDAP Configuration of Open Enterprise Services*, click the *disabled* link to enable re-configuration.

The sentence changes to *Reconfiguration is enabled*.

- 9f2** Click the *LDAP Configuration of Open Enterprise Services* link to open the LDAP Configuration page.

- 9f3** Specify the following values:

- ♦ **Admin name and context:** The user name and context (in LDAP form) of the container administrator user (or non-administrator user) who has the eDirectory rights needed to install Novell Cluster Services.
- ♦ **Admin password:** The password of the container administrator (or non-administrator user).

- 9f4** Click *Next*.

The install returns to the Novell Open Enterprise Server Configuration page.

- 9g** On the Novell Open Enterprise Server Configuration page under *Novell Cluster Services*, click the *disabled* link to enable configuration.

The sentence changes to *Configuration is enabled*.

- 9h** Click the *Novell Cluster Services* link to open the Novell Cluster Services Configuration page.

- 9i** Click *Existing Cluster*, specify the fully distinguished name (FDN) of the cluster, then click *Next*.

IMPORTANT: Use the comma format illustrated in the example. Do not use dots.

This is the name and eDirectory context of the cluster that you are adding this server to.

- 9j** Select the IP address that Novell Cluster Services will use for this node.

Some servers have multiple IP addresses. This step lets you choose which IP address Novell Cluster Services uses.

- 9k** Deselect *Start Services Now*.

- 9l** Click *Next*, then continue through the rest of the OES installation.

- 9m** After the install is complete, use the Software Updater (or other update methods) to install any patches from the OES 11 patch channel and the SUSE Linux Enterprise Server 11 patch channel.

- 10** If you have a shared disk system on the cluster, enter `sbdutil -f` at the Linux terminal console to verify that the node can see the cluster (SBD) partition on the SAN.

`sbdutil -f` also tells you the device on the SAN where the SBD partition is located.

- 11** Reboot the server.

- 12 (Optional) Manually migrate the resources that were on the old server nodes to this Linux server.

Some cluster resources for services on NetWare cannot be used on Linux. For information, see [Chapter 1, “Planning the Cluster Conversion,” on page 9](#).

The resources can automatically fail back if all of the following apply:

- ♦ The failback mode for the resources was set to Auto.
- ♦ You used the same node number for this Linux server that was used for the former NetWare server.

This only applies if this Linux server is the next server added to the cluster.

- ♦ This Linux server is the preferred node for the resources.

4.2 Adding New OES 11 Nodes to Your NetWare Cluster

You can add new OES 11 cluster nodes to your existing NetWare 6.5 cluster without bringing down the cluster.

- 1 Before you add the first Linux node to the NetWare cluster, if the NetWare cluster uses an SBD, ensure that the device (or devices) being used by the SBD are marked as *Shareable for Clustering*.

You can use NSSMU or iManager to mark the SBD devices as shareable. It is not necessary to bring the cluster down when changing the device attribute to *Shareable for Clustering*.

Using NSSMU:

- 1a Log in to the master node of the NetWare cluster as the administrator user.
- 1b Enter `nssmu` at the server console prompt.
- 1c In the NSSMU main menu, select *Devices*.
- 1d In the *Devices* list, highlight the device that contains the SBD partition, then press F5 to select it.
- 1e Press F6 to mark the device as *Shareable for Clustering*.
- 1f If the SBD partition is mirrored, repeat [Step 1d](#) and [Step 1e](#) to also mark the mirror device as *Shareable for Clustering*.
- 1g Press Esc to exit NSSMU.
- 2 Install OES 11 on the new node, but do not install the Novell Cluster Services option from OES Services at this time.
See the “[OES 11: Installation Guide](#)” for more information.
- 3 Set up and verify SAN connectivity for the new OES 11 node.
Consult your SAN vendor documentation for SAN setup and connectivity instructions.
- 4 Install Novell Cluster Services on the OES 11 node.
- 5 After the install, add the server to the NetWare cluster:
For detailed instructions, see “[Adding a Node to an Existing Cluster](#)” in the [OES 11: Novell Cluster Services 2.0 for Linux Administration Guide](#).
 - 5a Log in to the OES 11 server as the root user.
 - 5b In YaST, select *Open Enterprise Server > OES Install and Configuration*.
 - 5c On the Software Selection page under *OES Services*, verify that *Novell Cluster Services* is selected, then click *Accept* to continue to the configuration.

Services that you have already installed are indicated by a blue check mark in the status check box next to the service.

- 5d** On the Software Configuration page, enable Novell Cluster Services configuration, then click the Novell Cluster Services link.
- 5e** When you are prompted, enter the credentials of the LDAP administrator that is configured for the server.
- 5f** On the Novell Cluster Services Configuration page, add the server to the existing NetWare cluster, then click *Next*.

Parameter	Action
<i>New or Existing Cluster</i>	Select <i>Existing Cluster</i> .
<i>Cluster FDN</i>	Browse to select the Cluster object for the NetWare cluster, or type the cluster fully distinguished name. For example: cn=nwcluster,ou=clusters,o=mycompany

- 5g** On the Proxy User Configuration page, specify one of the following users as the NCS Proxy user, then click *Next*.
 - ♦ **OES Common Proxy User:** If the OES Common Proxy User is enabled in eDirectory, the *Use OES Common Proxy User* check box is automatically selected and the *NCS Proxy User Name* and *Specify NCS Proxy User Password* fields are populated with the credentials of the OES Common Proxy User.
 - ♦ **LDAP Admin User:** If the OES Common Proxy User is disabled in eDirectory, the *Use OES Common Proxy User* check box is automatically deselected and the *NCS Proxy User Name* and *Specify NCS Proxy User Password* fields are populated with the credentials of the LDAP Admin user. The fields are also automatically populated with the LDAP Admin credentials if you deselect the *Use OES Common Proxy User* check box.
 - ♦ **Another Administrator User:** Deselect the *Use OES Common Proxy User* check box, then specify the credentials of an administrator user.

You can reset the default settings by clicking *Back* to return to the Novell Cluster Services Configuration page, then clicking *Next* to continue again to the Proxy User Configuration page.

- 5h** On the Configuration page, specify the following parameters, then click *Finish*.

Parameter	Action
<i>IP address of this node</i>	If the server has multiple network adapters, select the IP address that Novell Cluster Services will use for this node.
<i>Start Cluster Services now</i>	Deselect the check box. You will start Novell Cluster Services software on this node manually for the conversion process.

- 5i** On the OES Server Configuration page, scroll down to the Novell Cluster Services entry to review the summary of the Cluster Services configuration, then click *Next*.

Wait while Novell Cluster Services is configured.

- 5j After the configuration is completed, click *Finish* to exit the OES Configuration page, then exit YaST.
- 6 If you have a shared disk system on the cluster, enter `sbdutil -f` at the Linux terminal console to verify that the node can see the cluster (SBD) partition on the SAN.
`sbdutil -f` will also tell you the device on the SAN where the SBD partition is located.
- 7 Start cluster software by going to the `/etc/init.d` directory and running `novell-ncs start`.
You must be logged in as root to run `novell-ncs start`.
- 8 Add and assign cluster resources to the new Linux cluster node.
For information, see “[Configuring Preferred Nodes for a Resource](#)” in the *OES 11: Novell Cluster Services 2.0 for Linux Administration Guide*.

4.3 Removing NetWare Nodes from the Cluster

After your OES 11 cluster nodes are set up and resources have been migrated to them from the NetWare nodes, you are ready to remove the NetWare nodes from the cluster.

To remove the NetWare nodes from the cluster:

- 1 Log in to the NetWare node as the administrator user.
- 2 Check the cluster status and verify that all cluster resources have been migrated to the Linux nodes.
`cluster status`
- 3 Remove the NetWare node from the cluster by entering
`cluster leave`
- 4 Stop Novell Cluster Services from running on the NetWare node by entering
`uldnscs`
- 5 Remove the node’s Cluster Node object and the NCS attributes from its Server object.
 - 5a In a Web browser, open iManager, then log in to the Novell eDirectory tree that contains the node you want to manage.

IMPORTANT: Log in as an administrator user who has sufficient rights in eDirectory to delete and modify eDirectory objects.

 - 5b Delete the node’s Cluster Node object from the cluster container:
 - 5b1 Select *Directory Administration > Delete Objects*.
 - 5b2 Browse to the Cluster container (🔗) of the cluster, locate and select the Cluster Node object (🗑️) for the NetWare node in the container, then click *OK*.
 - 5b3 On the Delete Objects page, click *OK*, then click *OK* again to confirm the deletion of the Cluster Node object.
 - 5c Select *Directory Administration > Modify Object*, select the NetWare node’s Server object, remove its NCS attributes, then click *OK* to save and apply your changes.
- 6 Repeat this process to remove each of the remaining NetWare nodes in the cluster.

4.4 Finalizing the Cluster Conversion

If you have converted all nodes in a former NetWare cluster to OES 11, you must finalize the conversion process by issuing the `cluster convert` command on one Linux cluster node. The `cluster convert` command moves cluster resource load and unload scripts from the files where they were stored on Linux cluster nodes into eDirectory. This enables a Linux cluster that has been converted from NetWare to utilize eDirectory like the former NetWare cluster.

WARNING: After you finalize the cluster conversion, rollback to NetWare is not supported. All of the scripts for the NetWare nodes are deleted and are no longer available.

To finalize the cluster conversion:

- 1 Run `cluster convert preview resource_name` at the terminal console of one Linux cluster node.

The `preview` switch lets you view the resource load and unload script changes that will be made when the conversion is finalized. Replace *resource_name* with the name of a resource that you want to preview.

You can preview the information for all cluster resources by issuing the command without specifying a resource name.

- 2 Run `cluster convert commit` at the terminal console of one Linux cluster node to finalize the conversion.

The `cluster convert commit` command generates or regenerates the cluster resource templates that are included with Novell Cluster Services for Linux. In addition to generating Linux cluster resource templates, this command deletes all NetWare cluster resource templates that have the same name as Linux cluster resource templates.

The cluster resource templates are automatically created when you create a new Linux cluster, but are not created when you convert an existing NetWare cluster to Linux.

- 3 Update the cluster configuration on all nodes by running the cluster configuration daemon. Enter the following command as the `root` user on every node in the cluster:

```
/opt/novell/ncs/bin/ncs-configd.py -init
```

This removes the NetWare nodes from the list of nodes in the cluster so they are not displayed in iManager.

5 Novell AFP

Novell Apple Filing Protocol (AFP) for Linux is available for Novell Open Enterprise Server (OES) 11.

After you set up Novell AFP on the Linux node and before you finalize the NetWare-to-Linux conversion, use the AFP function in the Migration Tool to convert the configuration. For information, see [“Migrating AFP from NetWare to OES 11”](#) in the *OES 11: Migration Tool Administration Guide*.

The commands in the scripts are also different. After the migration, modify the load and unload scripts on the Linux server. For information, see [Section 3.6, “Comparing File Access Protocol Resource Script Commands,”](#) on page 23.

AFP on Linux supports NCP cross-protocol file locking, which allows NCP, AFP, and CIFS users to access files on an NSS volume concurrently without data corruption by locking the files across protocols. On Linux, the cross-protocol file locking parameter for NCP Server is enabled by default. Verify that the Cross-Protocol File Locking parameter is enabled on each node in the cluster if you plan to give both NCP users and AFP users access to NSS volume in the cluster. See [“Configuring Cross-Protocol File Locks for NCP Server”](#) in the *OES 11: NCP Server for Linux Administration Guide*.

6 Apache Web Server

This section describes how reuse the Apache Web Server cluster resource when you convert a cluster from NetWare 6.5 SP8 to Novell Open Enterprise Server (OES) 11.

For information about installing and configuring Apache on OES 11, see “The Apache HTTP Server” (http://www.suse.com/documentation/sles11/book_sle_admin/data/cha_apache2.html) in the *SLES 11 Administration Guide* (http://www.suse.com/documentation/sles11/book_sle_admin/data/book_sle_admin_pre.html).

- ♦ Section 6.1, “Prerequisites,” on page 37
- ♦ Section 6.2, “Converting the Apache Cluster Resource,” on page 37
- ♦ Section 6.3, “Additional Information,” on page 40

6.1 Prerequisites


You must install Novell Storage Services on the OES 11 servers in order to reuse the cluster resource that contains the Web site files.

After you convert the cluster, you will install the *Linux Web and LAMP Server* functional pattern and set up Apache services. The *Web and LAMP Server* pattern includes the Apache and MySQL packages, and scripting languages such as PHP, Python, Ruby on Rails, and Perl.

6.2 Converting the Apache Cluster Resource

- 1 In iManager, offline the NSS pool cluster resource from a NetWare node, then modify its load and unload scripts to remove the Apache start and stop commands.
- 2 In iManager, online the cluster resource on a NetWare node to activate the changes you made to the scripts.
- 3 In iManager, cluster migrate the cluster resource to a Linux node, then offline the resource.
- 4 Complete the cluster conversion.
- 5 For each Linux node in the cluster, install the *Web and LAMP Server* option under the *Linux Primary Functions* category.
 - 5a Log in as the `root` user, then open YaST.
 - 5b In YaST, select *Open Enterprise Server > OES Install and Configuration*.

- 5c** On the Software Selection page, under *Primary Functions*, select *Web and LAMP Server*, then click *Accept*.



- 5d** Continue with the installation.
- 6** (Optional) Install Tomcat.
- 6a** Log in as the `root` user, then open YaST.
- 6b** In YaST, click *Software* in the left pane, then click *Software Management* in the right pane.
- 6c** In the Search field, type `tomcat`, then click *Search*.
- 6d** Select the Tomcat packages you want to install, then click *Accept*.
- If you encounter a dependency conflict, select the package you want to install to resolve the conflict, then click *OK -- Try Again* to continue with the installation.
- 7** After the Web services are installed on all nodes, log in as the `root` user on the master node, then configure the Apache Web Server.
- 7a** Log in as the `root` user, then open YaST.
- 7b** In YaST, click *Network Services* in the left pane, then click *HTTP Server* in the right pane.
- Apache is referred to as the HTTP Server on Linux.
- 7c** Configure the following HTTP Server settings by using the HTTP Server Wizard:
- For wizard instructions, see “Section 40.2.2, Configuring Apache with YaST” (http://www.suse.com/documentation/sles11/book_sle_admin/data/sec_apache2_configuration.html#sec_apache2_configuration_yast) in the *SLES 11 Administration Guide* (http://www.suse.com/documentation/sles11/book_sle_admin/data/book_sle_admin_pre.html).
- ♦ Port (and open the firewall)
 - ♦ Network devices

- ♦ Modules for scripting (PHPS, Perl, Python, Ruby)
- ♦ Default host
- ♦ Virtual host

The default host settings on Linux are:

Parameter	Default Value
Port	80
Document Root	/srv/www/htdocs Point the service to the virtual IP address of the NSS pool cluster resource that contains the Web content.
Alias	/icons points to /usr/share/apache2/icons
ScriptAlias	/cgi-bin points to /srv/www/cgi-bin
Include	/etc/apache2/conf.d /etc/apache2/conf.d/apache2-manual.conf
Server Name	/http://<fully_qualified_distinguished_name_or_ip_address>
Server Administrator Email	<specify an email address>

7d To verify that Apache has started successfully, open a Web browser and view the following URL:

`http://Web_server_address:port_number`

where *Web_server_address* is the IP address or hostname of your Linux server and *port_number* is the Apache listen port, which is 80 by default. For example:

`http://192.168.1.18:80`

`http://localhost:80`

If Apache is correctly set up, you should see a Web page that starts with the following message:

If you can see this, it means that the installation of the Apache Web Server software on this system was successful. You may now add content to this directory and replace this page.

7e Replace the Apache test page (/apache2/htdocs/index.html) with your own home page.

8 Copy the Apache configuration file (/etc/apache2/httpd.conf) to every Linux node in the cluster.

9 (Optional) Set up an SSL certificate for the Apache server.

For information, see “Setting Up a Secure Web Server with SSL” (http://www.suse.com/documentation/sles11/book_sle_admin/data/sec_apache2_ssl.html) in the *SLES 11 Administration Guide* (http://www.suse.com/documentation/sles11/book_sle_admin/data/book_sle_admin_pre.html).

10 In iManager, set up the preferred nodes for the Apache cluster resource.

- 11 In iManager, modify the load and unload scripts for the cluster resource to add the Apache service start and stop commands for Linux.

```
/usr/sbin/rcapache2 start
```

```
/usr/sbin/rcapache2 stop
```

- 12 Online the Apache cluster resource.

6.3 Additional Information

In addition to the SUSE documentation, the following Apache resources are available online.

- ♦ [Section 6.3.1, “Apache 2 Manual,” on page 40](#)
- ♦ [Section 6.3.2, “Virtual Hosts Support,” on page 40](#)

6.3.1 Apache 2 Manual

The Apache manual is available on the [Apache HTTP Server Version 2.2 Documentation Web site](http://httpd.apache.org/docs-2.2/) (<http://httpd.apache.org/docs-2.2/>). The package `apache2-doc` also contains the complete Apache manual. It is not installed by default.

- 1 Log in as the `root` user, then open a terminal console.
- 2 At the terminal prompt, enter

```
yast -i apache2-doc
```

Once installed, the Apache manual is available at `http://localhost/manual/`.

SUSE-specific configuration hints are available in the `/usr/share/doc/packages/apache2/README.*` directory.

6.3.2 Virtual Hosts Support

On Linux, the Apache service allows you to set up virtual hosts that can be used with a single instance of Apache instead of setting up different instances of Apache for each site. For information, see the following resources:

- ♦ “Virtual Host Configuration” (http://www.suse.com/documentation/sles11/book_sle_admin/data/sec_apache2_configuration.html#sec_apache2_configuration_manually_vhost) in the *SLES 11 Administration Guide* (http://www.suse.com/documentation/sles11/book_sle_admin/data/book_sle_admin_pre.html)
- ♦ Apache Virtual Host documentation Web site (<http://httpd.apache.org/docs/2.2/vhosts/>)

7 Novell Archive and Version Services

On NetWare, Archive and Versioning Services uses a MySQL database. On Novell Open Enterprise Server (OES) 11, it uses a PostgreSQL database. You can migrate the data from the MySQL database to the PostgreSQL database on Linux. You must configure a new cluster resource on a shared Linux POSIX file system for the PostgreSQL database.

The load script commands are also different on OES 11. For information, see “[Archive Load, Unload and Monitor Scripts](#)” in the *OES 11: Novell Archive and Version Services 2.1 Administration Guide*.

- ♦ [Section 7.1, “Prerequisites,”](#) on page 41
- ♦ [Section 7.2, “Copying Database Files from MySQL to PostgreSQL,”](#) on page 41

7.1 Prerequisites

Mixed-node operations are not supported by Novell Archive and Version Services. Before you begin the conversion, ensure that Archive and Version Services is not running on the NetWare servers in the cluster.

7.2 Copying Database Files from MySQL to PostgreSQL

- 1 Install Archive and Version Services on an OES 11 node in the cluster.
- 2 Install Archive and Version Services on a second OES 11 node in the cluster.
- 3 Using database migration tools, migrate the data in the MySQL database on NetWare to the PostgreSQL database on one of the Linux nodes.
- 4 Cluster migrate the shared NSS pool resource that contains the volumes that were being archived from the NetWare server to a Linux node.
- 5 Remove the NetWare nodes from the cluster and finish the cluster conversion process.
- 6 On the OES 11 cluster, set up Archive and Version Services as described in “[Configuring Archive and Version Service for Novell Cluster Services](#)” in the *OES 11: Novell Archive and Version Services 2.1 Administration Guide*.
- 7 On the Linux node where the primary NSS pool resources are active, use the *Clusters* plug-in in iManager to create an Archive Versioning cluster resource.
- 8 Copy the database files from the single-server location (`/var/opt/novell/arkmanager/data`) to the shared Linux POSIX volume that you created when you set up Archive and Version Services for clustering in [Step 7](#).

Use the `cp -a` command at a terminal console prompt to copy all files and retain the permissions.

- 9** Change the ownership of the new database location on the shared volume by entering the following at a terminal console prompt:

```
chown -R arkuser:arkuser_prgrp /shared/datapath
```

- 10** Edit the `/etc/opt/novell/arkmanager/conf/arkdatadir.conf` file to change the database location to new shared path.
- 11** Edit the `/opt/novell/arkmanager/bin/pg_restart.sh` file to change the line that starts the PostgreSQL database to the following:

```
su arkuser -c "postmaster -D /shared/datapath -h 127.0.0.1 -p 5432 -i"
```

- 12** Start Archive and Version Services by entering

```
rcnovell-ark start
```

You should see Archive and Version Services and the PostgreSQL database starting.

8 eDirectory Server Certificates

Novell Certificate Server provides two categories of services: Certificate Authority (CA) and Server Certificates. The Certificate Authority services include the Enterprise CA and CRL (Certificate Revocation List). Only one server can host the CA, and normally that same server hosts the CRLs if they are enabled (although if you move the CA to a different server, the CRLs usually stay on the old server). The CA and CRL services are not cluster-enabled in either NetWare or OES 11, and therefore, there are no cluster-specific tasks for them.

Novell Certificate Server provides a Server Certificates service for NetWare and Linux. The service is not clustered. However, clustered applications that use the server certificates must be able to use the same server certificates on whichever cluster node they happen to be running. Use the instructions in the following sections to set up Server Certificate objects in a clustered environment to ensure that your cryptography-enabled applications that use Server Certificate objects always have access to them.

The eDirectory Server Certificate objects are created differently in OES 11 and cannot be directly reused from the NetWare server. The differences and alternatives for setting up certificates on Linux are described in the following sections:

- [Section 8.1, “Server Certificate Changes in OES 11,” on page 43](#)
- [Section 8.2, “Using Internal Certificates in a Cluster,” on page 44](#)
- [Section 8.3, “Using External Certificates in a Cluster,” on page 44](#)

8.1 Server Certificate Changes in OES 11

When you install NetWare or OES 11 in an eDirectory environment, the Server Certificate service can create certificates for eDirectory services to use. In addition, custom certificates can be created after the install by using iManager or command line commands.

For NetWare, all applications are integrated with eDirectory. This allows applications to automatically use the server certificates created by Novell Certificate Server directly from eDirectory. In a NetWare cluster, you might have copied the Server Certificate objects to all nodes in the cluster using backup and restore functions as described in [“Server Certificate Objects and Clustering”](http://www.novell.com/documentation/crt33/crtadmin/data/a2ebopb.html#acebe5n) (<http://www.novell.com/documentation/crt33/crtadmin/data/a2ebopb.html#acebe5n>) in the *Novell Certificate Server 3.3.2 Administration Guide* (<http://www.novell.com/documentation/crt33/crtadmin/data/a2ebomw.html>).

For OES 11, many applications (such as Apache and Tomcat) are not integrated with eDirectory and therefore, cannot automatically use the certificates created by Novell Certificate Server directly from eDirectory. By default, these services use self-signed certificates, which are not in compliance with the X.509 requirements as specified in RFC 2459 and RFC 3280.

To address the difference, Novell Certificate Server offers an install option for OES 11 called *Use eDirectory Certificates* that automatically exports the default eDirectory certificate *SSL Certificate DNS* and its key pair to the local file system in the following files:

```
/etc/ssl/servercerts/servercert.pem  
/etc/ssl/servercerts/serverkey.pem
```

8.2 Using Internal Certificates in a Cluster

Recent versions of Novell Certificate Server create default certificates that allow you to specify an alternative IP address or DNS address by adding it in the Subject Alternative Name extension. This requires that your DNS service be configured to reflect the cluster IP/DNS address as the default (or first) address. If the DNS service is set up correctly, the cluster applications can use the default certificates without needing any administration.

IMPORTANT: If the DNS service is not set up correctly, then you must use the process described for external certificates in [“Using External Certificates in a Cluster” on page 44](#).

For OES 11 clusters using the internal certificate method, ensure that the DNS service is configured to use the cluster IP/DNS address. During the OES 11 install, select the *Use eDirectory Certificates* option so that Novell Certificate Server automatically creates the *SSL Certificate DNS* certificate with the correct IP/DNS address. By selecting the *Use eDirectory Certificates* option during the install and using the cluster IP/DNS address, clustered applications should be able to access the certificates without needing further configuration for the Server Certificate object.

8.3 Using External Certificates in a Cluster

External (third-party) certificates create a Server Certificate object that includes the cluster's IP and/or DNS address. Create a backup of this certificate. For each server in the cluster, create a Server Certificate object with the same name by importing the previously created backup certificate and key pair to a location on that server. This allows all of the servers in the cluster to use and share the same certificate and key pair. After all cluster nodes have the certificate, configure the cluster applications to use the server certificate.

IMPORTANT: This cluster task can also be used for sharing internal certificates on the cluster nodes. In early versions of Novell Certificate Server, this was the only option available.

For information about exporting and using eDirectory Server Certificates for External Services, see [“Using eDirectory Certificates with External Applications”](http://www.novell.com/documentation/crt33/crtadmin/data/bh9x78f.html) (<http://www.novell.com/documentation/crt33/crtadmin/data/bh9x78f.html>) in the *Novell Certificate Server 3.3.4 Administration Guide* (<http://www.novell.com/documentation/crt33/crtadmin/data/a2ebomw.html>).

For OES 11 clusters using the external certificate method, the solution is more complicated than for internal certificates. You must create the certificate for each server in the cluster just as you did for NetWare. You must also create a configuration on the SAS:Service object for each server so that the common certificate is automatically exported to the file system where the non-eDirectory enabled applications can use it.

9 Novell CIFS

Novell CIFS for Linux is available for Novell Open Enterprise Server (OES) 11.

After you set up Novell CIFS on the Linux node and before you finalize the NetWare-to-Linux conversion, use the CIFS function in the Migration Tool to convert the configuration. For information, see [“Migrating CIFS from NetWare to OES 11”](#) in the *OES 11: Migration Tool Administration Guide*.

The commands in the scripts are also different. After the migration, modify the load and unload scripts on the Linux server. For information, see [Section 3.6, “Comparing File Access Protocol Resource Script Commands,”](#) on page 23.

CIFS supports NCP cross-protocol file locking, which allows NCP, AFP, and CIFS users to access files on an NSS volume concurrently without data corruption by locking the files across protocols. On Linux, the cross-protocol file locking parameter for NCP Server is enabled by default. Verify that it is enabled on each node in the cluster if you plan to give both NCP users and CIFS users access to an NSS volume in the cluster. See [“Configuring Cross-Protocol File Locks for NCP Server”](#) in the *OES 11: NCP Server for Linux Administration Guide*.

CIFS supports the merged view for Novell Dynamic Storage Technology (DST) shadow volumes built with NSS volumes. Wait until the cluster conversion is complete before attempting to set up DST shadow volumes in the OES 11 cluster.

10 Novell Distributed File Services VLDB

The Novell Distributed File Services volume location database (VLDB) .dat file format is the same on both NetWare and Linux. The shared NSS volume that contains the .dat file can be cluster migrated to the Linux server.

Use one of these two methods for migrating the VLDB from NetWare to Linux:

- ♦ [Section 10.1, “Cluster Migrating the Shared NSS Volume for the VLDB,” on page 47](#)
- ♦ [Section 10.2, “Adding a Linux Server as a Replica Site,” on page 48](#)

10.1 Cluster Migrating the Shared NSS Volume for the VLDB

Use this method if you want to use the same shared disk where the VLDB is currently stored.

- 1 For each Linux node where you expect to run the VLDB service, install Novell Storage Services and any of its dependent services on the Linux node, then add it to the mixed cluster that you are converting.
- 2 For each of the Linux nodes, assign the node's nssadmin user as a trustee of the container that is configured as the Management Context for the VLDB, and give the user at least the Read and Compare rights to the [All Attribute Rights] property.

IMPORTANT: If the Management Context is configured to use the container that contains a node's Server object, the nssadmin User object for that server is already a trustee of the container and has the Supervisor right. Do not modify the existing rights settings for this nssadmin User object when you add rights for the [All Attribute Rights] property.

2a In iManager, select *Rights > Modify Trustees*.

2b Select the container that is configured as the Management Context, then click *OK*.

2c Click *Add Trustee*, select the nssadmin User object, then click *OK*.

The nssadmin User object is in the same container as its server. The user name format is *servername.admin.context*. For example, if the server name is *server1.oul.mycompany*, then *server1admin.oul.mycompany* is the nssadmin user name.

2d Click *Assigned Rights* for the selected nssadmin User object.

2e Assign the *Read* and *Compare* rights to the [All Attribute Rights] property, then click *Done*.

2f Click *Apply* to save and apply the changes.

2g Repeat [Step 2c](#) through [Step 2f](#) for each of the Linux nodes where you expect to run the VLDB service.

3 Cluster migrate the DFS cluster resource from NetWare to Linux.

4 On the Linux node where the VLDB is active, offline the DFS cluster resource.

- 5 Remove the NetWare clusters from the cluster by using the `cluster leave` command, then finish the cluster conversion.

This automatically updates the basic cluster commands in the cluster resource scripts.

- 6 Using the *Clusters* plug-in in iManager, modify the load script of the DFS cluster resource to change the `vldb` command to the Linux format. For example, change it from

```
vldb /dir=vldbpath  
  
to  
  
vldb -dir /vldbpath
```

- 7 Online the cluster resource.
- 8 Run a VLDB repair to ensure that the database is correct.

10.2 Adding a Linux Server as a Replica Site

Use this method if you want to use a different shared disk for the VLDB on Linux. You can do this by adding a DFS replica site on Linux.

- 1 Install OES 11 on the server that you want to add to the cluster. Ensure that Novell Storage Services and any of its dependent services are installed.
- 2 Assign the node's `nssadmin` user as a trustee of the container that is configured as the Management Context for the VLDB, and give the user at least the `Read` and `Compare` rights to the `[All Attribute Rights]` property.

IMPORTANT: If the Management Context is configured to use the container that contains a node's Server object, the `nssadmin` User object for that server is already a trustee of the container and has the `Supervisor` right. Do not modify the existing rights settings for this `nssadmin` User object when you add rights for the `[All Attribute Rights]` property.

- 2a In iManager, select *Rights > Modify Trustees*.
 - 2b Select the container that is configured as the Management Context, then click *OK*.
 - 2c Click *Add Trustee*, select the `nssadmin` User object, then click *OK*.

The `nssadmin` User object is in the same container as its server. The user name format is `servername.admin.context`. For example, if the server name is `server1.oul.mycompany`, then `server1admin.oul.mycompany` is the `nssadmin` user name.
 - 2d Click *Assigned Rights* for the selected `nssadmin` User object.
 - 2e Assign the *Read* and *Compare* rights to the `[All Attribute Rights]` property, then click *Done*.
 - 2f Click *Apply* to save and apply the changes.
- 3 Create a shared NSS pool and volume on the OES 11 server, or create a shared Linux POSIX volume.
 - 4 In iManager, add the Linux server as the second VLDB replica site for the DFS management context, and point to the shared NSS volume as the VLDB location.
 - 5 Allow the VLDB data to synchronize between the NetWare replica and the Linux replica.
 - 6 In iManager, remove the NetWare instance of the replica site.
 - 7 Add the Linux server to the mixed-node NetWare cluster.
 - 8 Continue with the cluster conversion as described in [Section 4.1, "Converting NetWare Cluster Nodes to OES 11 \(Rolling Cluster Conversion\),"](#) on page 27.

11 DHCP Server

The Novell DHCP Server for Linux is based on a standards-compliant implementation from ISC that is distributed with SUSE Linux Enterprise Server. DHCP uses a different schema on Linux to store the configuration in eDirectory.

After you set up Novell DHCP Server on the OES 11 server and before you complete the cluster conversion, you can use the DHCP option for the Migration Tool to convert the configuration from NetWare to OES 11. You cannot directly reuse the data. Migrate your DHCP server data, then perform the post-migration tasks to set up the configuration in the OES 11 nodes of the cluster.

- ♦ [Section 11.1, “Setting Up Novell DHCP on OES 11,” on page 49](#)
- ♦ [Section 11.2, “Prerequisites for Migration,” on page 49](#)
- ♦ [Section 11.3, “Migrating the DHCP Configuration from NetWare to Linux Clusters in the Same Tree,” on page 49](#)
- ♦ [Section 11.4, “Post-Migration Tasks,” on page 50](#)

11.1 Setting Up Novell DHCP on OES 11

Novell DHCP Server for OES 11 supports using a shared Linux POSIX file system or a shared NSS file system for the cluster resource. Set up DHCP on the OES 11 servers by using one of the following methods in the [OES 11: Novell DNS/DHCP Services for Linux Administration Guide](#):

- ♦ [“Configuring DHCP with Novell Cluster Services for the NSS File System”](#)
- ♦ [“Configuring DHCP with Novell Cluster Services for the Linux File System”](#)

11.2 Prerequisites for Migration

For more information about prerequisites, see [“Migration Requirements”](#) for DHCP in the [OES 11: Migration Tool Administration Guide](#).

11.3 Migrating the DHCP Configuration from NetWare to Linux Clusters in the Same Tree

In this scenario, both the NetWare server and the OES 11 server are in the same eDirectory tree. The NetWare source server must be running NetWare 5.1 SP8 or later versions. The Linux target server must be running OES 11 on 64-bit hardware.

Run the DHCP function in the Migration Tool from one of the OES 11 nodes. Perform the Tree Level Migration with the same Source server (tree to which NetWare clustered nodes are attached) and Target server (tree to which the Linux clustered nodes are attached). This ensures that the entire NetWare DHCP configuration data is available for OES 11 DHCP.

For information, see “[Migrating DHCP](#)” in the *OES 11: Migration Tool Administration Guide*, and follow the instructions for NetWare and Linux in the same eDirectory tree.

IMPORTANT: Before starting the DHCP server on the Linux cluster, stop the DHCP server on the NetWare cluster.

11.4 Post-Migration Tasks

- 1 Log in as the root user to the OES 11 node where you ran the migration, then open a terminal console
- 2 Online the DHCP service cluster resource by entering

```
cluster online resource_name
```
- 3 On the Linux node where you ran the migration:
 - 3a Open the `/mount_path/etc/dhcpd.conf` file in a text editor.
Replace `mount_path` with the Linux path to the folder in the shared volume where DHCP-specific directories are created.
 - 3b In the `/mount_path/etc/dhcpd.conf` file, change the value for the `ldap-dhcp-server-cn` parameter to the cn of the migrated DHCP server, then save your changes.
 - 3c Copy the `migrated_server.leases` file from `/var/opt/novell/dhcp/leases/` folder or to the lease path specified in the Migration Tool to the `/mount_path/var/lib/dhcp/db/` folder, then rename it to `dhcpd.leases`.
- 4 Stop the DHCP server on the NetWare cluster by taking the NetWare DHCP cluster resource offline.
- 5 Start the DHCP server on the Linux cluster.

```
rcnovell-dhcpd start
```

12 DNS Server

You can migrate the data from the Novell DNS Server on NetWare to a Novell DNS Server on Linux after you have installed and set up DNS services on an Novell Open Enterprise Server (OES) 11 node in the cluster. You cannot directly reuse the data.

- ♦ [Section 12.1, “Prerequisites for Migration,” on page 51](#)
- ♦ [Section 12.2, “Migrating the DNS Configuration from NetWare to Linux Clusters in the Same Tree,” on page 51](#)
- ♦ [Section 12.3, “Post-Migration Tasks,” on page 51](#)

12.1 Prerequisites for Migration

For information about prerequisites, see [“Migrating DNS from NetWare to OES 11”](#) in the *OES 11: Migration Tool Administration Guide*.

12.2 Migrating the DNS Configuration from NetWare to Linux Clusters in the Same Tree

In this scenario, both the NetWare server and the OES 11 server are in the same eDirectory tree. The NetWare source server must be running NetWare 5.1 SP8 or later versions. The Linux target server must be running OES 11 on 64-bit hardware.

Use iManager to move the DNS server from a NetWare NCP server to an OES 11 NCP server. For information see [“Using Java Console to Migrate Servers within the Same eDirectory Tree”](#) in the *OES 11: Migration Tool Administration Guide*.

12.3 Post-Migration Tasks

See [“Post-Migration Procedure”](#) in the *OES 11: Migration Tool Administration Guide*.

- 1 Use iManager or the Java Management Console to check for the existence of the following objects:
 - ♦ DNS-DHCP
 - ♦ DNSDHCP-GROUP
 - ♦ RootServerInfo
 - ♦ DNS Server object

- 2 Use the Clusters plug-in for iManager to verify the Cluster load script and unload script of the DNS cluster resources.

For information, see “[DNS Load, Unload, and Monitor Scripts](#)” in the *OES 11: Novell DNS/DHCP Services for Linux Administration Guide*.

- 3 Start the DNS server on the OES 11 cluster.

13 Novell iPrint

This section describes how to convert the iPrint cluster resource from NetWare 6.5 SP8 to Novell Open Enterprise Server (OES) 11.

- ♦ [Section 13.1, “Installing iPrint on the OES 11 Nodes,” on page 53](#)
- ♦ [Section 13.2, “Setting Up iPrint on the OES 11 Nodes,” on page 53](#)
- ♦ [Section 13.3, “Migrating the iPrint Cluster Resource from NetWare to OES 11,” on page 56](#)
- ♦ [Section 13.4, “Finalizing the Cluster Conversion,” on page 57](#)
- ♦ [Section 13.5, “Additional Information,” on page 57](#)

13.1 Installing iPrint on the OES 11 Nodes

Prepare the first OES 11 server for use with iPrint in a cluster:

- 1 Install the following services on an OES 11 server:

- ♦ Novell iPrint
- ♦ Novell Storage Services
- ♦ Novell Cluster Services (but do not configure at install time)

Select at least these services and any dependent services that each one requires.

- 2 After the install, add the server to the NetWare cluster:

For instructions, see [Section 4.2, “Adding New OES 11 Nodes to Your NetWare Cluster,” on page 30](#).

13.2 Setting Up iPrint on the OES 11 Nodes

Perform the steps in this section to set up iPrint and an iPrint cluster resource on the OES 11 nodes in the mixed-node cluster.

- ♦ [Section 13.2.1, “Preparing the OES 11 Nodes for iPrint,” on page 54](#)
- ♦ [Section 13.2.2, “Setting Up iPrint on the OES 11 iPrint Cluster Resource,” on page 55](#)
- ♦ [Section 13.2.3, “Setting Up Preferred Nodes for the OES 11 iPrint Cluster Resource,” on page 55](#)
- ♦ [Section 13.2.4, “Editing the Load and Unload Scripts for the OES 11 iPrint Cluster Resource,” on page 55](#)
- ♦ [Section 13.2.5, “Verifying the Status of the iPrint Setup,” on page 56](#)

13.2.1 Preparing the OES 11 Nodes for iPrint

Because iPrint on NetWare and iPrint on Linux are different, cluster migrating the iPrint cluster resource from NetWare to Linux is not an option. You create a new pool cluster resource on an OES 11 node that will be the iPrint cluster resource on Linux. To set up iPrint on each server, you move the iPrint configuration information from the default Linux installation path on each node to the newly created shared NSS pool resource. Later, you will move the iPrint Driver Store and Print Manager information from the NetWare resource to the OES 11 resource.

- 1 In a Web browser, open iManager, then use the Storage role to create a new shared pool and volume on one of the OES 11 servers where iPrint is installed.

This is the iPrint cluster resource that will contain the iPrint data.

For information about creating a clustered NSS pool and volume, see “[Creating Cluster-Enabled Pools and Volumes](#)” in the *OES 11: Novell Cluster Services 2.0 for Linux Administration Guide*.

- 2 On the first OES 11 node, set up clustering for iPrint on the shared NSS volume that you created in [Step 1](#).

- 2a Log in as the root user to the OES 11 node where the shared pool resource is active, then open a terminal console.

- 2b Go to the `/opt/novell/iprint/bin` directory, then run the `iprint_nss_relocate` script by entering

```
./iprint_nss_relocate -a admin_fdn -p admin_password -n nss_volume_path -l
cluster [-c <Specify Container FDN where iPrint LUM object already
exists or should be created>] [-w <Specify Container FDN where Apache LUM
objects exist>]
```

Replace `admin_fdn` with the comma-delimited fully distinguished name of the iPrint administrator user (such as `cn=admin,o=mycompany`). Replace `admin_password` with the actual password of the specified iPrint administrator user. Replace `nss_volume_path` with the Linux path (such as `/media/nss/NSSVOL1`) to the shared NSS volume where you want to relocate the iPrint configuration data.

For information about the script options, see “[Setting up iPrint on an NSS File System](#)” in the *OES 11: iPrint Linux Administration Guide*.

For example, enter

```
./iprint_nss_relocate -a cn=admin,o=mycompany -p password -n /media/nss/
NSSVOL1 -l cluster -c o=mycompany,t=iPrint_Tree -w
o=mycompany,t=iPrint_Tree
```

- 2c Review the messages displayed on the screen to confirm the data migration from the local Linux path to the shared NSS path is completed.
- 3 For each remaining Linux node in the cluster where iPrint is installed, set up clustering for iPrint by doing the following:

- 3a Log in as the root user to the OES 11 node where the shared pool resource is active, then open a terminal console.

- 3b Cluster migrate the shared NSS pool resource from the active OES 11 node to this OES 11 node by entering

```
cluster migrate resource_name node_name
```

- 3c Log in to the newly active OES 11 node as the root user, then open a terminal console.

- 3d Run the `iprint_nss_relocate` script as described in [Step 2b](#), using the same values.

- 3e Repeat [Step 3a](#) through [Step 3d](#) until all of the OES 11 nodes are configured for iPrint.

13.2.2 Setting Up iPrint on the OES 11 iPrint Cluster Resource

- 1 In iManager, select *iPrint > Create Driver Store*, then create a Driver Store on the OES 11 node where the iPrint cluster resource is active.

For information, see “[Creating a Driver Store](#)” in the *OES 11: iPrint Linux Administration Guide*.

Use the IP or DNS name of the shared NSS pool resource that you created in [Section 13.2.1](#), “[Preparing the OES 11 Nodes for iPrint](#),” on page 54 as the *Target Server*. For the *eDirectory Server Name*, choose an eDirectory server that holds a copy of the replica where the Printer Agents will be created.

- 2 In iManager, select *iPrint > Create Print Manager*, then create a Print Manager on the OES 11 node where the iPrint cluster resource is active.

For information, see “[Creating a Print Manager](#)” in the *OES 11: iPrint Linux Administration Guide*.

Use the IP or DNS name of the shared NSS pool resource that you created in [Section 13.2.1](#), “[Preparing the OES 11 Nodes for iPrint](#),” on page 54 as the *iPrint Service*. For the *eDirectory Server Name*, choose same server that you specified for the Driver Store. Deselect the *Start print manager after creation* option.

13.2.3 Setting Up Preferred Nodes for the OES 11 iPrint Cluster Resource

Configure the Preferred Nodes list for the Linux shared NSS pool cluster resource to prevent an inadvertent failback of the resource to a NetWare server.

- 1 In iManager, click *Clusters > Cluster Manager*, then select the cluster where the Linux shared NSS pool resource is currently active.
- 2 Select the link for the OES 11 shared NSS pool cluster resource to open its Properties page.
- 3 Go to the *Preferred Nodes* tab.
- 4 Move all of the NetWare nodes from the *Assigned Nodes* list to *Unassigned Nodes* list.
- 5 Click OK to save your changes.

13.2.4 Editing the Load and Unload Scripts for the OES 11 iPrint Cluster Resource

Edit the load and unload scripts for the OES 11 iPrint cluster resource.

- 1 Edit the load script. Add the following lines to the existing load script before the `exit 0` statement

```
ignore_error mv /media/nss/NSSVOL1/var/opt/novell/iprint/iprintgw.lpr /media/nss/NSSVOL1/var/opt/novell/iprint/iprintgw.lpr.bak
```

NOTE: Replace `/media/nss/NSSVOL1` in the above command with your actual cluster volume mount point.

```
exit_on_error rcnovell-idsd start
exit_on_error rcnovell-ipsmd start
```

- 2 Edit the unload script. Add the following lines to the existing unload script after the `/opt/novell/ncs/lib/ncsfuncs` statement:

```
ignore_error rcnovell-ipsmd stop
ignore_error rcnovell-idsd stop
```

- 3 Activate the load and unload scripts by taking the resource offline, then bringing the resource online.

13.2.5 Verifying the Status of the iPrint Setup

Verify that the iPrint cluster resource is working by cluster migrating the OES 11 iPrint cluster resource to each OES 11 node in turn and performing the following checks:

- 1 Log in as the `root` user on the OES 11 node where the iPrint cluster resource is active, then open a terminal console.
- 2 Check the status of the Print Manager and Driver Store.

```
rcnovell-ipsmd status
rcnovell-idsd status
```

- 3 Test the ability of `iprntman` to authenticate the admin user (or other user given with `miggui`).

```
iprntman psm -l -u admin
```

- 4 Cluster migrate the iPrint cluster resource to another OES 11 node by entering

```
cluster migrate resource_name node_name
```

- 5 Repeat this check for each OES 11 node in the mixed-node cluster.

13.3 Migrating the iPrint Cluster Resource from NetWare to OES 11

After iPrint is configured for the OES 11 nodes, you are ready to migrate the iPrint Driver Store and Print Manager information from the NetWare iPrint cluster resource to the OES 11 iPrint cluster resource.

Perform the following steps in “[Migrating an iPrint Cluster Resource](#)” in the *OES 11: Migration Tool Administration Guide*.

- 1 Perform the pre-migration checks as described in “[Pre-Migration iPrint Configuration](#)” in the *OES 11: Migration Tool Administration Guide*.
- 2 Perform a consolidated migration of the iPrint service as described in “[iPrint Consolidate Migration](#)” in the *OES 11: Migration Tool Administration Guide*.

Start the Migration Tool from the target server (the OES 11 node where the iPrint cluster resource is active).

For the source server, authenticate by using the IP address or DNS name of the NetWare iPrint cluster resource.

For the target server, authenticate by using the IP address or DNS name of the Linux iPrint cluster resource.

- 3 Verify that the migration was successful as described in “[Verifying the Result of the iPrint Migration](#)” in the *OES 11: Migration Tool Administration Guide*.

- 4 Transition the Transition end-user printing from NetWare to Linux.
 - ♦ Offline the NetWare iPrint cluster resource.
 - ♦ View the NetWare iPrint cluster load script's /DNSNAME value.
 - ♦ Configure DNS to resolve the /DNSNAME value to the IP address of the target Linux cluster resource hosting the Print Manager.

NOTE: The propagation of the DNS change might take time, depending on your network.

DNSNAME is the address that the clients use to find the NetWare Print Manager. The same DNSNAME is used to find the Linux Print Manager.

- ♦ Update each of the Linux node `/etc/hosts` files to resolve to the Linux iPrint cluster IP address.
 - ♦ Update the `/etc/opt/novell/iprint/conf/ipsmd.conf` `PSMHostAddress` value to the /DNSNAME.
 - ♦ Restart the Print Manager.
- 5 (Optional) Perform the post-migration steps as described in “[Transfer ID](#)” and “[Post-Migration Steps](#)” in the *OES 11: Migration Tool Administration Guide*.

For detailed information about iPrint migration requirements, pre-migration configuration, migration procedures, post-migration tasks, and troubleshooting, see “[Migrating iPrint from NetWare or OES 2 to OES 11](#)” in the *OES 11: Migration Tool Administration Guide*.

13.4 Finalizing the Cluster Conversion

After your OES 11 iPrint setup is working as expected, finalize the cluster conversion, as described in [Section 4.4, “Finalizing the Cluster Conversion,”](#) on page 33.

13.5 Additional Information

See the following Novell Support Technical Information Documents (TIDs) in the Novell Knowledgebase for more information about migrating iPrint from NetWare to OES 11:

- ♦ [TID 7005448: Migrating an iPrint Cluster from NetWare to OES 2](#) (<http://www.novell.com/support/>)
- ♦ [TID 7004455: iPrint Migration Best Practices](#) (<http://www.novell.com/support/>)

14 MySQL

Novell Open Enterprise Server 11 provides an open source version of MySQL 5.0.x software that is offered under the GNU General Public License (GPL) Version 2. MySQL can be used with Novell Cluster Services to provide high availability support to the customers you service with MySQL. This helps prevent interruptions of access for the MySQL database.

IMPORTANT: As stated in the *Release Notes for SUSE Linux Enterprise Server 11*, the open source MySQL packages require additional support contracts to be obtained by the customer in order to receive full support.

Novell also offers the MySQL Network product that combines the latest MySQL Pro Certified Server software with a comprehensive set of services and support from Novell. For information, see [MySQL Network \(http://www.novell.com/products/mysql/\)](http://www.novell.com/products/mysql/).

MySQL is installed on all nodes where you want it to run, but a database runs on only one node in the cluster at a time. The MySQL configuration files are modified on each node to point to a path on a Linux Logical Volume Manager (LVM) volume group cluster resource that contains the MySQL database files. You cluster-enable the volume group by using the MySQL template, then configure its resource load, unload, and monitoring scripts, set its resource failover and failback modes, and assign the resource to specific nodes in the cluster. When a node fails where the resource is online, the resource fails over to the next preferred node in the cluster.

IMPORTANT: Refer to the official MySQL 5.0 documentation for information about configuring, managing, and using MySQL. For information, see [MySQL Documentation Library: MySQL Reference Manuals \(http://dev.mysql.com/doc/\)](http://dev.mysql.com/doc/).

The instructions in this section describes how to set up MySQL on an OES 11 cluster.

- ♦ [Section 14.1, “Prerequisites for Clustering MySQL,” on page 60](#)
- ♦ [Section 14.2, “Installing and Enabling MySQL,” on page 60](#)
- ♦ [Section 14.3, “Creating an LVM Volume Group and Logical Volume,” on page 62](#)
- ♦ [Section 14.4, “Configuring MySQL on the LVM Logical Volume,” on page 68](#)
- ♦ [Section 14.5, “Cluster-Enabling MySQL on the Logical Volume,” on page 69](#)
- ♦ [Section 14.6, “File Location,” on page 72](#)
- ♦ [Section 14.7, “Security Considerations for the MySQL Configuration,” on page 73](#)
- ♦ [Section 14.8, “Additional Information,” on page 74](#)

14.1 Prerequisites for Clustering MySQL

The following setup is required for clustering the MySQL database files with Novell Cluster Services:

- ☐ Novell Cluster Services must be installed and configured as described in “[Installing and Configuring Novell Cluster Services on OES 11](#)” in the *OES 11: Novell Cluster Services 2.0 for Linux Administration Guide*.
- ☐ MySQL must be installed on every node in the cluster where you want MySQL to run. The installation is described in [Section 14.2, “Installing and Enabling MySQL,”](#) on page 60.
- ☐ The SAN device that you want to use for the MySQL database must be accessible to all nodes in the cluster. It will be activated on only one node at a time.
- ☐ You must create a shared Linux Logical Volume Management (LVM) volume group where you will store the MySQL database and configuration file. This setup is described in [Section 14.3, “Creating an LVM Volume Group and Logical Volume,”](#) on page 62.


14.2 Installing and Enabling MySQL

Before you configure MySQL with Novell Cluster Services, MySQL must be installed and configured properly on all servers in the cluster where you intend to run it. You can use the YaST Software Management tool to install the MySQL and the MySQL Client packages. Other MySQL packages are available that allow you to use MySQL with Perl, PHP, Postfix, or Python, but this guide does not cover their installation or use.

Package	Description
mysql	Provides the MySQL software and database.
mysql-client	Provides the MySQL client command line program that acts as a text-based front end for the MySQL Server. It's used for issuing queries and viewing the results interactively from a terminal window
mysql-Max	<p>Provides the MySQL software, database, and the following features for users that require transaction support:</p> <ul style="list-style-type: none">♦ Berkeley database (BDB) tables♦ InnoDB tables <p>These features provide transaction-safe tables to which locks are applied while a series of SQL queries is made. The series of queries is referred to as a transaction.</p>
perl-DBD-mysql	Provides a MySQL database driver (DBD) to support a database-independent interface (DBI) for the Perl programming language.
php5-mysql	Provides a PHP plug-in that allows an Apache HTTP server to access a MySQL database.
postfix-mysql	Provides a Postfix plug-in that allows a Postfix mail system to access a MySQL database.
python-mysql	Provides a Python plug-in that allows you to execute SQL queries on a MySQL database through your Python application.

Use the following procedure to install the `mysql` and `mysql-client` packages, and enable MySQL on each node in the cluster:

- 1 Log in to the server as the Linux `root` user, then open YaST.
- 2 Ensure that the SUSE Linux Enterprise Server 11 SP1 installation CD is mounted on the server.
- 3 In YaST, select *Software > Software Management*, then click the *Search* tab.
- 4 To find the components, type `mysql` in the *Search* field, then click *Search*.
- 5 In the *Package* list, select `mysql` and `mysql-client`.



- 6 Click *Accept*, then click *Continue* for each component to confirm that you want to install it.

YaST does the following:

- ♦ Installs the MySQL Server and MySQL Client software.
The software is not enabled by default, and the MySQL daemon is not running at this time. No run levels are set.
- ♦ Creates the MySQL root user (a user internal to the MySQL system) as a superuser that has access rights to perform any function in MySQL. Initially, this user has no password assigned.
- ♦ Creates a default path `/var/lib/mysql` for storing databases that you create later. Initially, this directory is empty. It is populated later when you enable the MySQL service.
- ♦ Creates the `mysql` user and group on the server and makes them the owners of the default data directory `/var/lib/mysql` and its contents.
- ♦ Creates a default mount point `/mnt/mysql` for the database. This is where you will mount the LVM logical volume that you create for the database in [Section 14.3, "Creating an LVM Volume Group and Logical Volume,"](#) on page 62.
- ♦ Creates the default MySQL configuration file (`/etc/my.cnf`).

- 7 In YaST, enable the MySQL service:


7a Select *System > System Services (Runlevel)*.

7b Select *Expert Mode*.

7c In the *Service* list, select the `mysql` daemon.

7d Click *Set/Reset > Enable the Service*.

Under *Service will be started in the following runlevels*, notice that the 2, 3, and 5 check boxes are selected by default. You don't want the service to start on system boot because it starts when the cluster resource is brought online on a cluster node.



7e In the lower right corner, click *OK*.

7f When you are prompted to confirm the changes, click *Yes* to save them.

7g Exit YaST.

8 Stop the MySQL daemon from running. In a terminal console, enter the following as the Linux root user:

```
/etc/init.d/mysql stop
```

Alternatively, you can use the `rcmysql stop` command.

9 Repeat [Step 1](#) through [Step 8](#) on each node in the cluster to install and enable MySQL.

10 After you have installed and enabled MySQL on all servers in the cluster, continue with [Section 14.3, "Creating an LVM Volume Group and Logical Volume,"](#) on page 62.

14.3 Creating an LVM Volume Group and Logical Volume

After you have installed MySQL, you are ready to set up the LVM volume group and logical volume where you will store a MySQL database. Sample values are used in the procedures in this section to help you understand what is required at each step. The overview provides only the Linux commands that you need to create and prepare the volume group for use by MySQL. The detailed description provides more information about the process, including the syntax and sample commands.

- [Section 14.3.1, "Sample Values,"](#) on page 63
- [Section 14.3.2, "Setting Up the VG and LV \(Overview\),"](#) on page 64
- [Section 14.3.3, "Setting up the VG and LV \(Detailed\),"](#) on page 64

14.3.1 Sample Values

The procedures in this section uses the following parameters. Ensure that you replace the sample values with your values. The first node in the cluster is where you configure MySQL and the cluster resource.

Parameter	Sample Value
LVM physical volume	<code>/dev/sdd</code>
LVM volume group name	<code>mysqlvg</code>
LVM logical volume	<code>msql1v</code>
File system type	<code>ext3</code> This is the file system type that you make on the LVM logical volume, such as <code>ext2</code> , <code>ext3</code> , <code>reiserfs</code> , or <code>xfs</code> .
Logical volume path	<code>/dev/mysqlvg/msql1v</code>
Mount point for the logical volume	<code>/mnt/mysql</code>
Default MySQL root path	<code>/var/lib/mysql</code>
New MySQL root path	<code>/mnt/mysql/var/lib/mysql</code>

14.3.2 Setting Up the VG and LV (Overview)

You can create the volume group and logical volume by issuing the following LVM commands as the *root* user on the cluster node. This overview of the process uses the sample values. Ensure that you substitute your own values in the commands. For details, see [Section 14.3.3, “Setting up the VG and LV \(Detailed\),” on page 64](#).

Command Action	Command
1. Create the LVM physical volume.	<code>pvccreate /dev/sdd</code>
2. Create the clustered LVM volume group.	<code>vgcreate -c y mysqlvg /dev/sdd</code>
3. Activate the volume group exclusively on the node.	<code>vgchange -a ey mysqlvg</code>
4. Create the LVM logical volume.	<code>lvcreate -n mysqllv -L size mysqlvg</code>
5. Add a file system to the LVM logical volume.	<code>mkfs -t ext3 /dev/mysqlvg/mysqllv [fs_options]</code>
6. Create a mount point for the logical volume.	<code>mkdir /mnt/mysql</code> You must also create this path on each node in the cluster.
7. Mount the LVM logical volume.	<code>mount -t ext3 /dev/mysqlvg/mysqllv /mnt/ mysql</code>
8. Create the directory structure for the MySQL database files on the mounted logical volume.	<code>cd /mnt/mysql mkdir /mnt/mysql/var mkdir /mnt/mysql/var/lib mkdir /mnt/mysql/var/lib/mysql</code>
9. Modify the file ownership of the mount point and subdirectories.	<code>chown -R mysql:mysql /mnt/mysql</code>
10. Deactivate the LVM logical volume.	<code>vgchange -a n mysqlvg</code>


14.3.3 Setting up the VG and LV (Detailed)

For detailed instructions, use the following procedure to create the LVM volume group and logical volume:

- 1 Log in as the Linux *root* user to the first node of the cluster, then open a terminal console.
- 2 In NSSMU, initialize the SAN device that you want to use for the MySQL database, but do not mark it as shareable for clustering:
 - 2a At the console prompt, launch NSSMU by entering:

```
nssmu
```
 - 2b Select *Devices*, then press Enter.
 - 2c In the *Devices* list, select the unpartitioned device that you want to use, then press F3 to initialize it.
 - 2d Read the advisory, then press Y to confirm that you want to initialize the device.
 - 2e Specify the Master Boot Record (MBR) type as DOS or GPT, then press Enter.
Typically, you use DOS format for devices up to 2 TB. You use GPT for devices greater than 2 TB.

- 2f Verify that the device is initialized and that it is unshared (that is, *Shareable for Clustering* is set to *No*).



The screenshot shows the NSS Management Utility (NSSMU) interface. It has a title bar 'NSS Management Utility' and a subtitle 'NSS Version 4.13a Build 0506'. The interface is divided into two main panels. The left panel, titled 'Devices', lists several devices: sda, sdb, sdc, *sdd (highlighted with a yellow background), sde, and cluster.sbd. The right panel, titled 'Device Information', displays details for the selected device 'sdd': Name: sdd, ID: 8:48, MBR type: DOS, RAID: No, LVM: No, Capacity: 512.00 MB, Partitioned Space: 16 KB, Unpartitioned Space: 511.98 MB, and Shareable for Clustering: No. At the bottom, a status bar shows keyboard shortcuts: F3=Init, F5=Refresh, F6=Share, ENTER=Show Partitions, and ESC=Prev Menu.

Devices	Device Information
sda	Name: sdd
sdb	ID: 8:48
sdc	MBR type: DOS
* sdd	RAID: No
sde	LVM: No
cluster.sbd	Capacity: 512.00 MB
	Partitioned Space: 16 KB
	Unpartitioned Space: 511.98 MB
	Shareable for Clustering: No

- 2g Exit NSSMU to return to the command prompt.
- 3 Create an LVM physical volume on the device (such as `/dev/sdd`) by entering:
- ```
pvccreate <device>
```
- For example:
- ```
pvccreate /dev/sdd
No physical volume label read from /dev/sdd
Physical volume "/dev/sdd" successfully created
```

- 4 Create an LVM volume group (such as `mysqlvg`) on the physical volume by entering:

```
vgcreate -c y <vg_name> <device>
```

For example:

```
vgcreate -c y "mysqlvg" /dev/sdd
Clustered volume group "mysqlvg" successfully created
```

The volume group is automatically activated.

- 5 Activate the volume group exclusively on the current server by entering:

```
vgchange -a ey <vg_name>
```

The `-a` option activates the volume. The `ey` parameter specifies the values exclusively and yes.

For example:

```
vgchange -a ey mysqlvg
```

- 6 View information about the volume group by using the `vgdisplay` command:

```
vgdisplay <vg_name>
```

Notice that 4 MB of the device are used for the volume group's Physical Extent (PE) table. You must consider this reduction in available space on the volume group when you specify the size of the LVM logical volume in the next step (Step 7).

For example:

```
vgdisplay mysqlvg
--- Volume group ---
VG Name                mysqlvg
System ID
Format                 lvm2
Metadata Areas         1
Metadata Sequence No   1
VG Access              read/write
VG Status              resizable
MAX LV                 0
Cur LV                0
Open LV               0
Max PV                0
Cur PV               1
Act PV               1
VG Size                508.00 MB
PE Size                4.00 MB
Total PE              127
Alloc PE / Size        0 / 0
Free PE / Size         127 / 508.00 MB
VG UUID                rgyAd3-U2dg-HYLw-0SyN-1oO7-jBH3-qHvySe
```

- 7** Create an LVM logical volume (such as `mysql1v`) on the volume group by entering:

```
lvcreate -n <lv_name> -L size <vg_name>
```

Specify the logical volume name, size, and the name of the volume group where you want to create it. The size is specified in megabytes by default.

The logical volume full path name is `/dev/<vg_name>/<lv_name>`.

For example:

```
lvcreate -n "mysql1v" -L 500 "mysqlvg"
Logical volume "mysql1v" created
```

This volume's full path name is `/dev/mysqlvg/mysql1v`.

- 8** View information about the logical volume by entering:

```
lvdisplay -v <lv_path_name>
```

For example:

```
lvdisplay -v /dev/mysqlvg/mysql1v
Using logical volume(s) on command line
--- Logical volume ---
LV Name                /dev/mysqlvg/mysql1v
VG Name                mysqlvg
LV UUID                nIfsMp-alRR-i4Lw-Wwdt-v5io-2hDN-qrWTLH
LV Write Access        read/write
LV Status              available
# open                 0
LV Size                500.00 MB
Current LE             125
Segments              1
Allocation             inherit
Read ahead sectors     auto
- currently set to     1024
Block device           253:1
```

- 9** Create a file system (such as Ext2, Ext3, ReiserFS, or XFS) on the LVM logical volume by entering:

```
mkfs -t <fs_type> <lv_path_name> [fs_options]
```

You can specify file system options according to the type of file system you are making. For information, see the `mkfs(8)` man page and the related man page for the file system type, such as `mkfs.ext2(8)`, `mkfs.ext3(8)`, `mkfs.reiserfs(8)`, or `mkfs.xfs(8)`.

For example:

```
mkfs -t ext3 /dev/mysqlvg/mysql1lv
mke2fs 1.41.9 (22-Aug-2009)
Filesystem label=
OS type: Linux
Block size=1024 (log=0)
Fragment size=1024 (log=0)
128016 inodes, 512000 blocks
25600 blocks (5.00%) reserved for the super user
First data block=1
Maximum filesystem blocks=67633152
63 block groups
8192 blocks per group, 8192 fragments per group
2032 inodes per group
Superblock backups stored on blocks:
    8193, 24577, 40961, 57345, 73729, 204801, 221185, 401409
Writing inode tables: done
Creating journal (8192 blocks): done
Writing superblocks and filesystem accounting information: done

This filesystem will be automatically checked every 29 mounts or
180 days, whichever comes first.  Use tune2fs -c or -i to override.
```

- 10 Create a mount point for the logical volume by entering:

```
mkdir /mnt/mysql
```

- 11 Mount the logical volume on the MySQL mount point by entering:

```
mount -t <fs_type> <lv_path_name> <mount_point>
```

For example:

```
mount -t ext3 /dev/mysqlvg/mysql1lv /mnt/mysql
```

- 12 Go to the mount point location (`/mnt/mysql`), then create the `/var/lib/mysql` subdirectory structure by entering:

```
cd /mnt/mysql
mkdir /mnt/mysql/var
mkdir /mnt/mysql/var/lib
mkdir /mnt/mysql/var/lib/mysql
```

- 13 Change the owner and group owner of the `/mnt/mysql` directory and its contents to use the `mysql` user and group. Enter the `chown` command with the recursive (`-R`) option:

```
cd /mnt
chown -R mysql:mysql mysql
```

Another way to do this is to explicitly specify the directory path:

```
chown -R mysql:mysql /mnt/mysql
```

- 14 Continue with [Section 14.4, “Configuring MySQL on the LVM Logical Volume,”](#) on page 68.

14.4 Configuring MySQL on the LVM Logical Volume

MySQL databases are usually located in a subdirectory of the `/var/lib/mysql/` directory. If you create a database named `test`, then the database files are located in the `/var/lib/mysql/test` directory.

In order for MySQL to take advantage of the benefits provided by Novell Cluster Services, you must make some configuration changes to MySQL. On the first server, you copy the default MySQL configuration file (`/etc/my.cnf`) to the LVM logical volume, modify `/mnt/mysql/var/lib/mysql/my.cnf` file so that all `datadir` entries are commented out, then create a MySQL database on the LVM Logical volume.

The following instructions assume that you have not created a database on the server at this time. If a MySQL database currently exists in the default `/var/lib/mysql` location, the database's directory and its contents must be relocated to the new `/mnt/mysql/var/lib/mysql` path, rather than creating it as described in [Step 6 on page 68](#) of the following procedure. Afterwards, ensure that you modify the ownership of the folder and files to the `mysql` user and group by using the `chown` command as illustrated in [Step 13 of Section 14.3, "Creating an LVM Volume Group and Logical Volume," on page 62](#).

IMPORTANT: After you have modified the MySQL configuration file to use the LVM logical volume path, you should always exclusively activate the volume group on the server before attempting to start the MySQL daemon. The cluster resource does this automatically in the load script.

To configure a MySQL database on the LVM logical volume:

- 1 Log in as the Linux `root` user on the first node, then open a file browser or terminal console.
- 2 Copy the default `/etc/my.cnf` configuration file to the `/mnt/mysql/var/lib/mysql` directory. Enter

```
cp /etc/my.cnf /mnt/mysql/var/lib/mysql
```

- 3 In a text editor, modify the `/mnt/mysql/var/lib/mysql/my.cnf` file and comment out any data directory entries, then save your changes.

```
# datadir=
```

- 4 Change the permissions on the `/mnt/mysql/var/lib/mysql/my.cnf` file to Read and Execute for each permission level, and change the ownership to the `mysql` user and group. Enter the following commands:

```
chmod 555 /mnt/mysql/var/lib/mysql/my.cnf
chown mysql:mysql /mnt/mysql/var/lib/mysql/my.cnf
```

You can view these settings by using the `ll <filepath>` command. For example:

```
ll /mnt/mysql/var/lib/mysql/my.cnf
-r-xr-xr-x 1 mysql mysql 6297 2011-07-08 14:19 /mnt/mysql/var/lib/mysql/
my.cnf
```

- 5 Open a terminal console as the Linux `root` user, then start MySQL:

```
/etc/init.d/mysql start
```

Another option is to use the `rcmysql start` command.

- 6 Create a database named `data` on the LVM logical volume:

```
mysql_install_db --datadir=/mnt/mysql/var/lib/mysql/data --user=mysql
```

- 7 Set the ownership of the data database to be the `mysql` user and group:

```
chown -R mysql:mysql /mnt/mysql/var/lib/mysql/data
```

- 8 Stop the MySQL daemon from running:

```
/etc/init.d/mysql stop
```

Another option is to use the `rcmysql stop` command.

- 9 Deactivate the LVM volume group:

```
vgchange -a n <vg_name>
```

For example:

```
vgchange -a n mysqlvg
```

- 10 Continue with [Section 14.5, “Cluster-Enabling MySQL on the Logical Volume,”](#) on page 69.

14.5 Cluster-Enabling MySQL on the Logical Volume

Now that you have configured MySQL for the LVM logical volume, you are ready to cluster-enable MySQL. In iManager, you use the Novell Cluster Services MySQL template to create a cluster resource for the LVM volume group that contains the MySQL database. The resource’s load script starts the MySQL daemon when the resource is brought online, and the unload script stops it when the resource is taken offline.

The sample scripts in this section use the following sample parameters. Ensure that you replace the sample values with your values.

Parameter	Sample Value
Resource IP Address	10.10.10.44
MOUNT_FS	ext3 This is the file system you created on the LVM volume group, such as ext2, ext3, reiserfs, or xfs.
VOLGROUP_NAME	mysqlvg
MOUNT_DEV	/dev/\$VOLGROUP_NAME/mysql1lv
MOUNT_POINT	/mnt/mysql
MySQL_ROOT	\$MOUNT_POINT/var/lib/mysql

Use the following procedure to create the MySQL cluster resource for the LVM volume group:

- 1 In iManager, select *Clusters > Cluster Options*, then browse to select the cluster.
- 2 Under the *Cluster Objects* title, click *New*.
- 3 On the *New Resource > Resource Type* page, specify *Resource* as the type, then click *Next*.

- 4 On the *New Resource > Cluster Resource Information* page, specify a cluster resource name, browse to select the *MySQL_Template*, then click *Next*.

Do not select *Online Resource after Create*. You must configure the resource scripts and settings before bringing the resource online.

The screenshot shows the 'New Resource' window in the NetWare console. The left pane lists various roles and tasks, with 'Cluster Options' highlighted. The main pane is titled 'New Resource' and 'Cluster Resource Information'. It contains the following fields and options:

- Cluster Resource Name:** mysqlv
- Inherit From Template:** MySQL_Template.cluster.ncs.r
- ☐ Online Resource after Create
- ☒ Define Additional Properties

At the bottom, there are three buttons: '<< Back', 'Next >>', and 'Cancel'.

- 5 On the *Load Script* page, modify the definition fields for your MySQL resource, file system type, volume group name, logical volume name, and mount point, then click *Next*.

The following load script uses the sample values from the MySQL setup:

```
#!/bin/bash
. /opt/novell/ncs/lib/ncsfuns

# define the IP address
RESOURCE_IP=10.10.10.44
# define the file system type
MOUNT_FS=ext3
# define the volume group name
VOLGROUP_NAME=mysqlvg
# define the device
MOUNT_DEV=/dev/$VOLGROUP_NAME/mysql1v
# define the mount point
MOUNT_POINT=/mnt/mysql

# define MySQL database root
MYSQL_ROOT=$MOUNT_POINT/var/lib/mysql

# activate the volume group
exit_on_error vgchange -a ey $VOLGROUP_NAME

# mount the file system
exit_on_error mount_fs $MOUNT_DEV $MOUNT_POINT $MOUNT_FS

# add the IP address
exit_on_error add_secondary_ipaddress $RESOURCE_IP

# start MySQL
/usr/bin/mysqld_safe --user=mysql --pid-file=$MYSQL_ROOT/mysql.pid --
socket=$MYSQL_ROOT/mysql.sock --datadir=$MYSQL_ROOT --bind-
address=$RESOURCE_IP &>/dev/null &

# return status
exit 0
```

- 6** On the Unload Script page, modify the definition fields for your MySQL resource, file system type, volume group name, logical volume name, and mount point, then click *Next*.

The following unload script uses the sample values from the MySQL setup:

```
#!/bin/bash
. /opt/novell/ncs/lib/ncsfuns

# define the IP address
RESOURCE_IP=10.10.10.44
# define the file system type
MOUNT_FS=ext3
# define the volume group name
VOLGROUP_NAME=mysqlvg
# define the device
MOUNT_DEV=/dev/$VOLGROUP_NAME/mysql1v
# define the mount point
MOUNT_POINT=/mnt/mysql

# define MySQL database root
MYSQL_ROOT=$MOUNT_POINT/var/lib/mysql

# request MySQL stop
ignore_error killproc -p $MYSQL_ROOT/mysql.pid -TERM /usr/sbin/mysqld

# del the IP address
ignore_error del_secondary_ipaddress $RESOURCE_IP

# umount the file system
sleep 10 # if not using SMS for backup, please comment out this line
exit_on_error umount_fs $MOUNT_DEV $MOUNT_POINT $MOUNT_FS

# deactivate the volume group
exit_on_error vgchange -a n $VOLGROUP_NAME

# return status
exit 0
```

- 7** On the Monitoring Script page, modify the definition fields for your MySQL resource, file system type, volume group name, logical volume name, and mount point, then click *Next*.

The following monitoring script uses the sample values from the MySQL setup:

```
#!/bin/bash
. /opt/novell/ncs/lib/ncsfuns

# define the IP address
RESOURCE_IP=10.10.10.44
# define the file system type
MOUNT_FS=ext3
# define the volume group name
VOLGROUP_NAME=mysqlvg
# define the device
MOUNT_DEV=/dev/$VOLGROUP_NAME/mysql1v
# define the mount point
MOUNT_POINT=/mnt/mysql

# define MySQL database root
MYSQL_ROOT=$MOUNT_POINT/var/lib/mysql

# check the logical volume
```

```

exit_on_error status_lv $MOUNT_DEV

# check the file system
exit_on_error status_fs $MOUNT_DEV $MOUNT_POINT $MOUNT_FS

# check the IP address
exit_on_error add_secondary_ipaddress $RESOURCE_IP

# check MySQL
exit_on_error checkproc -p $MySQL_ROOT/mysql.pid /usr/sbin/mysqld

# return status
exit 0

```



- 8 On the Resource Policies page, specify the *Resource Behavior*, *Start Mode*, *Failover Mode*, and *Failback Mode*, then click *Next*.

For information about completing these fields, see “[Configuring the Start, Failover, and Failback Modes for Cluster Resources](#)” in the *OES 11: Novell Cluster Services 2.0 for Linux Administration Guide*.

- 9 On the Resource Preferred Nodes page, assign the nodes where MySQL is installed, then click *Finish*.

The resource appears in the Cluster Objects list:

- 10 Bring the MySQL resource online. Select *Clusters > Cluster Manager*, select the MySQL resource check box, then click *Online*.

		mysqliv		Running	avalon	2	Jul 8, 2011 5:32:48 PM
---	---	---------	---	---------	--------	---	------------------------

If the resource goes comatose, offline the resource, then open its properties page and re-verify the scripts.

14.6 File Location

During the MySQL installation, the following files are unpackd or created by YaST:

MySQL Component	Default Location in OES
MySQL daemon for start, stop, and restart commands	/etc/init.d/mysql
Configuration files	/etc/my.cnf /etc/mysqlaccess.conf
Database files	/var/lib/mysql
Man pages	/usr/share/man/man1
Documentation (<i>MySQL Readme</i>)	/usr/share/doc/packages/mysql
Log file	/var/lib/mysql/mysqld.log The MySQL log file can also be accessed via a hard link from /var/log/mysqld.log.

MySQL Component	Default Location in OES
Software	<p>Some of the software components might not appear in this location until after you enable the service.</p> <pre> /usr/bin/mysql /usr/bin/mysqladmin /usr/bin/mysqlbinlog /usr/bin/mysqlbug /usr/bin/mysqlcheck /usr/bin/mysqld_multi /usr/bin/mysqld_safe /usr/bin/mysqldump /usr/bin/mysqldumpslow /usr/bin/mysql_fix_extensions /usr/bin/mysql_fix_privilege_tables /usr/bin/mysqlimport /usr/bin/mysql_install_db /usr/bin/mysql_secure_installation /usr/bin/mysqlshow /usr/bin/mysqlupgrade /usr/bin/my_print_defaults /usr/bin/myisamcheck /usr/bin/myisam_ftdump /usr/bin/myisamlog /usr/bin/myisampack </pre>

14.7 Security Considerations for the MySQL Configuration

Consider the security measures in this section when working with MySQL.

- ♦ [Section 14.7.1, “MySQL Ports,” on page 73](#)
- ♦ [Section 14.7.2, “Securing MySQL,” on page 73](#)

14.7.1 MySQL Ports

MySQL uses port 3306 by default. Additional ports are assigned sequentially as 3307, 3308, and so on. These ports must be open in the firewall in order to allow remote access to the MySQL database.

14.7.2 Securing MySQL

The default installation of MySQL provides some configuration settings, an anonymous user, and the `test` database that can possibly compromise security in a production environment:

- ♦ The root user can connect from the local host or remotely.
- ♦ An anonymous user is also created and can connect from the local host or remotely.
- ♦ Any local user on the server can connect to the `test` database without a password and be treated as the anonymous user.
- ♦ The anonymous user can perform any function on any databases named `test` or with a name that begins with `test_`.

For production servers, we recommend that you secure your MySQL service by setting a password for the MySQL root user. This is a password for the MySQL administrator user, that is, a root user within the MySQL system. It is not the Linux root user.

- 1 To set the password and log in to MySQL on the server, enter the following commands:

```
/usr/bin/mysqladmin -u root password <new_password>
```

```
/usr/bin/mysqladmin -u root -h <server_fdn_name> password <new_password>
```

For example:

```
/usr/bin/mysqladmin -u root password novell
```

```
/usr/bin/mysqladmin -u root -h myserver1.europe.example.com password novell
```

Alternatively, you can run the `mysql_secure_installation` command as the Linux root user, complete the fields that make sense for your MySQL configuration, then use:

```
/usr/bin/mysql_secure_installation
```

We recommend that you configure the following secure settings:

- ♦ Set a password for the MySQL root user.
- ♦ Remove MySQL anonymous users.
- ♦ Disallow remote login for the MySQL root user.

The MySQL root user is allowed to connect to the database, but only from the local host.

- ♦ Remove the `test` database.
- ♦ Reload the Privileges table.

14.8 Additional Information

The following resources are available to help you manage and use MySQL:

- ♦ *MySQL 5.0 Reference Manual* (<http://dev.mysql.com/doc/refman/5.0/en/>) from the [MySQL Documentation Library](http://dev.mysql.com/doc/) (<http://dev.mysql.com/doc/>)
- ♦ After you have installed MySQL and the MySQL client on the server, the following man pages are available for MySQL utilities by entering the `man <mysql_utility>` command:

- ♦ `mysql(1)`
- ♦ `mysqladmin(1)`
- ♦ `mysqlbinlog(1)`
- ♦ `mysqlbug(1)`
- ♦ `mysqlcheck(1)`
- ♦ `mysqld_multi(1)`
- ♦ `mysqld_safe(1)`
- ♦ `mysqldump(1)`
- ♦ `mysql_fix_extensions(1)`
- ♦ `mysql_fix_privilege_tables(1)`
- ♦ `mysqlimport(1)`
- ♦ `mysql_install_db(1)`
- ♦ `mysqlsecure_installation(1)`
- ♦ `mysqlshow(1)`
- ♦ `mysqlupgrade(1)`

15 QuickFinder Server

In a Novell Cluster Services cluster, you must install QuickFinder on each node in the cluster. This registers QuickFinder Server with each of the Web servers and application servers running on each server. On OES 11, QuickFinder is installed by default in the `/var/lib/qfsearch` directory. We recommend that you use the default path. After the installation, you must set up one or more virtual search servers to enable QuickFinder Server to work in a cluster.

When the Linux setup is completed, you are ready to manually migrate settings from the NetWare cluster to the Linux cluster. Set up QuickFinder on the OES 11 cluster nodes, then manually migrate QuickFinder data from a NetWare node to an OES 11 node.

For information about using the QuickFinder Server Manager and other procedures for QuickFinder, see the *OES 11: Novell QuickFinder Server 5.0 Administration Guide*.

- ♦ [Section 15.1, “Prerequisites,” on page 75](#)
- ♦ [Section 15.2, “Setting Up QuickFinder Server on Linux Cluster Nodes,” on page 75](#)
- ♦ [Section 15.3, “Migrating QuickFinder Data from NetWare to Linux,” on page 76](#)
- ♦ [Section 15.4, “Post-Migration Considerations,” on page 77](#)
- ♦ [Section 15.5, “Searching the Cluster Volume,” on page 78](#)

15.1 Prerequisites

Before you begin:

- 1 On one Linux node, create a Linux POSIX cluster resource where all of the indexes and virtual search server settings are to be stored.

For information, see [“Configuring and Managing Cluster Resources for LVM Volume Groups”](#) in the *OES 11: Novell Cluster Services 2.0 for Linux Administration Guide*.

15.2 Setting Up QuickFinder Server on Linux Cluster Nodes

On each OES 11 node, do the following to set up QuickFinder for Linux:

- 1 Cluster migrate the Linux POSIX cluster resource to the OES 11 node where you want to install QuickFinder
- 2 Install QuickFinder on the active cluster node.

- 3 Create a virtual search server to enable QuickFinder Server to work in a cluster.
Give each virtual search server the same name and location. After the first server is set up, any settings that you create on the shared volume are automatically displayed.
 - 3a On the active cluster node, open the QuickFinder Server Manager.
 - 3b Click *Global Settings*, then click *Add New Virtual Server*.
 - 3c In *Name*, specify the DNS name of the cluster.
 - 3d In *Location*, specify the Linux path on the Linux POSIX cluster resource where all of the indexes and virtual search server settings will be located.
 - 3e Click *Add*.
- 4 Repeat [Step 1](#) to [Step 3](#) for each of the nodes in the cluster.

15.3 Migrating QuickFinder Data from NetWare to Linux

Use the following steps to migrate QuickFinder Server data from a NetWare server to a corresponding Linux server. You must repeat the tasks for each NetWare server in the cluster. It assumes a one-to-one server replacement in the cluster.

WARNING: Migrating indexes and virtual search server settings from a QuickFinder Server running on NetWare to QuickFinder Server running on OES 11 replaces the existing settings on the Linux server. If you want to merge your NetWare settings with the existing Linux settings, you must manually re-create the NetWare settings by using the QuickFinder Server Manager.

- 1 Open a Web browser, then access the QuickFinder Server Manager on the NetWare server.
`http://servername/qfsearch/admin`
- 2 Click *Global Settings* in the top toolbar.
- 3 Write down the paths for each virtual search server displayed in the *Location* column.
- 4 On the OES 11 server where the shared volume is active, mount the NetWare server by using the `ncpmount` command.
- 5 Make a backup of the `/var/lib/qfsearch/SiteList.properties` file.
Ensure that you don't have a file with this name as a backup on the NetWare server.
- 6 Copy all `.properties` and `Cron.jobs` files from the root folder `sys:/qfsearch` on the NetWare server to `/var/lib/qfsearch` on the Linux server.
- 7 Copy `sys:/qfsearch/Sites` and all of its subdirectories to `/var/lib/qfsearch/Sites`.
- 8 Copy `sys:/qfsearch/Templates` and all of its subdirectories to `/var/lib/qfsearch/Templates`.
- 9 If any of the paths listed in [Step 3](#) are not under `sys:/qfsearch` (for example, if you installed a virtual search server somewhere other than the default location), you must also copy those paths to Linux.

For example, if you have the path `sys:/SearchSites/PartnerSite`, you must copy it to the Linux server. You could copy it to `/var/opt/SearchSites/PartnerSite` or `/var/lib/qfsearch/Sites/PartnerSite`.

- 10 Edit all NetWare paths in `/var/lib/qfsearch/SiteList.properties` to reflect the new Linux paths.

For example, change `sys:/qfsearch` to `/var/lib/qfsearch`.

Or, as in the example in [Step 9](#), change `sys:/SearchSites/PartnerSite` to `/var/opt/SearchSites/PartnerSite`.

Some paths might have one or two backslashes (`\`) that must be replaced with one forward slash (`/`). For example, `sys:\\qfsearch\\docs` needs to be changed to `/var/lib/qfsearch/docs`.

- 11 Update all NetWare paths in the properties and configuration files copied in the steps above to the Linux paths, and update any DNS names.

The following files must be updated:

```
AdminServlet.properties
Cron.jobs
Sites/Highlighter.properties
Sites/Print.properties
Sites/Search.properties
```

For each of the virtual search servers, modify the following:

- ♦ `qfind.cfg`
- ♦ Any of the above `.properties` files, if they exist.

IMPORTANT: Linux file names are case sensitive.

The names of most properties files are mixed case, so ensure that the files copied from NetWare are the correct case. You can compare them to the `.properties.sample` files on Linux.

You might also need to update paths in templates. If you have problems such as a template not being found or some properties not being set properly, check the case of the file name.

If you modified any “file” index paths to index directories on the Linux server, that index must be regenerated.

- 12 After all the files have been modified, run the following commands to set the access rights and the owner and groups so that the QuickFinder engine has rights to access the files.

As the root user, enter

```
chown -R root:www /var/lib/qfsearch
chmod -R 770 /var/lib/qfsearch
```

- 13 Repeat [Step 1](#) to [Step 12](#) for each NetWare and Linux pair of nodes.

15.4 Post-Migration Considerations

QuickFinder Server 5.0 indexes are not compatible with previous versions of QuickFinder Server. The indexes must be regenerated, and you cannot synchronize QuickFinder Server 5.0 indexes with indexes from a previous version of QuickFinder Server (and vice-versa).

15.5 Searching the Cluster Volume

To perform a search on the shared volume after the NetWare migration is complete:

- 1 Open a Web browser, then enter

`http://DNS_CLUSTER/qfsearch/search`

QuickFinder Server sees the DNS and sends the request to the appropriate virtual search server.

16 Novell Storage Services Pools

Consider the guidelines in this section when converting Novell Storage Services (NSS) pool cluster resources from NetWare to Novell Open Enterprise Server (OES) 11.

- ♦ [Section 16.1, “NSS Pool Cluster Migration,” on page 79](#)
- ♦ [Section 16.2, “NSS File System Migration to NCP Volumes or Linux POSIX File Systems,” on page 79](#)
- ♦ [Section 16.3, “Estimated Time Taken to Build the Trustee File on Linux,” on page 79](#)

16.1 NSS Pool Cluster Migration

In the mixed-node cluster, NSS pool cluster resources created on NetWare can be failed over or cluster migrated to nodes that are running OES 11 where NSS is installed and running.

For information about NSS differences in OES 11, see “[NSS Pools](#)” in the *OES 11: Novell Cluster Services 2.0 for Linux Administration Guide*.

Some NSS features are not available or work differently on Linux. For information, see “[Cross-Platform Issues for NSS](#)” in the *OES 11: NSS File System Administration Guide for Linux*.

Pool snapshots use different technologies on NetWare and Linux. Pool snapshots are not supported for shared pools on Linux.

IMPORTANT: Ensure that you delete pool snapshots for all clustered pools before you begin the cluster conversion.

16.2 NSS File System Migration to NCP Volumes or Linux POSIX File Systems

To move data from NSS file systems on NetWare to NCP volumes or to Linux POSIX file systems on Linux, you must use the Migration tool. For information, see “[Migrating File Systems to OES 11](#)” in the *OES 11: Migration Tool Administration Guide*.

16.3 Estimated Time Taken to Build the Trustee File on Linux

On Linux, NCP Server stores file system trustees and rights information in the `._NetWare/.trustee_database.xml` file at the root of each NSS volume or NCP volume. The NSS file system also stores this information in its file system metadata as it does on NetWare. This database file is updated when you:

- ♦ Add file system trustees and rights

- ♦ Delete file system trustees and rights
- ♦ Modify file system trustees and rights

When you migrate an NSS volume from NetWare to Linux, the trustee database file does not exist. NCP Server reads the trustee and rights information from the NSS file system metadata, validates the User object, and stores the settings in a `._NetWare/.trustee_database.xml` file at the root of the volume. The information collection process begins automatically when the NSS volume is mounted on the OES 11 server.

Testing found that building the initial database on Linux for an existing volume takes about one minute per 50,000 storage objects. Testing was done on the following configuration for the target server:

HP DL380 G5

2 Quadcore Intel Xeon CPU E5345 @ 2.33 GHz

12 GB RAM

1 Gigabit NIC

2 HBAs with 4 paths to the EMC DMX Symmetrix Storage with 4 gigabits per second (Gbps) bandwidth

To follow the synchronization between the file system and the trustee file, look for output in the `/var/opt/novell/log/ncp2nss.log` file.

A Documentation Updates

This section contains information about documentation content changes made to information in the *Novell Cluster Services NetWare to Linux Conversion Guide* since the initial release for Novell Open Enterprise Server 11.

This document was updated on the following dates:

- ♦ [Section A.1, “April 30, 2012,” on page 81](#)
- ♦ [Section A.2, “January 31, 2012,” on page 82](#)

A.1 April 30, 2012

Updates were made to the following sections. The changes are explained below.

- ♦ [Section A.1.1, “Novell Storage Services Pools,” on page 81](#)
- ♦ [Section A.1.2, “Planning the Conversion of Load and Unload Scripts,” on page 81](#)

A.1.1 Novell Storage Services Pools

Location	Change
Section 16.3, “Estimated Time Taken to Build the Trustee File on Linux,” on page 79	To follow the synchronization between the file system and the trustee file, look for output in the <code>/var/opt/novell/log/ncp2nss.log</code> file.

A.1.2 Planning the Conversion of Load and Unload Scripts

Location	Change
Section 3.4, “Comparing Master IP Address Scripts,” on page 21	You can modify the Master IP Address only after the cluster conversion is finalized.

A.2 January 31, 2012

Updates were made to the following section. The changes are explained below.

- ♦ [Section A.2.1, “Converting NetWare 6.5 Clusters to OES 11,” on page 82](#)
- ♦ [Section A.2.2, “Planning the Cluster Conversion,” on page 82](#)

A.2.1 Converting NetWare 6.5 Clusters to OES 11

Location	Change
Section 4.1, “Converting NetWare Cluster Nodes to OES 11 (Rolling Cluster Conversion),” on page 27	In Step 9m on page 29 , corrected text to read “SLES 11 patch channel”.
Section 4.4, “Finalizing the Cluster Conversion,” on page 33	During the final conversion of the cluster from NetWare 6.5 SP8 to OES 11, all of the scripts for the NetWare nodes are deleted and are no longer available.

A.2.2 Planning the Cluster Conversion

Location	Change
Section 1.1, “Supported Conversion Paths,” on page 10	The NetWare to Linux conversion is supported from NetWare 6.5 SP8 (with the latest patches applied) to OES 11 on the SUSE Linux Enterprise Server (SLES) 11 SP1 operating system.
Section 1.2, “Supported Mixed-Node Clusters,” on page 10	A mixed-node cluster made up of NetWare 6.5 SP7 or earlier nodes and OES 11 nodes is not supported.